
# **HEALPix** IDL Facilities Overview



Revision: Version 3.83; November 13, 2024

Prepared by: Eric Hivon, Anthony J. Banday, Benjamin D. Wan-

delt, Frode K. Hansen and Krzysztof M. Góorski

Abstract: This document is an overview of the **HEALPix** IDL

facilities.

https://healpix.sourceforge.io http://healpix.sf.net

# TABLE OF CONTENTS

Using the <b>HEALPix</b> -IDL facilities
Using <b>HEALPix</b> -IDL together with other IDL libraries
Using GDL or FL instead of IDL
What is available?
Maps related tools
Pixels related tools
Power spectrum, alm, beam and pixel window functions
Other tools
Changes in release 3.83
Previous changes
alm_i2t 13
alm_t2i 15
alm2fits
ang2vec
angulardistance
azeqview
beam2bl
bin_llcl
bl2beam
bl2fits
cartcursor
cartview
change_polcconv
cl2fits
convert_oldhpx2cmbfast
euler_matrix_new
fits2alm
fits2cl
gaussbeam
getdisc_ring
getsize_fits
gnomeursor

gnomview
healpix_doc: PDF, HTML and EPUB documentation
healpixwindow
help_st
hpx2dm
hpx2gs
ialteralm
ianafast
index2lm
init_healpix and !healpix system variable
iprocess_mask
ismoothing
isynfast
lm2index
median_filter
mollcursor
mollview
neighbours_nest
neighbours_ring
nest2uniq
npix2nside
nside2npix
nside2npweights
nside2ntemplates
orthcursor
orthview
outline_earth
pix2xxx, ang2xxx, vec2xxx, nest2ring, ring2nest
planck_colors
query_disc
query_polygon
query_strip
query_triangle
read fits out4

read_fits_map
read_fits_partial
read_fits_s
read_tqu 170
remove_dipole
reorder
rotate_coord
$same\_shape\_pixels\_nest \& same\_shape\_pixels\_ring$
template_pixel_nest & template_pixel_ring
ud_grade
unfold_weights
uniq2nest
vec2ang
write_fits_cut4
write_fits_map
write_fits_partial
write_fits_sb
write ton

### Using the HEALPix-IDL facilities

The current version of the **HEALPix** package provides an IDL startup file which defines various environment variables for your convenience, and adds the **HEALPix** IDL directory tree to your IDL\_PATH. In order to utilise this feature, the user should invoke IDL using the commands hidl or hidlde which are aliases defined in the **HEALPix** profile created during the installation process for the package (see the Installation Document).

#### Using HEALPix-IDL together with other IDL libraries

Many users want to use **HEALPix**-IDL routines at the same time as other (home made or third party<sup>1</sup>) IDL routines. There are several ways to achieve this:

#### - with hidl:

before starting hidl or hidlde, (re)define the environment variable \$IDL\_PATH so that it looks like: "+/path/to/my/idl/routines:+/path/to/other/idl/routines:<IDL\_DEFAULT>" (where <IDL\_DEFAULT> should be typed literally and the +/path means that subdirectories of path will be searched recursively). For example, if young Albert types in Bourne shell: export IDL\_PATH="+/home/aeinstein/brownian:<IDL\_DEFAULT>" hidl

he will start an IDL session in which the **HEALPix-IDL** routines are accessible, followed by all those located in subdirectories of /home/aeinstein/brownian, followed by the standard IDL routines. If .pro files of the same name are avaible at the different locations, the first one encountered will prevail;

#### - without hidl:

before starting IDL, the environment variables \$IDL\_PATH and \$IDL\_STARTUP must be defined. For instance, to emulate under (ba)sh the behavior of hidl shown above, the same (bolder) Albert will type:

export IDL\_PATH="+\${HEALPIX}/src/idl:+/home/aeinstein/brownian:<IDL\_DEFAULT>"
export IDL\_STARTUP="+\${HEALPIX}/src/idl/HEALPix\_startup"
idl

FL users will do exactly the same thing, replacing hidl with hfl and idl with f164\_cmd (or f132 cmd).

As for GDL users, they will replace hid1, IDL\_PATH and IDL\_STARTUP above with hgd1, GDL\_PATH and GDL\_STARTUP respectively, while <IDL\_DEFAULT> must be replaced by the default value of \${GDL PATH}.

Of course, \${HEALPIX}/src/idl (and all the + signs) remain unchanged.

<sup>&</sup>lt;sup>1</sup> An extensive list of third party IDL libraries can be found at https://idlastro.gsfc.nasa.gov/other\_url.html. Among them, we recommend the IDL Astronomy Users library (https://idlastro.gsfc.nasa.gov) maintained by Wayne Landsman and which is extensively used in **HEALPix**-IDL, David Fanning's IDL Coyote library (http://www.idlcoyote.com) from which some routines are used in **HEALPix**-IDL, and Craig Markwardt's IDL library (https://cow.physics.wisc.edu/~craigm/idl/idl.html).

### Using GDL or FL instead of IDL

See the sections "Using GDL instead of IDL" or "Using FL instead of IDL" in the Installation Document for more information on these topics.

### What is available?

The **HEALPix**-IDL tools are mostly designed to generate, visualize, filter and analyze sky maps; identify, query and process **HEALPix** pixels; and deal with angular spectral objects (such as power spectra or Spherical Harmonics coefficients), as detailed below. The full documentation is available online in IDL via healpix doc

#### **HEALPix** maps related tools

- Visualization: gnomic, Mollweide, Cartesian, orthographic and azimuthal equatorial projections mollview, gnomview, cartview, orthview, azeqview (with interactive cursor: cartcursor, mollcursor, gnomcursor, orthcursor)
- Production of outlines for Earth continents, coastlines, countries and rivers outline\_earth
- Color table creation: planck colors
- Production of HEALPix maps in Google Sky and Dome Master format: hpx2gs, hpx2dm.
- Spherical Harmonics analysis and synthesis: ianafast, isynfast.
- Smoothing and filtering: ismoothing, median\_filter, remove\_dipole.
- Handling of quadrature weights: nside2npweights, unfold weights.
- Pixel pro/down-grading and NESTED/RING pixel reordering: ud grade, reorder.
- Mask processing: iprocess mask
- Maps I/O: read\_fits\_cut4, read\_fits\_map, read\_fits\_partial, read\_fits\_s, read\_tqu.
   write\_fits\_cut4, write\_fits\_map, write\_fits\_partial, write\_fits\_sb, write\_tqu.
   getsize fits, change polcconv

Pixels related tools 7

### HEALPix pixels related tools

• Coordinate tools: ang2vec, angulardistance, euler\_matrix\_new, rotate\_coord, vec2ang

- Coordinates to pixel transforms, and back: nside2npix, npix2nside, ang2pix\_\*, pix2ang\_\*, pix2vec\_\*, vec2pix\_\*
- RING/NESTED transforms: nest2ring, ring2nest
- Unique Identifier to NESTED index, and back: uniq2nest, nest2uniq
- Neighbouring pixels: neighbours nest, neighbours ring
- Pixel query within a disc, polygon, strip or triangle: query\_disc, query\_polygon, query\_strip, query\_triangle.
- Template pixels: nside2ntemplates, same\_shape\_pixels\_ring, same\_shape\_pixels\_nest, template\_pixel\_ring, template\_pixel\_nest

### Power spectrum, $a_{\ell m}$ , beam and pixel window functions

- $B(\ell)$ ,  $B(\theta)$  and pixel WF generation: gaussbeam, beam2bl, bl2beam, healpixwindow
- $C(\ell)$  binning: bin 11cl
- $a_{\ell m}$  handling tools: alm\_i2t, alm\_t2i, index2lm, lm2index, ialteralm
- $C(\ell)$ ,  $B(\ell)$  and  $a_{\ell m}$  I/O: fits2cl/cl2fits, bl2fits, fits2alm/alm2fits,

#### Other tools

- HEALPix variables and paths initialization: init healpix
- online documentation: healpix\_doc
- recursive help on IDL sub-structures: help st

### Changes in release 3.83

- bug corrections in read fits map and read tqu
- update of the required IDL-astron library routines, and Coyote library routines (2022-07-27).

### Previous changes

#### Changes between release 3.70 and 3.80

- Improvement to the query\_disc routine in inclusive mode;
- update of the required IDL-astron library routines, and Coyote library routines (2021-04-08).

#### Changes between release 3.60 and 3.70

Addition of read\_fits\_partial and write\_fits\_partial to read and write FITS files containing polarized or unpolarized maps defined on a fraction of the sky.

#### Changes between release 3.50 and 3.60

- addition of outline\_earth to create a structure outlining Earth features such as coastlines, rivers, country boundaries,
- azeqview, cartview, gnomview, mollview, orthview visualization routines: support for color and thickness in outline keyword
- Update of the required IDL-astron library routines, and Coyote library routines (2019-10-30).

#### Changes between releases 3.40 and 3.50

- fits2cl: addition of /PLANCK3 keyword to read the fiducial Λ-CDM C(ℓ) model which best fits the 2018 Planck data analysis (available from Healpix/data/planck2018\_lcdm\_cl\_v3.fits);
- rotate\_coord: addition of optional variable Delta\_Psi containing rotation of polarization on output, and of keyword
   Free\_Norm to deal with un-normalized input coordinate vectors

#### Changes between releases 3.31 and 3.40

- The routines ianafast and ismoothing can now use pixel-based quadrature weights. Addition of the supporting functions nside2npweights and unfold\_weights.
- ianafast and ismoothing: test the value of the POLCCONV FITS keyword when reading a polarized map, and interpret the polarization accordingly, as described in the note on POLCCONV in The HEALPix Primer.
- change\_polcconv has been improved to allow the change of polarization convention (by changing the sign of *U* Stokes parameter and updating POLCCONV value) in FITS files containing polarized maps generated by standard **HEALPix** tools, as well as for specific formats brewed by the WMAP and Planck projects throughout the years. An equivalent python facility change\_polcconv.py is now available as well.
- New help\_st to get information on a structure and its sub-structures
- azeqview, cartview, gnomview, mollview, orthview visualization routines:
  - addition of the keywords CUSTOMIZE and DEFAULT\_SETTINGS for extensize customization of the figures produced
  - GLSIZE and IGLSIZE can now be 2-element vectors to control separately the size (and presence) of labels on the parallel and meridian graticules
  - fine control of polarisation rods thickness with POLARIZATION
  - addition of the SILHOUETTE keyword to add a tunable silhouette around the projected map (mollview and orthview only)
- $\bullet~$  Improved support for GDL and FL (Fawlty Language).
- Update of the required IDL-astron library routines, and Coyote library routines (2018-05-15).

Previous changes 9

#### Changes between releases 3.30 and 3.31

- Improved support for GDL;
- update of the required IDL-astron library routines, and Coyote library routines (2016-08-19).

#### Changes between releases 3.20 and 3.30

- azeqview, cartview, gnomview, mollview, orthview visualization routines:
  - addition of PDF keyword for production of Adobe PDF outputs;
  - addition of LATEX keyword for genuine or emulated LATEX processing of character strings;
  - addition of PFONTS keyword to select origin and type of character font;
  - the CROP keyword now has the same behavior for all output media (GIF, JPEG, PDF, PNG, PS, ... and X); the NOBAR keyword now removes the color bar or the polarization color wheel, as applicable; correct EQUINOX date in header of output FITS map; the double precision maps and those with constant value are now correctly handled.
- fits2cl: addition of /PLANCK2 keyword to read best fit  $C(\ell)$  model to Planck 2015 data.
- new routines nest2uniq and uniq2nest for conversion of standard pixel index to/from Unique ID number. See "The Unique Identifier scheme" section in "HEALPix Introduction Document" for more details.
- HEALPix enabled GDL commands (hgdl and hgdlde) are defined during the configuration process.
- update of the required IDL-astron library routines, and Coyote library routines (2015-09-23).

#### Changes between releases 3.11 and 3.20

- addition of ialteralm to modify Spherical Harmonics coefficients  $(a_{\ell m})$ .
- addition of planck\_colors to modify current color table to one used in Planck 2013 publications.
- cartview, gnomview, mollview, orthview:
  - addition of BAD\_COLOR, BG\_COLOR and FG\_COLOR keywords to change the color of the missing pixels, background and foreground labels and lines.
  - support for COLT='planck1' and COLT='planck2' to use the Planck color tables defined in planck\_colors
- Bugs correction in bin\_llcl, query\_disc.
- update of the required IDL-astron library routines, and their supporting Coyote routines (2014-11-10).

#### Changes between releases 3.00 and 3.11

- Latest edition (version 3.11)
  - ang2pix\_ring and pix2ang\_nest routines now accept scalar arguments
- Previous edition (version 3.10)
  - bug corrections: query\_disc: correct handling of empty disc; bin\_llcl: correct handling of optional argument.
  - double precision of input now preserved in gaussbeam and euler\_matrix\_new.
  - fits2cl: addition of /PLANCK1 keyword to read best fit  $C(\ell)$  model to Planck 2013 + external data.
  - it is now possible to read a specific FITS file extension identified by its (0-based) number or its case-insensitive EXTNAME value with the Extension keyword added to fits2cl, getsize\_fits, read\_fits\_map, read\_fits\_s and read\_tqu.
  - update of the required IDL-astron library routines, and their supporting Coyote routines (2013-02-08).

#### Changes between releases 2.20 and 3.00

- Previous edition (version 3.0)
  - New routines to go from circular beam profile to transfer function (beam2bl), and back (bl2beam); to go from indexed list of a<sub>ℓm</sub> to a(l,m) 2D table (alm\_i2t), and back (alm\_t2i); and to compute the angular distance between pairs of vectors (angulardistance).
  - addition of iprocess\_mask interface to F90 process\_mask facility to compute the angular distance of valid pixels to the closest invalid pixels for a input binary mask.
  - creation of hpx2dm routine to generate DomeMaster images of HEALPix maps that can be projected on planetariums.
  - the pixel query routines query\_triangle, query\_polygon, and in particular query\_disc, have been improved
    and will return fewer false positive pixels in the *inclusive* mode
  - improved accuracy of the co-latitude calculation in the vicinity of the poles for high resolution in nest2ring, ring2nest, pix2ang\_\*, pix2vec\_\*, ...
  - cartview, gnomview, mollview, orthview: the length and spacing of the headless vectors used to represent
    polarization is now user-controlled via POLARIZATION keyword. The COLT keyword now allows the use of an
    interactively modified color table.
  - orthview now accepts STAGGER keyword to overplot staggered spheres (with a twist) in order to detect periodic boundary conditions on the sky
  - fits2cl: addition of WMAP7 keyword to read best fit  $C(\ell)$  model to WMAP 7yr data.
  - read\_fits\_map can now read N<sub>side</sub>=8192 HEALPix maps and is generally faster than previously for smaller maps
  - update of astron library routines (01-Feb-2012).

#### Changes between release 2.0 and 2.20

Several routines have been added or improved since version 2.0, as listed below. Note that thanks to the newer IDL-astron library, FITS read/write routines in IDL-Healpix routines can now deal with FITS files larger than 2GB (on architectures supporting 64bit addressing).

Using 64 bit integers available since version 5.2 of IDL the maximum resolution parameter Nside supported has increased from  $2^{13} = 8192$  to  $2^{29} = 536870912$ , corresponding to 3.46  $10^{18}$  pixels on the sphere.

- Recent edition (versions 2.20 and 2.20a)
  - fits2cl: addition of WMAP1 and WMAP5 keywords to read best fit  $C(\ell)$  model to WMAP 1st and 5yr data respectively,
  - cartview, gnomview, mollview, orthview: the OUTLINE option now accept symbols with PSYM > 8, using cgsymcat symbols definition.
- Recent editions (versions 2.15 and 2.15a)
  - cartview, gnomview, mollview, orthview:
    - \* export of projected map into a FITS file (FITS keyword), or an IDL array (MAP\_OUT option) now available with all viewing routines,
    - \* added CHARTHICK support; accept array of OUTLINE structures (if they have the same fields), and still support structure of structures,
    - correction of a bug (in loaddata\_healpix) that was affecting the behavior of these viewing routines after consecutive calls with very partial cut-sky and then full-sky data sets [2.15a];
  - remove\_dipole now outputs the monopole and dipole covariance matrix;
  - write\_fits\_map, write\_tqu, write\_fits\_sb: BAD\_DATA keyword added to FITS header;
  - $-\,$  update of astron library routines (24-May-2010) for improved WCS support.
- Previous edition (version 2.14a)
  - cartview, gnomview, mollview, orthview:
    - \* OUTLINE=, GRATICULE=, IGRATICULE= work again with virtual windows (WINDOW< 0)
    - $\ast\,$  YPOS= and RETAIN= keywords active again
    - \* PS= keyword fixed
  - orthview: fixed problems with /SHADE keyword, which now outputs 8-byte (instead of 16-byte) PNG files

Previous changes 11

- ianafast, ismoothing: fixed problem with processing of polarized maps stored in memory.
- ud\_grade: improved handling of flagged pixels on Double Precision input maps
- remove\_dipole: COORD\_IN= and COORD\_OUT= now accept lower case values; /SILENT keyword added.
- Old edition (version 2.13)
  - new healpix\_doc routine to browse HTML and PDF documentations
  - cartview, gnomview, mollview, orthview:
    - \* introduction of the TRUECOLORS= keyword to generate color image from 3 channel map
    - \* extended capability of the TRANSPARENT= keyword
    - \* addition of MAP\_OUT= to gnomview
  - improved compatibility with GDL (free IDL clone). See "HEALPix Installation Document" for current GDL limitations.
  - update of the IDL-astron library routines, which now require IDL 6.1 or more
  - fits2alm: new LMAX= and LMIN= keywords
  - fits2cl: new LLFACTOR= keyword
  - init\_healpix defines substructure with complete path to **HEALPix** subdirectories (test, data, bin)
  - slightly faster write\_fits\_cut4 and write\_fits\_sb routines.
  - ianafast, ismoothing: solved problem with W8DIR= keyword.
- Older editions (versions 2.11 and 2.12a)
  - ianafast, ismoothing, isynfast: the TMPDIR keyword now works properly, and \$IDL\_TMPDIR is used as the
    default temporary directory; more stable behaviour of these routines
  - ud\_grade:
    - \* correctly flags bad output pixels with bad\_data value when upgrading maps
    - $\ast~$  cut sky map: improved, faster routine, now works for Nside >8192
  - cartview, gnomview, mollview, orthview:
    - \* using a virtual window (ie, setting WINDOW to a negative value) now allows faster generation of GIF and PNG files (especially useful over remote connections);
    - \* addition of RETAIN= keyword;
    - \* deals correctly with user provided MIN and MAX in LOG and ASINH modes
    - \* polarization norm map can be offset (POLARIZATION=1 mode)
    - \* original color table and plot settings are restored when leaving these routines
  - orthview: addition of /SHADED keyword for 3D rendering
  - issues warning when non-integer pixel indexes are fed to nest2ring, ring2nest, pix2ang\_\*, pix2vec\_\*, ...
  - ximview:
    - \* fixed problem with cut-sky FITS files
    - st color scale bar added to PNG output
    - \* version 0.6.2, fixed bug in pixel coordinates
  - cosmetic editions to remove\_dipole
- New routines in version 2.10 include
  - ximview: visualisation routine developed by J. P. Leahy intended for quick-look inspection of HEALPix images
    (as well as ordinary 2-D images) at the level of individual pixels. Features include panning, zooming, blinking,
    image statistics and peak finding.
  - hpx2gs: turns a healpix data set into a Google Earth/Google Sky-compatible image
  - ianafast: interface to (F90) anafast and (C++) anafast\_cxx facilities
  - isynfast: interface to F90 synfast facility
  - ismoothing: interface to F90 smoothing facility
  - bin\_llcl:  $C(\ell)$  binning
  - **bl2fits**: writes  $B(\ell)$  or  $W(\ell)$  window into FITS file
  - neighbours\_nest, neighbours\_ring: find immediate neighbours of a given pixel
  - query\_strip: find pixels lying within a colatitude strip

- Routines with extended/improved user interface or new functionalities include
  - mollview, gnomview, cartview, orthview:
    - \* ONLINE keyword is now redundant,
    - \* introduction of GLSIZE and IGLSIZE to control automatic labeling of graticules, see Fig. 2 on page 122,
    - \* addition of SILENT and EXECUTE keywords, see Fig. 2 on page 122,
    - \* addition of ASINH keyword to allow better visualisation of highly contrasted maps; see Figure 3 on page 123,
    - \* under certain circumstances, can process high resolution cut sky data sets without creating full sky dummy maps,
    - \* accept gzip compressed FITS files,
    - \* accept polarized cut sky maps,
    - \* accept multi-dimensional online arrays,
    - \* more robust OUTLINE option.
  - median\_filter: bugs correction
  - ud\_grade: more robust user interface
  - change\_polcconv: new /FORCE keyword
  - remove\_dipole: more accurate
  - query\_disc: when the disc center is located at one of the poles, only the pixels overlapping with the disc are now returned.
- Miscellaneous
  - mollcursor, gnomcursor...: an X11 patch is given so that these routines work under Mac OS X 10.4 and 10.5.

alm i2t

# $alm_i2t$

Location in HEALPix directory tree: <a href="mailto:src/idl/misc/alm\_i2t.pro">src/idl/misc/alm\_i2t.pro</a>

This IDL function turns an indexed list of alm (as generated by fits2alm) into a tabular (real or complex) a(l,m) array for easier manipulation

**FORMAT** 

IDL> alm\_table=alm\_i2t(Index, Alm\_vec, [/COMPLEX, /HELP, LMAX=, MMAX=])

**QUALIFIERS** 

Index Integer vector of size ni containing the index i of

the of  $a_{\ell m}$  coefficients, related to  $\{\ell, m\}$  by i =

 $\ell^2 + \ell + m + 1$ 

Alm\_vec Array of  $a_{\ell m}$  coefficients, with dimension (ni, nalm

[,nsig]) where

ni = number of i indices

nalm = 2 for real and imaginary parts of alm co-

efficients or

4 for above plus corresponding error values

nsig = number of signals (usually 1 for any of T

E B or 3 for T,E,B together)

**KEYWORDS** 

/COMPLEX if set, the output array is complex with dimen-

sions (lmax+1, mmax+1, [nalm/2 , nsig]),

otherwise, the array is real with dimensions

(lmax+1, mmax+1, nalm [, nsig]).

 ${\tt lmax}$  and  ${\tt mmax}$  are determined from input  ${\tt Index}$ 

values, unless set otherwise by user.

/HELP if set, prints out the help header and exits

LMAX= lmax to be used in output array, regardless of

value found in input index

MMAX= mmax to be used in output array, regardless of

value found in input index

**DESCRIPTION**alm\_i2t returns a real or complex array, containing the  $a_{\ell m}$  with  $0 \le \ell \le \ell_{\text{max}}$  and  $0 \le m \le m_{\text{max}}$ . The negative m are therefore ignored.

#### RELATED ROUTINES

This section lists the routines related to alm\_i2t.

idl version 6.4 or more is necessary to run alm\_i2t.

alm\_t2i turns tabular alm's such as those generated by alm\_i2t into indexed lists than can written to

FITS files with alm2fits

alm2fits, fits2alm routines to read and write  $a_{\ell m}$  indexed lists from and to FITS files.

### EXAMPLE:

```
fits2alm, i1, a1, 'alm1.fits'
ac1 = alm_i2t(i1, a1, /complex, lmax=100, mmax=100)

fits2alm, i2, a2, 'alm2.fits'
ac2 = alm_i2t(i2, a2, /complex, lmax=100, mmax=100)
ac = 0.9*ac1 + 0.1*ac2

alm_t2i, ac, i, a
alm2fits, i, a, 'almsum.fits'
```

The example above reads 2 sets of  $a_{\ell m}$  from FITS files, puts the alm's with  $(\ell, m) \leq 100$  in tabular arrays, and then make a weighted sum of the alm's. The resulting alm or put back into a indexed list in order to be written to FITS.

alm t2i 15

# alm t2i

Location in HEALPix directory tree: src/idl/misc/alm t2i.pro

This IDL facility turns a tabular (real or complex) a(l,m) array into an indexed list of alm that can be written into a FITS file with alm2fits

**FORMAT** 

IDL> alm\_t2i, Alm\_table, Index, Alm\_vec, [HELP=, MFIRST=])

**QUALIFIERS** 

Alm\_table Input real or complex array, containing all the  $a_{\ell m}^s$ 

for  $\ell$  in  $[0, \ell_{\text{max}}]$  and m in  $[0, m_{\text{max}}]$  (and s in  $[0, s_{\text{max}}]$ 

if applicable)

if REAL it has 3 (or 4) dimensions,

if COMPLEX is has 2 (or 3) dimensions

Index Output integer vector of size ni containing the in-

dex i of the of  $a_{\ell m}$  coefficients, related to  $\{\ell, m\}$ 

by  $i = \ell^2 + \ell + m + 1$ 

Alm\_vec Output array of  $a_{\ell m}$  coefficients, with dimension

(ni,  $2[,s_{\text{max}}+1]$ ) where ni = number of i indices

2 for real and imaginary parts of alm coefficients

 $s_{\text{max}} + 1 = \text{number of signals (usually 1 for any of } 1$ 

T E B or 3 for T,E,B together)

**KEYWORDS** 

HELP= if set, prints out the help header and exits

MFIRST= if set, the input array is a(m,l) instead of a(l,m)

**DESCRIPTION**alm\_t2i turns a real or complex tabular array of a(l,m) (or a(m,l) if MFIRST is set) into a real list of  $a_{\ell m}$  (with the real and imaginary parts separated) and its index  $i = \ell^2 + \ell + m + 1$ . The unphysical  $m > \ell$  elements of the input table are dropped from the output list.

### RELATED ROUTINES

This section lists the routines related to alm\_t2i.

idl version 6.4 or more is necessary to run alm\_t2i.

alm\_i2t this function is complementary to alm\_t2i and

turns an indexed list of alm (as generated by fits2alm) into a tabular (real or complex) a(l,m)

array for easier manipulation

alm2fits, fits2alm routines to read and write  $a_{\ell m}$  indexed lists from

and to FITS files.

### **EXAMPLE:**

See alm\_i2t example

alm2fits 17

# alm2fits

#### Location in HEALPix directory tree: src/idl/fits/alm2fits.pro

This IDL routine provides a means to write spherical harmonic coefficients (and optional errors) and their index label to a FITS file. Each signal is written to a separate binary table extension. The routine also writes header information if required. The facility is primarily designed to allow the user to write a FITS files containing constraints for a constrained realisation performed by the **HEALPix** facility **synfast**.

### **FORMAT**

IDL> ALM2FITS, index, alm\_array, fitsfile, [HDR=, /HELP, XHDR=]

# **QUALIFIERS**

index Long array containing the index for the corre-

sponding array of alm coefficients (and erralm if required). The index i is related to  $\ell, m$  by the relation

 $i = \ell^2 + \ell + m + 1$ 

alm\_array Real array of alm coefficients written to the file.

This has dimension (nl,nalm,nsig) – correspond-

ing to

nl = number of l, m indices

nalm = 2 for real and imaginary parts of alm coefficients or 4 for above plus corresponding error

values

nsig = number of signals to be written (1 for any of T E B or 3 if ALL to be written). Each signal

is stored in a separate extension.

fitsfile String containing the name of the file to be writ-

ten.

### **KEYWORDS**

HDR = String array containing the primary header to be

written in the FITS file.

/HELP If set, the routine documentation header is shown

and the routine exits

XHDR =String array containing the extension header. If

ALL signals are required, then each extension ta-

ble is given this header.

NOTE: optional header strings should NOT include the header keywords explicitly written by

this routine.

**DESCRIPTION** alm2fits writes the input alm coefficients (and associated errors if required) into a FITS file. Each signal type is written as a separate binary table extension. Optional headers conforming to the FITS convention can also be written to the output file. All required FITS header keywords are automatically generated by the routine and should NOT be duplicated in the optional header inputs. The keywords EXTNAME and TTYPE\* are now also automatically generated.

#### RELATED ROUTINES

This section lists the routines related to alm2fits.

idl version 6.4 or more is necessary to run alm2fits.

fits2alm provides the complimentary routine to read in alm

coefficients from a FITS file.

these facilities turn indexed lists of  $a_{\ell m}$  into 2D alm i2t, alm t2i

a(l,m) tables and back

lm2index converts the  $a_{\ell m}$  order and degree  $(\ell, m)$  into the

index  $i = \ell^2 + \ell + m + 1$  required by alm2fits.

routine to write a power spectrum into a FITS cl2fits

file.

fits2cl routine to read/compute  $C(\ell)$  power spectra from

a file containing  $C(\ell)$  or  $a_{\ell m}$  coefficients

alteralm utilises the output file generated by alm2fits.

synfast utilises the output file generated by alm2fits.

#### **EXAMPLE:**

alm2fits 19

alm2fits, index, alm, 'alm.fits', HDR = hdr, XHDR = xhdr

alm2fits writes the coefficients stored in the variable alm to the output FITS file alm.fits with optional headers passed by the string variables hdr and xhdr.

# ang2vec

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/ang2vec.pro">src/idl/toolkit/ang2vec.pro</a>

This IDL facility convert the position angles of points on the sphere into their 3D position vectors.

# FORMAT

IDL> ANG2VEC, Theta, Phi, Vector[, AS-TRO=]

# **QUALIFIERS**

Theta input: scalar or vector,

colatitude in radians measured southward from

north pole (in  $[0,\pi]$ ).

If ASTRO is set, Theta is the latitude in degrees

measured northward from the equator (in [-90,

90]).

Phi input: scalar or vector of same size as Theta,

longitude in radians measured eastward (in [0,

 $2\pi$ ]).

If ASTRO is set, it is the longitude in degree mea-

sured eastward (in [0,360]).

Vector output : array,

three dimensional cartesian position vector (x, y, z) normalised to unity. The north pole is (0, 0, 1). The coordinates are ordered as follows  $x(0), \ldots, x(n-1), y(0), \ldots, y(n-1)$ 

1),  $z(0), \ldots, z(n-1)$ 

### **KEYWORDS**

ASTRO =

if set Theta and Phi are the latitude and longitude in degrees instead of the colatitude and longitude in radians. ang2vec 21

**DESCRIPTION** ang2vec performs the geometrical transform from the position angles of points  $(\theta, \phi)$  into their position vectors (x, y, z):  $x = \sin \theta \cos \phi$ ,  $y = \sin \theta \sin \phi$ ,  $z = \cos \theta$ 

### RELATED ROUTINES

This section lists the routines related to ang2vec.

idl version 6.4 or more is necessary to run ang2vec.

pix2xxx, ... conversion between vector or angles and pixel in-

 $\operatorname{dex}$ 

vec2ang conversion from position vectors to angles

#### **EXAMPLE:**

lat = -45; latitude in degrees
long = 120; longitude in degrees
ang2vec, lat, lon, /astro, vec

will return in vec the 3D cartesian position vector of the point of latitude -45 deg and longitude 120 deg

# angulardistance

Location in HEALPix directory tree: src/idl/toolkit/angulardistance.pro

This IDL facility computes the angular distance (in RADIANS) between pairs of vectors.

FORMAT	IDL>	distance = angular distance(V,	W,
	[/HELP]		

### **QUALIFIERS**

V 3D-vector (of shape (3) or (1,3)) or list of n 3D-vectors (of shape (n,3))

W 3D-vector (of shape (3) or (1,3)) or list of n 3D-vectors (of shape (n,3))

It is **not** necessary for **V** and **W** vectors to be normalised to 1 upon calling the function.

If V and W both are lists of vectors, they should be of the same length.

If V (and/or W) has the form (n,3,4) (like the pixel *corners* returned by  $pix2vec_*$ ), it should be preprocessed with V = reform( transpose(V, [0,2,1]), n\_elements(V)/3, 3) to take the form (n\*4,3) before being passed to angular distance.

### **KEYWORDS**

/HELP if set, prints out the help header and exits

angulardistance 23

**DESCRIPTION**After renormalizing the vectors, angular distance computes the angular distance using  $\cos^{-1}(\mathbf{V}.\mathbf{W})$  in general, or  $2\sin^{-1}(||\mathbf{V}-\mathbf{W}||/2)$  when  $\mathbf{V}$  and  $\mathbf{W}$  are almost aligned.

If V (resp. W) is a single vector, while W (resp. V) is a list of vectors, then the result is a list of distances  $d_i = \text{dist}(\mathbf{V}, \mathbf{W}_i)$ (resp.  $d_i = \operatorname{dist}(\mathbf{V}_i, \mathbf{W})$ ).

If both V and W are lists of vector of the same length, then the result is a list of distances  $d_i = \text{dist}(\mathbf{V}_i, \mathbf{W}_i)$ .

#### RELATED ROUTINES

This section lists the routines related to **angulardistance**.

idl version 6.4 or more is necessary to run angulardistance.

#### **EXAMPLE:**

nside=8

pix2vec\_ring, nside, lindgen(nside2npix(nside)), vpix mollview, angulardistance( vpix, [1,1,1])

> will plot the angular distance between the Healpix pixels center for  $N_{\rm side} = 8$ , and the vector  $(x, y, z) = (1, 1, 1)/\sqrt{3}$

# azeqview

#### Location in HEALPix directory tree: src/idl/visu/azeqview.pro

This IDL facility provides a means to visualise an azimuthal equidistant projection of **HEALPix** and COBE Quad-Cube maps in an IDL environment. It also offers the possibility to generate GIF, JPEG, PDF, PNG and Postscript color-coded images of the projected map. The projected (but not color-coded) data can also be output in FITS files and IDL arrays.

#### **FORMAT**

AZEQVIEW, IDL> File [, Select] [, INH=, BAD COLOR=, BG COLOR=, CHARSIZE=. CHARTHICK=, COLT=, COORD=, /CROP, CUS-TOMIZE=, DEFAULT\_SETTINGS=, EXECUTE=, FAC-TOR=, FG COLOR=, FITS=, /FLIP, GAL CUT=, GIF=, GLSIZE=, GRATICULE=, /HALF SKY, HBOUND=, /HELP, /HIST\_EQUAL, HXSIZE=, IGLSIZE=, IGRATIC-ULE=, JPEG=, LATEX=, /LOG, MAP\_OUT=, MAX=, MIN=, /NESTED, /NO DIPOLE, /NO MONOPOLE, /NOBAR, /NOLABELS, /NOPOSITION, OFFSET=, OUT-LINE=, PDF=, PFONTS=, PNG=, POLARIZATION=, /PREVIEW, PS=, PXSIZE=, PYSIZE=, RESO\_ARCMIN=, RETAIN=, ROT=, /SAVE, /SHADED, /SILENT, SIL-HOUETTE=, STAGGER=, SUBTITLE=, TITLEPLOT=, TRANSPARENT=, TRUECOLORS=, UNITS=, WIN-DOW=, XPOS=, YPOS=

### **QUALIFIERS**

For a full list of qualifiers see mollview

azeqview 25

### **KEYWORDS**

For a full list of keywords see mollview

### **DESCRIPTION**

azeqview reads in a **HEALPix** sky map in FITS format and generates an azimuthal equidistant projection of it, that can be visualized on the screen or exported in a GIF, JPEG, PNG, PDF or Postscript file. azeqview allows the selection of the coordinate system, map size, color table, color bar inclusion, linear, log, hybrid or histogram equalised color scaling, maximum and minimum range for the plot, plot-title *etc*. It also allows the representation of the polarization field.

#### RELATED ROUTINES

This section lists the routines related to azeqview.

see mollview

hpx2dm

turns Healpix maps into DomeMaster images using azeqview.

# beam2bl

Location in HEALPix directory tree: <a href="mailto:src/idl/misc/beam2bl.pro">src/idl/misc/beam2bl.pro</a>

This IDL facility computes a transfer (or window) function  $b(\ell)$  for a circular beam profile  $b(\theta)$ .

### **FORMAT**

IDL> bl=beam2bl( beam, theta, lmax, [/AR-CMIN , /DEGREES, /HELP, /RADIANS])

# **QUALIFIERS**

beam input beam profile  $b(\theta)$ 

theta angles  $\theta$  (in arcmin, degrees or radians) at which

the input beam  $b(\theta)$  is defined

lmax maximum multipole on which the output  $b(\ell)$  is

to be computed

## **KEYWORDS**

/ARCMIN if set,  $\theta$  is in arcmin

/DEGREES if set,  $\theta$  is in degrees

/HELP if set, prints out the help header and exits

/RADIANS if set,  $\theta$  is in radians

beam2bl 27

### **DESCRIPTION**Since the SH Transform of an arbitrary beam is

$$b_{\ell m} = \int d\mathbf{r} \ b(\mathbf{r}) \ Y_{\ell m}^*(\mathbf{r}) \tag{1}$$

then, for a circular beam

$$b(\ell) = b_{\ell 0} \sqrt{\frac{4\pi}{2\ell + 1}}$$
$$= \int b(\theta) P_{\ell}(\theta) \sin(\theta) d\theta 2\pi$$
(2)

where  $P_{\ell}$  is the Legendre Polynomial,  $b(\ell)$  is the beam window (or transfer) function returned by beam2bl and  $b(\theta)$  is the beam radial profile expected as input of beam2bl.

IDL's routine INT\_TABULATED is used to perform the integration.

#### RELATED ROUTINES

This section lists the routines related to **beam2bl**.

idl	version 6.4 or more is necessary to run beam2bl.
bl2beam	facility to perform the inverse transform to beam2bl.
bl2fits	facility to write a $b(\ell)$ window function into a FITS file.
fits2cl	facility to read a $b(\ell)$ window function from a FITS file

#### **EXAMPLE:**

```
bl = gaussbeam(15.d0, 4000, 1)
theta = dindgen(4000)/100.
beam = bl2beam(bl, theta, /arcmin)
bl1 = beam2bl(beam, theta, 4000, /arcmin)
plot, bl1-bl
```

the example above generates a beam window function (defined for all  $\ell$  in  $\{0, \ldots, 4000\}$ ) for a 15arcmin-FWHM gaussian beam, computes the beam profile for angles in [0, 40] arcmin, computes back the beam window function from the beam profile and finally plots the difference between the beam window functions.

# bin llcl

Location in HEALPix directory tree: <a href="mailto:src/idl/misc/bin\_llcl.pro">src/idl/misc/bin\_llcl.pro</a>

This IDL facility provides a means to bin an angular power spectrum into arbitrary bins.

**FORMAT** 

IDL> BIN\_LLCL, Llcl\_in, Bin, L\_out, Llcl\_out, [Dllcl, DELTAL=, /FLATTEN, /HELP, /UNIFORM]

**QUALIFIERS** 

Llcl\_in 1D vector: **input** power spectrum (given for each

l starting at 0).

Bin input: binning in l to be applied,

-either a scalar interpreted as the step size of a regular binning, the first bins are then  $\{0, \text{ bin } -$ 

1,{bin, 2bin-1}, ...

-or a 1D vector, interpreted as the lower bound of each bin, ie the first bins are {bin[0],bin[1]-1},

 $\{ bin[1], bin[2]-1 \}, \dots$ 

L out contains on **output** the center of each bin  $l_b$ .

Llcl\_out contains on **output** the binned power spectrum

C(b), ie the (weighted) average of the input C(l)

over each bin.

Dllcl optional, contains on output a rough estimate

of the rms of the binned C(l) for a full sky obser-

vation  $C(b)\sqrt{2/((2l_b+1)\Delta l_b)}$ 

DELTAL= **optional**, contains on **output** the size of each bin

 $\Delta l(b)$ 

**KEYWORDS** 

/FLATTEN

if set, the C(l) is internally multiplied by l(l + l)

 $1)/2\pi$  before being binned.

By default, the input Llcl\_in is binned as is.

bin llcl 29

> /HELP if set, an extended help is printed and the code exits.

/UNIFORM

if set, the C(l) in each bin is given the same weight.

By default a weight  $\propto 2l+1$  is used (inverse cosmic variance weighting). Note that this weighting affects Llcl out but not L out.

 $\overline{
m DESCRIPTION}$  bin\_llcl bins the input power spectrum (as is, or after flattening by a  $\frac{1}{1+1}$ /2 $\pi$  factor) according to an arbitrary binning scheme defined by the user. Different weighting scheme (uniform or inverse variance) can be applied inside the bins.

#### RELATED ROUTINES

This section lists the routines related to **bin** llcl.

idl version 6.4 or more is necessary to run bin llcl. fits2cl facility to read a power spectrum from a FITS file.

#### **EXAMPLE:**

```
init healpix
fits2cl, cl, !healpix.directory+'/test/cl.fits', multipoles=l
fl = 1*(1+1) / (2. * !pi)
bin llcl, fl*cl[*,0], 10, lb, bbcb, /uniform
plot, 1, fl*cl[*,0]
oplot, lb, bbcb, psym = 4
```

Read a power spectrum, bin it with a binsize of 10 and a uniform weighting, and overplot the input spectrum and its binned version.

# bl2beam

Location in HEALPix directory tree: <a href="mailto:src/idl/misc/bl2beam.pro">src/idl/misc/bl2beam.pro</a>

This IDL facility computes a circular beam profile  $b(\theta)$  from its transfer (or window) function  $b(\ell)$ .

### **FORMAT**

IDL> beam=bl2beam( bl, theta, [/ARCMIN , /DEGREES, /HELP, /RADIANS])

# **QUALIFIERS**

bl input  $b(\ell)$  window function of beam (defined for

all integer multipoles l starting at 0)

theta angles  $\theta$  (in arcmin, degrees or radians) at which

the output beam  $b(\theta)$  is to be computed.

## **KEYWORDS**

/ARCMIN if set,  $\theta$  is in arcmin

/DEGREES if set,  $\theta$  is in degrees

/HELP if set, prints out the help header and exits

/RADIANS if set,  $\theta$  is in radians

bl2beam 31

**DESCRIPTION**Since an arbitrary beam is related to its SH Transform via

$$b(\mathbf{r}) = \sum_{\ell m} b_{\ell m} Y_{\ell m}(\mathbf{r}), \tag{3}$$

a circular beam has a radial profile (as returned by bl2beam)

$$b(\theta) = \sum_{\ell} b(\ell) P_{\ell}(\theta) \frac{2\ell + 1}{4\pi}, \tag{4}$$

where  $P_l$  is Legendre Polynomial and

$$b(\ell) = b_{\ell 0} \sqrt{\frac{4\pi}{2\ell + 1}} \tag{5}$$

is the beam window (or transfer) function, expected as input to bl2beam.

#### RELATED ROUTINES

This section lists the routines related to **bl2beam**.

idl version 6.4 or more is necessary to run bl2beam.

beam2bl facility to perform the inverse transform to

bl2beam.

bl2fits facility to write a  $b(\ell)$  window function into a

FITS file.

fits2cl facility to read a  $b(\ell)$  window function from a

FITS file

#### **EXAMPLE:**

bl = gaussbeam(15.d0, 4000, 1)

theta = dindgen(3000)/100.

beam = bl2beam(bl, theta, /arcmin)

plot, theta, beam

the example above generates a beam window function (defined for all l in  $\{0, \ldots, 4000\}$ ) for a 15arcmin-FWHM gaussian beam, computes the beam profile for angles in [0, 30] arcmin and then plots it.

# bl2fits

#### Location in HEALPix directory tree: src/idl/fits/bl2fits.pro

This IDL facility provides a means to write into a FITS file as an ascii table extension a (beam) window function  $B(\ell)$ . Adds additional headers if required. The facility is primarily intended to allow the user to write an arbitrary window function into a FITS file in the correct format to be ingested by the **HEALPix** simulation facilities synfast, isynfast, and others (see "Beam window function files" in the **HEALPix** Fortran Facilities document).

### **FORMAT**

IDL> BL2FITS, bl\_array, fitsfile, [HDR = ,
/HELP, XHDR =]

## **QUALIFIERS**

bl\_array real or double array of Bl coefficients to be written

to file. This has dimension (lmax+1,n) with 1  $\leq$ 

 $n \leq 3$ , given in the sequence T E B.

fitsfile String containing the name of the file to be writ-

ten.

### **KEYWORDS**

HDR= String array containing the (non-trivial) primary

header for the FITS file.

/HELP If set, a help message is printed out, no file is

written

XHDR= String array containing the (non-trivial) extension

header for the FITS file.

bl2fits 33

**DESCRIPTION** bl2fits writes the input  $B(\ell)$  coefficients into a FITS file containing an ascii table extension. Optional headers conforming to the FITS convention can also be written to the output file. All required FITS header keywords (like SIMPLE, BITPIX, ...) are automatically generated by the routine and should NOT be duplicated in the optional header inputs (they would be ignored anyway). The one/two/three column(s) are automati-

RELATED ROUTINES

This section lists the routines related to **bl2fits**.

idl version 6.4 or more is necessary to run bl2fits.

cally named TEMPERATURE, GRAD, CURL respectively. If the window function is provided in a double precision array, the output

format will automatically feature more decimal places.

fits2cl provides the complimentary routine to read in a

window function or power spectrum from a FITS

file.

synfast utilises the output file generated by bl2fits(option

beam file).

#### **EXAMPLE:**

```
beam1 = gaussbeam(10., 2000, 1)
beam2 = gaussbeam(15., 2000, 1)
beam = (beam1 + beam2) / 2.
bl2fits, beam, 'beam.fits'
```

bl2fits writes the beam window function stored in the variable beam (=Legendre transform of a circular beam) into the output FITS file beam.fits.

## cartcursor

#### Location in HEALPix directory tree: src/idl/visu/cartcursor.pro

This IDL facility provides a point-and-click interface for finding the astronomical location, value and pixel index of the pixels nearest to the pointed position on a cartesian projection of a **HEALPix** map.

#### **FORMAT** CARTCURSOR, IDL> cursor type=. file out=

# **QUALIFIERS**

see mollcursor

**DESCRIPTION**cartcursor should be called immediately after cartview. It gives the longitude, latitude, map value and pixel number corresponding to the cursor position in the window containing the map generated by orthview. For more details, or in case of problems under Mac OS X, see mollcursor.

#### RELATED ROUTINES

This section lists the routines related to **cartcursor**.

see mollcursor

#### **EXAMPLE:**

cartcursor

After cartview has read in a map and generated its cartesian projection, cartcursor is run to determine the position and flux of bright synchrotron sources, for example.

cartview 35

### cartview

#### Location in HEALPix directory tree: src/idl/visu/cartview.pro

This IDL facility provides a means to visualise a cartesian (or equirectangular) projection (where the longitude and latitude are treated as the cartesian abscissa and ordinate) of **HEALPix** and COBE Quad-Cube maps in an IDL environment. It also offers the possibility to generate GIF, JPEG, PDF, PNG and Postscript color-coded images of the projected map. The projected (but not color-coded) data can also be output in FITS files and IDL arrays.

### **FORMAT**

CARTVIEW, IDL> File [, Select] [, AS-INH=, BAD COLOR=, BG COLOR=, CHARSIZE=, CHARTHICK=, COLT=, COORD=, /CROP, CUS-TOMIZE=, DEFAULT SETTINGS=, EXECUTE=, FAC-TOR=, FG\_COLOR=, FITS=, /FLIP, GAL\_CUT=, GIF=, GLSIZE=, GRATICULE=, /HALF SKY, HBOUND=, /HELP, /HIST EQUAL, HXSIZE=, IGLSIZE=, IGRATIC-ULE=, JPEG=, LATEX=, /LOG, MAP\_OUT=, MAX=, MIN=, /NESTED, /NO\_DIPOLE, /NO\_MONOPOLE, /NOBAR, /NOLABELS, /NOPOSITION, OFFSET=, OUT-LINE=, PDF=, PFONTS=, PNG=, POLARIZATION=, /PREVIEW, PS=, PXSIZE=, PYSIZE=, RESO\_ARCMIN=, RETAIN=, ROT=, /SAVE, /SHADED, /SILENT, SIL-HOUETTE=, STAGGER=, SUBTITLE=, TITLEPLOT=, TRANSPARENT=, TRUECOLORS=, UNITS=, WIN-DOW=, XPOS=, YPOS=

### **QUALIFIERS**

For a full list of qualifiers see mollview

### **KEYWORDS**

For a full list of keywords see mollview

### **DESCRIPTION**

cartview reads in a **HEALPix** sky map in FITS format and generates a cartesian projection of it, that can be visualized on the screen or exported in a GIF, JPEG, PNG, PDF or Postscript file. cartview allows the selection of the coordinate system, map size, color table, color bar inclusion, linear, log, hybrid or histogram equalised color scaling, maximum and minimum range for the plot, plot-title *etc*. It also allows the representation of the polarization field.

#### RELATED ROUTINES

This section lists the routines related to **cartview**.

see mollview

#### **EXAMPLE:**

```
map = findgen(48)
triangle= create_struct('coord','G','ra',[0,80,0],'dec',[40,45,65])
cartview,map,/online,res=45,graticule=[45,30],rot=[10,20,30],pysize=250,$
   title='Cartesian cylindrical (full sky)',subtitle='cartview', $
   outline=triangle
```

makes a cartesian cylindrical projection of map (see Figure 1a on page 122) after an arbitrary rotation, with a graticule grid (with a  $45^{\circ}$  step in longitude and  $30^{\circ}$  in latitude) and an arbitrary triangular outline

change\_polcconv 37

## change\_polcconv

Location in HEALPix directory tree: <a href="mailto:src/idl/fits/change\_polcconv.pro">src/idl/fits/change\_polcconv.pro</a>

This IDL facility changes the coordinate convention in FITS file containing a polarised sky map. The main effect is to change the sign of the U Stokes parameter, and add/update the POLCCONV FITS header keyword with either COSMO or IAU value.

See note on POLCCONV in The **HEALPix** Primer

## FORMAT

IDL> CHANGE\_POLCCONV, File\_In, File\_Out, [/I2C|/C2I|/C2C|/I2I], [/FORCE]

## **QUALIFIERS**

 $File\_In$ 

name of a FITS file to be read

File Out

name of a FITS file to be written, after modification of the polarisation coordinate convention, if applicable. It must be different from File\_In

## **KEYWORDS**

One and only one among I2C, C2I, C2C and I2I must be set.

/I2C

changes from IAU to COSMO coordinate convention

-if POLCCONV is not found or found with value 'IAU', or FORCE is set, it is added/replaced with value 'COSMO', and the sign of the U Stokes parameter map is changed;

-if POLCCONV already has value 'COSMO' and FORCE is NOT set, File\_In is copied unchanged into File\_Out.

/C2I

changes from COSMO to IAU coordinate convention

-if POLCCONV is not found or found with value 'COSMO', or FORCE is set, it is added/replaced with value 'IAU', and the sign of the *U* Stokes parameter map is changed;

-if POLCCONV already has value 'IAU', and

FORCE is NOT set, File\_In is copied unchanged into File Out.

/C2Cdoes NOT change coordinate system

> -if POLCCONV is found with value 'IAU', and FORCE is NOT set, program will issue error message and no file is written;

> -in all other cases POLCCONV is set/added with value 'COSMO' in File Out, but data is NOT changed.

/I2Idoes NOT change coordinate system

> -if POLCCONV is found with value 'COSMO', and FORCE is NOT set, program will issue error message and no file is written;

> -in all other cases POLCCONV is set/added with value 'IAU' in File\_Out, but data is NOT changed.

/FORCE

if set, the value of POLCCONV read from File\_In FITS header is ignored. The sign of U is swapped (if used with /C2I or /I2C), and/or the File Out FITS keyword is updated to IAU (if used with /I2I or /C2I) or to COSMO (if used with /C2C or /I2C).

 $\overline{\mathbf{DESCRIPTION}}$  This routine will change the sign of the U Stokes parameters (and related quantities, such as the TU and QU crosscorrelations) and update the POLCCONV FITS keyword where applicable. The recognised formats are:

- standard **HEALPix** full sky polarised format,
- cut sky **HEALPix** polarised format,
- WMAP 9-year release polarised \* igumap \* and \* igusmap \* formats,
- Planck \* SkyMap \* and \* CMB IQU\* formats

#### RELATED ROUTINES

This section lists the routines related to **change\_polcconv**.

idl version 6.4 or more is necessary

change\_polcconv

write fits cut4 This **HEALPix** IDL facility can be used to write change\_polcconv 39

a (polarised or unpolarised) cut sky map into a FITS file.

read fits cut4 This HEALPix IDL facility can be used to read

a (polarised or unpolarised) cut sky map from a

FITS file.

write\_tqu This **HEALPix** IDL facility can be used to write

a polarised full sky map (with either the standard Healpix format or the WMAP 2nd year format)

into a FITS file

read\_tqu This HEALPix IDL facility can be used to read

a polarised cut sky map from a FITS file

#### **EXAMPLE:**

change\_polcconv, 'map\_cosmo.fits','map\_iau.fits',/c2i

Modify the file 'map\_cosmo.fits', which was using the 'COSMO' convention for polarisation coordinate convention into 'map iau.fits' which uses the 'IAU' convention

## cl2fits

#### Location in HEALPix directory tree: src/idl/fits/cl2fits.pro

This IDL facility provides a means to write into a FITS file as an ascii table extension the power spectrum coefficients passed to the routine. Adds additional headers if required. The facility is primarily intended to allow the user to write a theoretical power spectrum into a FITS file in the correct format to be ingested by the **HEALPix** simulation facility **synfast**.

## $\overline{\text{FORMAT}}$

IDL> CL2FITS, cl\_array, fitsfile, [HDR=, /HELP, XHDR=, /CMBFAST, UNITS=]

## **QUALIFIERS**

cl\_array real or double array of Cl coefficients to be writ-

ten to file. This has dimension either (lmax+1,9) given in the sequence T E B TxE TxB ExB ExT BxT BxE or (lmax+1,6) given in the sequence T E B TxE TxB ExB or (lmax+1,4) given in the sequence T E B TxE or (lmax+1) for T alone.

The convention for the power spectrum is that it is not normalised by the Harrison-Zeldovich (flat)

spectrum.

fitsfile String containing the name of the file to be writ-

ten.

## **KEYWORDS**

HDR= String array containing the (non-trivial) primary

header for the FITS file.

/HELP If set, a help message is printed out, no file is

written

XHDR= String array containing the (non-trivial) extension

header for the FITS file.

/CMBFAST if set, the routine will add the keyword 'POL-

NORM = CMBFAST' in the FITS header, meaning that the polarization power spectra have the

cl2fits 41

> same convention as CMBFAST (and Healpix 1.2). If this keyword is not present in the input FITS file, synfast will issue a warning when simulating a polarization map from that power spectrum, but no attempt to renormalize the power spectra will be made. To actually perform the renormalization, see convert\_oldhpx2cmbfast

UNITS=

String scalar containing units of power spectrum (eg, uK<sup>2</sup>, Kelvin\*\*2, ...), to be put in keywords 'TUNIT\*' of the extension header. If provided, will override the values present in XHDR (if any).

NOTE: optional header strings should NOT include the header keywords explicitly written by this routine.

**DESCRIPTION** cl2fits writes the input power spectrum coefficients into a FITS file containing an ascii table extension. Optional headers conforming to the FITS convention can also be written to the output file. All required FITS header keywords (like SIMPLE, BITPIX, ...) are automatically generated by the routine and should NOT be duplicated in the optional header inputs (they would be ignored anyway). The one/four/six/nine column(s) are automatically named TEMPERATURE, GRAD, CURL, TG, TC, GC, GT, CT and CG respectively. If the power spectrum is provided in a double precision array, the output format will automatically feature more decimal places. The current implementation is much faster than the one available in Healpix 1.10 thanks to replacing an internal loop by vector operations.

#### RELATED ROUTINES

This section lists the routines related to cl2fits.

idl version 6.4 or more is necessary to run cl2fits.

fits2cl provides the complimentary routine to read in a

power spectrum from a FITS file.

convert\_oldhpx2cmbfast convert an existing power spectrum FITS file from the polarization convention used in Healpix 1.1 to

the one used in Healpix 1.2 (and CMBFAST).

HEALPix 3.83

bl2fits facility to write a window function into a FITS

file.

fits2alm, alm2fits routines to read and write  $a_{\ell m}$  coefficients

synfast utilises the output file generated by cl2fits.

#### **EXAMPLE:**

cl2fits, pwrsp, 'spectrum.fits', HDR = hdr, XHDR = xhdr

cl2fits writes the power spectrum stored in the variable pwrsp to the output FITS file spectrum.fits with optional headers passed by the string variables hdr and xhdr.

## convert\_oldhpx2cmbfast

Location in HEALPix directory tree: src/idl/fits/convert\_oldhpx2cmbfast.pro

This IDL facility provides a means to change the normalization
of polarization power spectra in a FITS file from Healpix 1.1
convention to Healpix 1.2 (which is the same as CMBFAST).

# FORMAT IDL> CONVERT\_OLDHPX2CMBFAST, file\_in, [file\_out, NO\_RENORM=]

## **QUALIFIERS**

file\_in String containing the name of the FITS file with

the power spectra to be read.

file\_out (OPTIONAL) String containing the name of the

file to be written after renormalization. If absent,

file\_in will be used for output

## **KEYWORDS**

NO RENORM=

if set, the renormalization is not done. but the keyword POLNORM = CMBFAST is added to the FITS header (useful if the FITS file is already in CMBFAST format).

# DESCRIPTION convert\_oldhpx2cmbfast does the conversion from the polarization normalisation used in HEALPix 1.1 to the one used in HEALPix 1.2 (see the Healpix primer document). A keyword POLNORM = CMBFAST is added to the header to keep track of which files have been renormalized. If this keyword is not present in the input FITS file, synfast will issue a warning when simulating a polarization map from that power spectrum, but no attempt to renormalize the power spectra will be made.

#### RELATED ROUTINES

This section lists the routines related to **convert\_oldhpx2cmbfast**.

version 6.4 or more is necessary to run convert\_oldhpx2cmbfast.

cl2fits provides the a routine to write a power spectrum to a FITS file.

fits2cl provides the complimentary routine to read in a power spectrum from a FITS file.

synfast utilises the output file generated by convert\_oldhpx2cmbfast.

#### **EXAMPLE:**

convert\_oldhpx2cmbfast, 'cl\_flat.fits'

convert\_oldhpx2cmbfast will renormalize the polarization power spectra read from 'cl\_flat.fits', and write them in the same file.

euler\_matrix\_new 45

## euler matrix new

Location in HEALPix directory tree: <a href="mailto:src/idl/misc/euler\_matrix\_new.pro">src/idl/misc/euler\_matrix\_new.pro</a>

This IDL facility provides a means to generate a 3D rotation Euler matrix parametrized by three angles and three axes of rotation.

## **QUALIFIERS**

matrix	a 3x3 array containing the Euler matrix
a1	input, float scalar, angle of the first rotation, expressed in radians, unless DEG (see below) is set
a2	angle of the second rotation, same units as a1
a3	angle of the third rotation, same units as a1

## **KEYWORDS**

•	
DEG =	if set, the angles are in degrees instead of radians
HELP=	if set, the routine prints its documentation header and exits
X=	if set, uses the classical mechanics convention (ZXZ): rotation a1 around original Z axis, rotation a2 around intermediate X axis, rotation a3 around final Z axis (see Goldstein (1951) for more details).  Equivalent to: rotation a3 around Z axis, rotation a2 around initial (unrotated) X axis, rotation a1 around initial (unrotated) Z axis. (default: this convention is used)
Y=	if set, uses the quantum mechanics convention (ZYZ):

rotation a1 around original Z axis,

rotation a2 around intermediate Y axis, rotation a3 around final Z axis.

Equivalent to:
rotation a3 around Z axis,

rotation as around z axis, rotation as around initial (unrotated) Y axis,

rotation a2 around initial (unrotated) Y axis, rotation a1 around initial (unrotated) Z axis.

ZYX = if set, uses the aeronautics convention (ZYX):

rotation a1 around original Z axis,

rotation a2 around intermediate Y axis,

rotation a3 around final X axis.

Equivalent to:

rotation a3 around X axis,

rotation a2 around initial (unrotated) Y axis, rotation a1 around initial (unrotated) Z axis.

## **DESCRIPTION**euler\_matrix\_new allows the generation of a rotation Euler

matrix\_new allows the generation of a rotation Euler matrix. The user can choose the three Euler angles, and the three axes of rotation.

If vec is an  $N\times3$  array containing N 3D vectors, vecr = vec # euler\_matrix\_new(a1,a2,a3,/Y) will be the rotated vectors. Alternatively, rotate\_coord can also be used to rotate vec into vecr.

This routine supersedes euler\_matrix, which had inconsistent angle definitions. The relation between the two routines is as follows:

euler\_matrix\_new(a,b,c,/X) = euler\_matrix(-a,-b,-c,/X) = Transpose(euler\_matrix(c, b, a,/X))

 $euler\_matrix\_new(a,b,c,/Y) = euler\_matrix(-a,\,b,-c,/Y)$ 

 $= \overline{\text{Transpose}}(\overline{\text{euler\_matrix}}(c, -b, a, /\overline{Y}))$ 

 $euler\_matrix\_new(a,b,c,/Z) = euler\_matrix(-a,\,b,-c,/Z)$ 

#### RELATED ROUTINES

This section lists the routines related to **euler\_matrix\_new**.

idl version 6.4 or more is necessary to run eu-

ler matrix new.

rotate\_coord apply a rotation to a set of position vectors and

polarization Stokes parameters.

fits2alm 47

## fits2alm

Location in HEALPix directory tree: src/idl/fits/fits2alm.pro

This IDL routine provides a means to read from a FITS file binary table extension(s) containing spherical harmonic coefficients  $a_{\ell m}$  (and optional errors) and their index. Reads header information if required. The facility is intended to enable the user to read the output from the **HEALPix** facilities **anafast** and **synfast**.

**FORMAT** 

IDL> FITS2ALM, index, alm\_array, fitsfile, [signal, /HELP, HDR=, LMAX=, LMIN=, XHDR=]

**QUALIFIERS** 

index Long array containing the index for the corre-

sponding array of  $a_{\ell m}$  coefficients (and errors if required). The index i is related to  $(\ell, m)$  by the

relation

 $i = \ell^2 + \ell + m + 1.$ 

This has dimension nl (see below).

alm\_array Real or double array of alm coefficients read from

the file. This has dimension (nl,nalm,nsig) – cor-

responding to

 $nl = number of (\ell, m) indices$ 

nalm = 2 for real and imaginary parts of alm coefficients or 4 for above plus corresponding error

values

nsig = number of signals to be written (1 for any of T E B or 3 if ALL to be written). Each signal

is stored in a separate extension.

fitsfile String containing the name of the file to be read.

signal String defining the signal coefficients to read Valid

options: 'T', 'E', 'B' or 'ALL'

(default: 'T').

#### KEYWORDS

HDR= String array containing the primary header read

from the FITS file.

/HELP If set, the routine documentation header is shown

and the routine exits

LMAX= Largest  $\ell$  multipole to be output

LMIN= Smallest  $\ell$  multipole to be output. If LMIN (resp.

LMAX) is below (above) the range of l's present

in the file, it will be silently ignored

XHDR= String array containing the read extension

header(s). If ALL signals are required, then the three extension headers are returned appended

into one string array.

**DESCRIPTION** fits 2 alm reads binary table extension(s) which contain the  $a_{\ell m}$  coefficients (and associated errors if present) from a FITS file. FITS headers can also optionally be read from the input file.

#### RELATED ROUTINES

This section lists the routines related to fits2alm.

idl version 6.4 or more is necessary to run fits2alm.

alm2fits provides the complimentary routine to write  $a_{\ell m}$ 

coefficients into a FITS file.

alm\_i2t, alm\_t2i these facilities turn indexed lists of  $a_{\ell m}$  into 2D

a(l,m) tables and back

index2lm converts the index  $i = \ell^2 + \ell + m + 1$  returned by

fits2alm into  $\ell$  and m

lm2index converts  $(\ell, m)$  vectors into  $i = \ell^2 + \ell + m + 1$ 

fits2cl routine to read/compute  $C(\ell)$  power spectra from

a file containing  $C(\ell)$  or  $a_{\ell m}$  coefficients

ianafast, isynfast IDL routine providing  $a_{\ell m}$  coefficients file to be

read by fits2alm.

alteralm, anafast, synfast F90 facilities providing  $a_{\ell m}$  coefficients file to be

read by fits2alm.

fits2alm 49

## **EXAMPLE:**

fits2alm, index, alm, 'alm.fits', HDR = hdr, XHDR = xhdr

fits 2alm reads from the input FITS file alm.fits the  $a_{\ell m}$  coefficients into the variable alm with optional headers passed by the string variables hdr and xhdr. Upon return index will contain the value of  $\ell^2 + \ell + m + 1$  for each  $a_{\ell m}$  found in the file.

## fits2cl

#### Location in HEALPix directory tree: <a href="mailto:src/idl/fits/fits2cl.pro">src/idl/fits/fits2cl.pro</a>

This IDL facility provides a means to read from a FITS file an ascii or binary table extension containing power spectrum  $(C(\ell))$  or spherical harmonics  $(a_{\ell m})$  coefficients, and returns the corresponding power spectrum  $(C(\ell) = \sum_m a_{\ell m} a_{\ell m}^* / (2\ell + 1))$ . Reads primary and extension headers if required. The facility is intended to enable the user to read the output from the **HEALPix** facility **anafast**.

## **FORMAT**

IDL> fits2cl, cl\_array, [fitsfile, EXTENSION= , HDR= , /HELP, /INTERACTIVE, LLFACTOR=, MULTIPOLES=, /PLANCK1=, /PLANCK2=, /PLANCK3=, /RSHOW, /SHOW, /SILENT=, /WMAP1=, /WMAP5=, /WMAP7=, XHDR=]

## **QUALIFIERS**

cl array

real array of  $C_{\ell}$  coefficients read or computed from the file. The output dimension depends on the contents of the file. This has dimension either (lmax+1,9) given in the sequence T E B TxE TxB ExB ExT BxT BxE **or** (lmax+1,6) given in the sequence T E B TxE TxB ExB **or** (lmax+1,4) for T E B TxE **or** (lmax+1) for T alone.

The convention for the power spectrum is that it is not normalised by the Harrison-Zeldovich (flat) spectrum.

fitsfile

String containing the name of the FITS file to be read. The file contains either  $C(\ell)$  power spectra or  $a_{\ell m}$  coefficients. In either cases,  $C(\ell)$  is returned. If fitsfile is not set, then /PLANCK1, /PLANCK2, /PLANCK3, /WMAP1, /WMAP5 or /WMAP7 must be set.

fits2cl 51

**KEYWORDS** EXTENSION= extension unit to be read from FITS file: either its 0-based ID number (ie, 0 for first extension after primary array) or the case-insensitive value of its EXTNAME keyword. HDR =String array containing on output the primary header read from the FITS file. /HELP If set, produces an extended help message (using the doc library IDL command). /INTERACTIVE If set, the plots generated by /SHOW and /RSHOW options are produced using iPlot routine, allowing for interactive cropping, zooming and annotation of the plots. This requires IDL 6.4 or newer to work properly. LLFACTOR =vector containing on output the factor  $\ell(\ell+1)/2\pi$ which is often applied to  $C(\ell)$  to flatten it for plotting purposes MULTIPOLES =vector containing on output the multipoles  $\ell$  for which the power spectra are provided. They are either - read from the file (1st column in the Planck for-- or generated by the routine (assuming that all multipoles from 0 to lmax included are provided). /PLANCK1 If set. and fitsfile is not vided. then Planck 2013+external data best fit model (!healpix.path.test+-'planck2013ext lcdm cl v1.fits' which matches !healpix.path.test+'cl\_planck1.fits') defined up to lmax=4500, is read. See !healpix.path.test+'README' for details /PLANCK2 If set. and fitsfile is not provided. then Planck 2015 a data model best fit (!healpix.path.test+-'planck2015 lcdm cl v2.fits' which matches !healpix.path.test+'cl\_planck2.fits') defined up to lmax=4900, is read. See !healpix.path.test+'README' for details

/PLANCK3

If

vided,

set.

and

then

fitsfile

Planck

not

2018

pro-

data

best fit model (!healpix.path.test+-'planck2018 lcdm cl v3.fits' which matches !healpix.path.test+'cl\_planck3.fits') defined up to lmax=5000, is read. See !healpix.path.test+'README' for details /RSHOW If set, the raw power spectra  $C(\ell)$  read from the file are plotted /SHOW If set, the rescaled power spectra  $\ell(\ell+1)C(\ell)/2\pi$ are plotted /SILENT If set, no message is issued during normal execution /WMAP1 If set, and fitsfile is not provided, then one WMAP-1yr best fit model (!healpix.path.test+-'wmap lcdm pl model yr1 v1.fits' which currently matches !healpix.path.test+'cl.fits') defined up to lmax=3000, is read. See !healpix.path.test+'README' for details /WMAP5 If set, and fitsfile is not provided, then one WMAP-5yr best fit model (!healpix.path.test+-'wmap lcdm sz lens wmap5 cl v3.fits' which matches !healpix.path.test+'cl\_wmap5.fits') defined up to lmax=2000, is read. See !healpix.path.test+'README' for details /WMAP7 If set, and fitsfile is not provided, then one WMAP-7yr best fit model (!healpix.path.test+-'wmap lcdm sz lens wmap7 cl v4.fits' which matches !healpix.path.test+'cl\_wmap7.fits') defined up to lmax=3726, is read. **Note:** As opposed to the other WMAP spectra mentionned above, it includes a non-vanishing B (or CURL) power spectrum induced by lensing of E (or GRAD) polarization. See !healpix.path.test+'README' for details XHDR =String array containing on output the extension header read from the FITS file.

**DESCRIPTION** fits2cl reads the power spectrum coefficients from a FITS file containing an ascii table extension. Descriptive headers conforming to the FITS convention can also be read from the input file.

fits2cl 53

#### RELATED ROUTINES

This section lists the routines related to fits2cl.

idl	version 6.4 or more is necessary to run fits2cl.
bin_llcl	facility to bin a spectrum read with fits2cl.
bl2fits	facility to write a window function into a FITS file.
cl2fits	provides the complimentary routine to write a power spectrum to a FITS file.
fits2alm, alm2fits	routines to read and write $a_{\ell m}$ coefficients
ianafast	IDL routine computing $C(\ell)$ files that can be read by fits2cl.
anafast	F90 facility computing $C(\ell)$ files that can be read by fits2cl.

#### **EXAMPLE:**

fits2cl reads a power spectrum  $C(\ell)$  from the input FITS file \$HEALPIX/test/cl.fits into the variable pwrsp, with optional headers passed by the string variables hdr and xhdr. The multipoles  $\ell$  and factors  $\ell(\ell+1)/2\pi$  are read into 1 and fl1 respectively.  $\ell(\ell+1)C(\ell)/2\pi$  vs  $\ell$  is then plotted.

## gaussbeam

Location in HEALPix directory tree: src/idl/misc/gaussbeam.pro

This IDL facility provides the window function in  $\ell$  space for a gaussian axisymmetric beam of given FWHM.

**FORMAT** IDL> beam=GAUSSBEAM(Fwhm, [, Dim, HELP=])

**QUALIFIERS** 

Fwhm Full Width Half Maximum of the gaussian beam,

in arcmin (scalar real)

Lmax the window function is computed for the multi-

poles  $\ell$  in  $\{0,...,Lmax\}$ 

Dim scalar integer, optional.

If absent or set to 0 or 1, the output has size

(Lmax+1) and is the temperature beam;

if set to  $2 \leq \text{Dim} \leq 4$ , the output has size

(Lmax+1,Dim) and contains in that order:

the TEMPERATURE beam,

the GRAD/ELECTRIC polarization beam the CURL/MAGNETIC polarization beam

the TEMPERATURE\*GRAD beam

HELP= if set, prints out the help header and exits

 $\overline{\mathbf{DESCRIPTION}}_{\mathrm{gaussbeam}}$  computes the  $\ell$  space window function of a gaussian beam of FWHM Fwhm. For a sky of underlying power spectrum  $C(\ell)$  observed with beam of given FWHM, the measured power spectrum will be  $C(\ell)_{\text{meas}} = C(\ell)B(\ell)^2$  where  $B(\ell)$  is given by gaussbeam (Fwhm, Lmax). The polarization beam is also provided (when Dim > 1) assuming a perfectly co-polarized beam (eg, Challinor et al 2000, astro-ph/0008228)

#### RELATED ROUTINES

gaussbeam 55

This section lists the routines related to **gaussbeam**.

idl version 6.4 or more is necessary to run gaussbeam healpixwindow computes the  $\ell$  space window function associated with a **HEALPix** pixel size

synfast f90 code to generate CMB maps of given power spectrum convolved with a gaussian beam f90 code to smooth existing **HEALPix** maps with

a gaussian beam

anafast f90 code to compute the power spectrum of a

**HEALPix** sky map

#### **EXAMPLE:**

beam = gaussbeam(5.,1200)

beam contains the window function in  $\{0,...,1200\}$  of a gaussian beam of fwhm 5 arcmin

## getdisc\_ring

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/getdisc\_ring.pro">src/idl/toolkit/getdisc\_ring.pro</a>
This routine is obsolete. Use <a href="mailto:query\_disc">query\_disc</a> instead.

getsize fits 57

## getsize\_fits

Location in HEALPix directory tree: <a href="mailto:src/idl/fits/getsize\_fits.pro">src/idl/fits/getsize\_fits.pro</a>

This IDL function reads the number of maps and/or the pixel ordering of a FITS file containing a **HEALPix** map.

FORMAT IDL> var = GETSIZE\_FITS (File, [Nmaps=, Nside=, Mlpol=, Ordering=, Obs\_Npix=,

Type=, Header=, Extension=, /Help])

## **QUALIFIERS**

File name of a FITS file containing the **HEALPix** map(s).

var contains on output the number of pixels stored in a map FITS file. Each pixel is counted only once (even if several information is stored on each of them, see nmaps). Depending on the data storage format, result may be:

- equal or smaller to the number Npix of Healpix pixels available over the sky for the given resolution (Npix = 12\*nside\*nside)

- equal or larger to the number of non blank pixels (obs npix)

Nmaps= contains on output the number of maps in the file

Nside = contains on output the **HEALPix** resolution parameter  $N_{\text{side}}$ 

Mlpol= contains on output the maximum multipole used to generate the

map

Ordering contains on output the pixel ordering scheme: either 'RING' or

'NESTED'

Obs\_Npix= contains on output the number of non blanck pixels. It is set to -1

if it can not be determined from header

Type= Healpix/FITS file type

<0: file not found, or not valid

0: image only fits file, deprecated Healpix format (var =  $12N_{\text{side}}^2$ )

1: ascii table, generally used for C(l) storage

2 : binary table : with implicit pixel indexing (full sky) (var =  $12N_{\text{side}}^2$ )

3 : binary table : with explicit pixel indexing (generally cut sky) (var  $\leq 12N_{\rm side}^2$ )

999: unable to determine the type

Header= contains on output the FITS extension header

Extension= extension unit to be read from FITS file: either its 0-based ID

number (ie, 0 for first extension after primary array) or the case-

insensitive value of its EXTNAME keyword.

## **KEYWORDS**

HELP =if set, an extensive help is displayed and no file is

read

**DESCRIPTION** getsize\_fits gets the number of pixels in a FITS file. If the file follows the **HEALPix** standard, the routine can also get the resolution parameter Nside, the ordering scheme, ..., and can determine the type of data set contained in the file.

#### RELATED ROUTINES

This section lists the routines related to getsize fits.

idl version 6.4 or more is necessary to run getsize fits

This **HEALPix** IDL facility can be used to read read fits map

in maps written by getsize fits.

This IDL routine (included in **HEALPix** packsxaddpar

age) can be used to update or add FITS keywords

to Header

This **HEALPix** IDL routine can be used to rereorder

order a map from NESTED scheme to RING

scheme and vice-versa.

write\_fits\_sb routine to write multi-column binary FITS table

#### **EXAMPLE:**

npix = getsize fits(!healpix.directory+'/test/map.fits', nside=nside, \$ mlpol=lmax, type=filetype) print, npix, nside, lmax, filetype

getsize\_fits 59

should produce something like 196608 128 256 2

meaning that the map contained in that file has 196608 pixels, the resolution parameter is nside=128, the maximum multipole was 256, and this a full sky map (type 2).

## gnomcursor

#### Location in HEALPix directory tree: src/idl/visu/gnomcursor.pro

This IDL facility provides a point-and-click interface for finding the astronomical location, value and pixel index of the pixels nearest to the pointed position on a gnomonic projection of a **HEALPix** map.

#### **FORMAT** GNOMCURSOR, IDL> cursor type=. file out=

## **QUALIFIERS**

see mollcursor

**DESCRIPTION**gnomcursor should be called immediately after gnomview. It gives the longitude, latitude, map value and pixel number corresponding to the cursor position in the window containing the map generated by gnomview. For more details, or in case of problems under Mac OS X, see mollcursor.

#### RELATED ROUTINES

This section lists the routines related to **gnomcursor**.

see mollcursor

#### **EXAMPLE:**

gnomcursor

After gnomview has read in a map and generated its gnomonic projection, gnomcursor is run to determine the position and flux of bright synchrotron sources, for example.

gnomview 61

## gnomview

Location in HEALPix directory tree: src/idl/visu/gnomview.pro

This IDL facility provides a means to visualise a Gnomonic projection (radial projection onto a tangent plane) of **HEALPix** and COBE Quad-Cube maps in an IDL environment. It also offers the possibility to generate GIF, JPEG, PDF, PNG and Postscript color-coded images of the projected map. The projected (but not color-coded) data can also be output in FITS files and IDL arrays.

## **FORMAT**

IDL> GNOMVIEW, File [, Select] [, INH=, BAD\_COLOR=, BG\_COLOR=, CHARSIZE=, CHARTHICK=, COLT=, COORD=, /CROP, CUS-TOMIZE=, DEFAULT\_SETTINGS=, EXECUTE=, FAC-TOR=, FG\_COLOR=, FITS=, /FLIP, GAL\_CUT=, GIF=, GLSIZE=, GRATICULE=, /HALF\_SKY, HBOUND=, /HELP, /HIST\_EQUAL, HXSIZE=, IGLSIZE=, IGRATIC-ULE=, JPEG=, LATEX=, /LOG, MAP\_OUT=, MAX=, MIN=, /NESTED, /NO\_DIPOLE, /NO\_MONOPOLE, /NOBAR, /NOLABELS, /NOPOSITION, OFFSET=, OUT-LINE=, PDF=, PFONTS=, PNG=, POLARIZATION=, /PREVIEW, PS=, PXSIZE=, PYSIZE=, RESO ARCMIN=, RETAIN=, ROT=, /SAVE, /SHADED, /SILENT, SIL-HOUETTE=, STAGGER=, SUBTITLE=, TITLEPLOT=, TRANSPARENT=, TRUECOLORS=, UNITS=, DOW=, XPOS=, YPOS=

## **QUALIFIERS**

## **KEYWORDS**

For a full list of keywords see mollview

## DESCRIPTION

gnomview reads in a **HEALPix** sky map in FITS format and generates a gnomic (or gnomonic) projection of it, that can be visualized on the screen or exported in a GIF, JPEG, PNG, PDF or Postscript file. gnomview allows the selection of the coordinate system, map size, color table, color bar inclusion, linear, log, hybrid or histogram equalised color scaling, maximum and minimum range for the plot, plot-title *etc*. It also allows the representation of the polarization field.

#### RELATED ROUTINES

This section lists the routines related to **gnomview**.

see mollview

## EXAMPLES: #1

```
gnomview, 'planck100GHZ-LFI.fits', rot=[160,-30], reso_arcmin=2., $
   pxsize = 500., $
   title='Simulated Planck LFI Sky Map at 100GHz', $
   min=-100,max=100
```

gnomview reads in the map 'planck100GHZ-LFI.fits' and generates an output image of the size of  $500\times500$  screen pixels, with a resolution of 2 arcmin/screen pixel at the center. The temperature scale has been set to lie between  $\pm$  100, and the units will show as  $\mu$ K. The title 'Simulated Planck LFI Sky Map at 100GHz' has been appended to the image. The map is centered at (l=160, b=-30)

## EXAMPLES: #2

gnomview 63

```
map = findgen(48)
triangle= create_struct('coord','G','ra',[0,80,0],'dec',[40,45,65])
gnomview,map,/online,res=25,graticule=[45,30],rot=[10,20,30],$
   title='Gnomic projection',subtitle='gnomview', $
   outline=triangle
```

makes a gnomic projection of map (see Figure 1b on page 122) after an arbitrary rotation, with a graticule grid (with a  $45^{\circ}$  step in longitude and  $30^{\circ}$  in latitude) and an arbitrary triangular outline

## healpix\_doc

Location in HEALPix directory tree: <a href="mailto:src/idl/misc/healpix\_doc.pro">src/idl/misc/healpix\_doc.pro</a>

This IDL facility displays HTML or PDF **HEALPix** documentation

FORMAT IDL> healpix\_doc, [HTML=| PDF=| EPUB=] [, HELP=, WHOLE=]

## **KEYWORDS**

HELP= if set, an extensive help on healpix\_doc is dis-

played.

EPUB if set, the (whole) **HEALPix** EPUB documenta-

tion is shown with an ebook reader.

HTML= if set, the **HEALPix** (IDL) HTML documenta-

tion is shown with a web browser. If the browser

is already in use, a new tab is open.

PDF= if set, the **HEALPix** (IDL) PDF documentation

is shown with a pdf viewer.

Either EPUB, HTML or PDF must be set.

WHOLE= if set, the whole **HEALPix** documentation is ac-

cessible, not just the IDL related part.

**DESCRIPTION** healpix\_doc calls the script \$HEALPIX/healpix\_doc to open either the EPUB, HTML or PDF **HEALPix** documentation. The content of the !healpix system variable is used to determine the documentation path.

#### RELATED ROUTINES

This section lists the routines related to **healpix** doc.

idl version 6.4 or more is necessary to run healpix doc.

!HEALPIX

IDL system variable used by healpix\_doc to locate the documentation.

## EXAMPLES: #1

healpix\_doc, /html, /whole

will open the whole **HEALPix** HTML documentation in a web browser.

## EXAMPLES: #2

healpix\_doc, /pdf

will open the IDL related  $\mathbf{HEALPix}$  PDF documentation.

## EXAMPLES: #3

healpix\_doc, /epub

will open the whole **HEALPix** EPUB documentation.

## healpixwindow

Location in HEALPix directory tree: src/idl/misc/healpixwindow.pro

This IDL facility provides the window function in  $\ell$  associated with the Healpix pixel of resolution Nside.

## FORMAT IDL> wpix=HEALPIXWINDOW(Nside Dim, DIRECTORY=, HELP=, LMAX=])

## **QUALIFIERS**

Nside resolution parameter

Wpix the pixel window function, computed for the mul-

tipoles  $\ell$  in  $\{0,...,LMAX\}$ 

Dim scalar integer, optional.

If absent or set to 0 or 1, the output has size (LMAX+1) and is the temperature window func-

tion;

if set to  $2 \leq \text{Dim} \leq 4$ , the output has size

(LMAX+1,Dim) and contains in that order: the TEMPERATURE window function, the GRAD/ELECTRIC polarization one the CURL/MAGNETIC polarization one

the TEMPERATURE\*GRAD one.

DIRECTORY= directory in which the precomputed pixel window

file is looked for.

(default: !healpix.path.data)

HELP= if set, a documentatin header is printed out, and

the routine exits

LMAX= maximum multipole included in Wpix. Must be

in [0, 4 Nside]. Negative values are ignored.

(default: 4 Nside).

healpixwindow 67

 $\mathbf{DESCRIPTION}$  healpixwindow computes the  $\ell$  space window function due to the finite size of the **HEALPix** pixels. The typical size of a pixel (square root of its uniform surface area) is  $\sqrt{3/\pi} 3600/N_{\rm side}$ arcmin. If a unpixelated sky has a power spectrum  $C(\ell)$ , the same sky pixelated with a resolution parameter Nside will have the power spectrum  $C(\ell)_{pix} = C(\ell)W(\ell)^2$  where  $W(\ell)$  is given by healpixwindow(Nside). The polarized pixel window function is also provided (when Dim > 1). This routine reads some FITS files located in the subdirectory data/ of the HEALPix distribution, unless the keyword Directory is set otherwise.

#### RELATED ROUTINES

This section lists the routines related to **healpixwindow**.

idl version 6.4 or more is necessary to run healpixwin-

computes the  $\ell$  space window function associated gaussbeam

with a gaussian beam

F90 code to generate CMB maps of given power synfast

spectrum at a given resolution (=pixel size)

anafast F90 code to compute the power spectrum of a

**HEALPix** sky map

#### **EXAMPLE:**

wpix = healpixwindow(256)

wpix contains the window function in  $\{0,...,1024\}$  of the **HEALPix** pixel with resolution parameter 256 (pixel size of 13.7 arcmin)

## help\_st

Location in HEALPix directory tree: <a href="mailto:src/idl/misc/help\_st.pro">src/idl/misc/help\_st.pro</a>

This IDL facility provides some HELP-like information on any IDL variable, and especially on sub-structures.

## **FORMAT**

IDL> help\_st, Var

## **QUALIFIERS**

Var

IDL variable, of any kind

**DESCRIPTION**If Var is an IDL structure, help\_st does a recursive HELP,/STRUCTURES on Var and each of its substructure, otherwise it does the equivalent of HELP, Var (see respectively Examples #1 and #2 below)

#### RELATED ROUTINES

This section lists the routines related to **help\_st**.

idl

version 6.4 or more is necessary to run help\_st.

## EXAMPLES: #1

init\_healpix ; make sure that !healpix is defined
help, /structure, !healpix
help\_st, !healpix

help\_st 69

the example above compares the output of help,/structures which only describes the top structure:

```
** Structure <151cef8>, 7 tags, length=528, data length=524, refs=2:
 VERSION
            STRING
                     3.40
            STRING
                     '2018-01-01'
 DATE
 DIRECTORY
            STRING
                     '/home/user/Healpix'
 PATH
            STRUCT
                     -> <Anonymous> Array[1]
 NSIDE
            LONG
                     Array[30]
 BAD_VALUE
            FLOAT
                     -1.63750e+30
 COMMENT
            STRING Array[15]
and help_st, which describes each sub-structure:
** Structure <151cef8>, 7 tags, length=528, data length=524, refs=2:
 .VERSION
                          3.40
                 STRING
 .DATE
                 STRING
                          ,2018-01-01,
 .DIRECTORY
                 STRING
                          '/home/user/Healpix'
 .PATH.BIN.CXX
                 STRING
                          '/home/user/Healpix/src/cxx/generic_gcc/bin/'
 .PATH.BIN.F90
                 STRING
                          '/home/user/Healpix/bin/'
 .PATH.DATA
                 STRING
                          '/home/user/Healpix/data/'
 .PATH.DOC.HTML
                 STRING
                          '/home/user/Healpix/doc/html/'
                          '/home/user/Healpix/doc/pdf/'
 .PATH.DOC.PDF
                 STRING
 .PATH.SRC
                 STRING
                          '/home/user/Healpix/src/'
 .PATH.TEST
                 STRING
                          '/home/user/Healpix/test/'
                 LONG
                          Array[30]
 .NSIDE
 .BAD_VALUE
                 FLOAT
                          -1.63750e+30
 .COMMENT
                 STRING
                          Array[15]
```

## EXAMPLES: #2

```
a=0
help,a+1
help st, a+1
```

```
will print out
<Expression> INT = 1
A+1 INT = 1
```

## hpx2dm

Location in HEALPix directory tree: src/idl/visu/hpx2dm.pro

This IDL facility provides a means to turn a **HEALPix** data set into a DomeMaster compliant image (azimuthal equidistant projection of the half-sphere in a PNG or lossless JPEG file) that can be projected on a planetarium. See eg <a href="http://fulldome.ryanwyatt.net/fulldome\_domemasterSpec\_v05.pdf">http://fulldome.ryanwyatt.net/fulldome\_domemasterSpec\_v05.pdf</a>

FORMAT IDL> hpx2dm, File, [ Select, ] [ /HELP, JPEG=, PNG=, PREVIEW=, PXSIZE=, +

most of azeqview keywords...

hpx2dm 71

## **QUALIFIERS**

File Required

name of a FITS file containing the **HEALPix** map in an extension or in the image field,

or name of an *online* variable (either array or structure) containing the **HEALPix** map (See note below);

if Save is set: name of an IDL saveset file containing the **HEALPix** map stored under the variable data

(default: none)

Select Optional

column of the BIN FITS table to be plotted, can be either

- a name : value given in TTYPEi of the FITS file

NOT case sensitive and can be truncated, (only letters, digits and underscore are valid)

 $\boldsymbol{-}$  an integer : number i of the column containing the data, starting with

1 (also valid if File is an online array)

( $\mathbf{default:}\ 1$  for full sky maps, 'SIGNAL' column for FITS files containing

cut sky maps)

## **KEYWORDS**

JPEG= name of the output lossless JPEG file

PNG= name of the output PNG file

/PREVIEW if set, the output JPEG or PNG file will be pre-

viewed

/HELP Prints out the documentation header

PXSIZE= number of pixels in each dimension of the square

output image

/ASINH,

COLT=, COORD=, FACTOR=, /FLIP, HBOUND=,

/HIST\_EQUAL, /LOG, MAX=, MIN=, /NESTED, OFFSET=,

/QUADCUBE, ROT=, SAVE=, /SILENT,

TRUECOLORS= those keywords have the same meaning as in aze-

qview and mollview

# **DESCRIPTION**hpx2dm reads in a **HEALPix** sky map in FITS format or from a memory array and generates a PNG or JPEG file containing a DomeMaster compliant map (azimuthal equidistant projection of the half-sky).

## RELATED ROUTINES

This section lists the routines related to hpx2dm.

azeqview performs Azimuthal Equidistant projection re-

quired by hpx2dm.

hpx2gs turns Healpix maps into GoogleEarth, GoogleSky

or Oculus VR compatible images

hpx2gs 73

# hpx2gs

Location in HEALPix directory tree: src/idl/visu/hpx2gs.pro

This IDL facility provides a means to turn a **HEALPix** map into a image that can be visualized with Google Earth or Google Skyas well as with Oculus VR headsets.

FORMAT

IDL> hpx2gs, File, [ Select, ] [ COORD\_IN=, /HELP, KML=, PNG=, RESO\_ARCMIN=, SUBTITLE=, TITLEPLOT=,+ most of cartview keywords... ]

#### QUALIFIERS

File Required

name of a FITS file containing the **HEALPix** map in an extension or in the image field,

or name of an *online* variable (either array or structure) containing the **HEALPix** map (See note below);

if Save is set: name of an IDL saveset file containing the **HEALPix** map stored under the variable data

(default: none)

Select Optional

column of the BIN FITS table to be plotted, can be either

- a name : value given in TTYPEi of the FITS file

NOT case sensitive and can be truncated, (only letters, digits and underscore are valid)

- an integer: number i of the column containing the data, starting with

1 (also valid if File is an online array)

(default: 1 for full sky maps, 'SIGNAL' column for FITS files containing

cut sky maps)

#### **KEYWORDS**

COORD\_IN= 1-character scalar, describing the input data coor-

dinate system:

either 'C' or 'Q' : Celestial 2000 = eQuatorial,

'E' : Ecliptic, 'G' : Galactic.

If set, it will over-ride the coordinates read from the FITS file header (when applicable). In absence of information, the input coordinates is assumed to be celestial.

The data will be rotated so that the output coordinates are Celestial, as expected by Google Sky

/HELP Prints out the documentation header

KML= Name of the KML file to be created (if the .kml

suffix is missing, it will be added automatically). Used only by Google Earth and Google Sky.

(default: 'hpx2googlesky.kml')

PNG= Name of the PNG overlay file to be created. Only

to be used if you want the filename to be different from the default ((default: same as KML file,

with a .png suffix instead of .kml))

hpx2gs 75

RESO\_ARCMIN= Pixel angular size in arcmin (at the equator) of

the cartesian map generated (**default:** 30)

SUBTITLE= information on the data, will appear in KML file

GroundOverlay description field

TITLEPLOT= information on the data, will appear in KML file

GroundOverlay name field

/ASINH,

COLT=, FACTOR=, /FLIP, GLSIZE=, GRATICULE=, HBOUND=,

/HIST\_EQUAL, IGLSIZE=, IGRATICULE=, /LOG, MAX=, MIN=,

/NESTED, OFFSET=,

OUTLINE=, POLARIZATION=, /PREVIEW,

/QUADCUBE, SAVE=, /SILENT,

TRUECOLORS= those keywords have the same meaning as in

cartview and mollview

**DESCRIPTION**hpx2gs reads in a **HEALPix** sky map in FITS format or from a memory array and generates a cartesian (equirectangular) projection of it in a PNG file, as well as a Google Sky compatible KML file. Missing or unobserved pixels in the input data will be totally 'transparent' in the output file.

#### RELATED ROUTINES

This section lists the routines related to **hpx2gs**.

see cartview

hpx2dm turns Healpix maps into DomeMaster images

#### **EXAMPLE:**

map = findgen(48)

hpx2gs, map, kml='my\_map.kml',title='my map in Google'

produces in my\_map.kml and in my\_map.png an image of the input map that can be seen with Google Sky. To do so, start GoogleEarth or GoogleSky and open my\_map.kml. Under Mac-OSX, simply type open my\_map.kml on the command line.

## ialteralm

#### Location in HEALPix directory tree: src/idl/interfaces/ialteralm.pro

This IDL facility provides an interface to F90 'alteralm' facility. This program can be used to modify a set of  $a_{\ell m}$  spherical harmonics coefficients, as those extracted by ianafast or simulated by isynfast, before they are used as constraints on a isynfast run. Currently the alterations possible are

- rotation (using Wigner matrices) of the  $a_{\ell m}$  from the input coordinate system to any other standard astrophysical coordinate system. The resulting  $a_{\ell m}$  can be used with e.g. synfast to generate a map in the new coordinate system.
- removal of the pixel and beam window functions of the input  $a_{\ell m}$  (corresponding to the pixel size and beam shape of the map from which they were extracted) and implementation of an arbitrary pixel and beam window function.

$$a_{\ell m}^{\rm OUT} = a_{\ell m}^{\rm IN} \frac{B^{\rm OUT}(\ell) P^{\rm OUT}(\ell)}{B^{\rm IN}(\ell) P^{\rm IN}(\ell)},\tag{6}$$

where  $P(\ell)$  is the pixel window function, and  $B(\ell)$  is the beam window function (assuming a circular beam) or any other  $\ell$  space filter (eg, Wiener filter). For an infinitely small pixel (or beam) one would have  $P(\ell) = 1$  (resp.  $B(\ell) = 1$ ) for any  $\ell$ .

#### **FORMAT**

IDL> IALTERALM, alm\_in, alm\_out, [beam\_file\_in, beam\_file\_out, binpath=, co-ord\_in, coord\_out, epoch\_in, epoch\_out, fwhm\_arcmin\_in, fwhm\_arcmin\_out, /help, keep\_tmp\_files=, lmax\_out, nlmax\_out, nside\_in, nside\_out, nsmax\_in, nsmax\_out, /silent, tmpdir=, windowfile\_in, winfiledir\_in, windowfile\_out, winfiledir\_out]

ialteralm 77

## **QUALIFIERS**

alm\_in alm out

required input: input  $a_{\ell m}$ , must be a FITS file required output: output  $a_{\ell m}$ , must be a FITS file

#### **KEYWORDS**

binpath= full path to back-end routine (default: \$HEXE/alteralm, then

\$HEALPIX/bin/alteralm)

– a binpath starting with / (or  $\backslash$ ), or \$ is interpreted as absolute

 a binpath starting with ./ is interpreted as relative to current directory

– all other binpaths are relative to \$HEALPIX

beam\_file\_in= Beam window function of input  $a_{\ell m}$ , either a FITS file or an array (see "Beam window function files"

section in the **HEALPix** Fortran Facilities document). If present, will override fwhm\_arcmin\_in (default: value of BEAM LEG keyword read

from alm\_in)

beam\_file\_out= Beam window function of output alm, either

a FITS file or an array (see beam\_file\_in. If present and non-empty, will override fwhm arcmin out (default: " (empty string, no

beam window applied))

coord\_in= Astrophysical coordinates system used to com-

pute input  $a_{\ell m}$ . Case-insensitive single letter code. Valid choices are 'g', 'G' = Galactic, 'e', 'E' = Ecliptic, 'c', 'q', 'C', 'Q' = Celestial/eQuatorial. (**default:** value of COORDSYS keyword read

from alm\_in)

coord\_out= Astrophysical coordinates system of output alm.

(default: coord\_in )

epoch\_in= Astronomical epoch of input coordinates

(coord\_in) (default: 2000.0)

epoch\_out= Astronomical epoch of output coordinates

(coord\_out) (default: same as epoch\_in)

fwhm\_arcmin\_in= Full Width Half-Maximum in arcmin of Gaussian beam applied to map from which are obtained in-

	put $a_{\ell m}$ . ( <b>default:</b> value of FWHM keyword in alm_in)
$fwhm\_arcmin\_out =$	FWHM in arcmin to be applied to output alm. (default: fwhm_arcmin_in)
/help	if set, prints extended help
/keep_tmp_files	if set, temporary files are not discarded at the end of the run
$lmax\_out=, nlmax\_out=$	maximum multipole of output alm
nside_in=, nsmax_in=	HEALPix resolution parameter of map from which were computed input $a_{\ell m}$ (default: determined from alm_in)
nside_out=,nsmax_out=	HEALPix resolution parameter Nside whose window function will be applied to output alm. Could be set to 0 for infinitely small pixels (no window) (default: same as input nsmax_in)
/silent	if set, works silently
$\operatorname{tmpdir}=$	directory in which are written temporary files (default: IDL_TMPDIR (see IDL documentation))
windowfile_in=	FITS file containing pixel window for nside_in (default: determined automatically by back-end routine). Do not set this keyword unless you really know what you are doing
winfiledir_in=	directory where windowfile_in is to be found (default: determined automatically by back-end routine). Do not set this keyword unless you really know what you are doing
$window file\_out =$	FITS file containing pixel window for nside_out (default: determined automatically by back-end routine). Do not set this keyword unless you really know what you are doing
$\ winfile dir\_out =$	directory where windowfile_out is to be found (default: determined automatically by back-end routine). Do not set this keyword unless you really know what you are doing

**DESCRIPTION** ialteralm is an interface to 'alteralm' F90 facility. It requires some disk space on which to write the parameter file and the other temporary files. Most data can be provided/generated as an external FITS file, or as a memory array.

ialteralm 79

#### RELATED ROUTINES

This section lists the routines related to **ialteralm**.

idl version 6.4 or more is necessary to run ialteralm.

alteralm F90 facility called by ialteralm.

ianafast IDL Interface to F90 anafast and C++

 $an a fast\_cxx$ 

iprocess\_mask
ismoothing
IDL Interface to F90 process\_mask
IDL Interface to F90 smoothing
isynfast
IDL Interface to F90 synfast

#### **EXAMPLE:**

```
ialteralm, !healpix.path.test+'alm.fits', '/tmp/alm_equat.fits', $
coord_in='g',coord_out='q'
isynfast, 0, alm_in='/tmp/alm_equat.fits', '/tmp/map_equat.fits'
mollview,'/tmp/map_equat.fits',1
mollview,'/tmp/map_equat.fits',2
```

This example script reads the test (polarised)  $a_{\ell m}$  located in \$HEALPIX/test/alm.fits and rotates them from Galactic to Equatorial coordinates, it then synthetizes a map out of those, and finally plots its I and Q Stokes components (in Equatorial coordinates)

## ianafast

#### Location in HEALPix directory tree: <a href="mailto:src/idl/interfaces/ianafast.pro">src/idl/interfaces/ianafast.pro</a>

This IDL facility provides an interface to 'anafast' F90 and 'anafast\_cxx' C++ facilities. It can be used to produce the Spherical Harmonics coefficients ( $a_{\ell m}$  of a **HEALPix** map (or pair of maps) and/or the resulting auto (or cross) power spectra  $C(\ell)$ .

## **FORMAT**

IDL> IANAFAST, map1\_in[, cl\_out, alm1\_out=, alm2\_out=, binpath=, cxx=, double=, help=, healpix\_data=, iter\_order=, keep\_tmp\_files=, map2\_in=, mask-file=, nested=, nlmax=, nmmax=, ordering=, plmfile=, polarisation=, regression=, ring=, show\_cl=, simul\_type=, silent=, theta\_cut\_deg=, tmpdir=, weighted=, won=, w8file=, w8dir=]

## **QUALIFIERS**

map1\_in required inpu

cl out

required input: 1st input map, can be a FITS file, or a memory array containing the map to analyze optional output: auto or cross power spectrum  $C(\ell)$ , can be a FITS file or a memory array

## **KEYWORDS**

alm1\_out= output alm of 1st map, must be a FITS file

(default: alm not kept)

alm2\_out= output alm of 2nd map (if any, must be a FITS

file) (default: alm not kept)

binpath= full path to back-end routine (default: \$HEXE/anafast, then \$HEALPIX-

ianafast 81

	/bin/anafast or \$HEALPIX/bin/anafast_cxx if cxx is set)
	– a binpath starting with $/$ (or $\backslash$ ), or $\$$ is interpreted as absolute
	<ul> <li>a binpath starting with ./ is interpreted as relative to current directory</li> <li>all other binpaths are relative to \$HEALPIX</li> </ul>
/cxx	if set, the C++ back-end anafast_cxx is invoked instead of F90 anafast, AND the parameter file is written accordingly
/double	if set, I/O is done in double precision ( <b>default:</b> single precision I/O)
/help	if set, prints extended help
$healpix_data =$	same as w8dir
$iter\_order =$	order of iteration in the analysis ( <b>default:</b> 0)
/keep_tmp_files	if set, temporary files are not discarded at the end of the run
map2_in=	2nd input map (FITS file or array), if provided, Cl_out will contain the cross power spectra of the 2 maps ( <b>default:</b> no 2nd map)
maskfile =	pixel mask (FITS file or array) ( <b>default:</b> no mask)
/nested=	if set, signals that *all* maps and mask read online are in NESTED scheme (does not apply to FITS file), see also /ring and Ordering
nlmax=	maximum multipole of analysis, *required* for C++ anafast_cxx, optional for F90 anafast
nmmax=	maximum degree m, only valid for C++ anafast_cxx ( <b>default:</b> nlmax)
ordering=	either 'RING' or 'NESTED', ordering of online maps and masks, see /nested and /ring
plmfile=	FITS file containing precomputed Spherical Harmonics (deprecated) ( <b>default:</b> no file)
/polarisation	if set analyze temperature $+$ polarization (same as simul_type $=$ 2)
regression=	0, 1 or 2, regress out best fit monopole and/or dipole before alm analysis ( <b>default:</b> 0, analyze raw map)
/ring	see /nested and ordering above
/show_cl	if set, and cl_out is defined, the produced $\ell(\ell+1)C(\ell)/2\pi$ will be plotted

simul\_type= 1 or 2, analyze temperature only or temperature

+ polarization

/silent if set, works silently

theta\_cut\_deg= cut around the equatorial plane

tmpdir= directory in which are written temporary files

(default: IDL\_TMPDIR (see IDL documenta-

tion))

weighted= same as won (default: see won)

won= if set to 0, no weighting applied, if set to 1,

a ring-based quadrature weighting scheme is applied, if set to 2, a pixel-based quadrature weighting scheme is applied. (**default:** 1: apply ring-

based weighting)

w8file= In F90: FITS file containing weights (**default:** de-

termined automatically by back-end routine). Do not set this keyword unless you really know what

you are doing

In C++ (/cxx flag): must be set to full path of weight file, consistent with value of won (or

weighted)

w8dir= In F90 only: directory where the weights are to

be found (default: determined automatically by

back-end routine)

# **DESCRIPTION**ianafast is an interface to 'anafast' F90 and 'anafast\_cxx' C++ facilities. It requires some disk space on which to write the parameter file and the other temporary files. Most data can be provided/generated as an external FITS file, or as a memory

#### RELATED ROUTINES

This section lists the routines related to **ianafast**.

array.

idl version 6.4 or more is necessary to run ianafast.

anafast F90 facility called by ianafast.

anafast cxx C++ called by ianafast.

ialteralm IDL Interface to F90 alteralm

ianafast 83

iprocess\_mask
ismoothing
IDL Interface to F90 process\_mask
IDL Interface to F90 smoothing
isynfast
IDL Interface to F90 synfast

#### **EXAMPLE:**

```
whitenoise = randomn(seed, nside2npix(256))
ianafast, whitenoise, cl, /ring, /silent
plot, cl[*,0]
```

will plot the power spectrum of a white noise map

## index2lm

Location in HEALPix directory tree: src/idl/misc/index2lm.pro

This IDL routine provides a means to convert the  $a_{\ell m}$  index  $i = \ell^2 + \ell + m + 1$  (as returned by eg the fits2alm routine) into  $\ell$  and m.

#### **FORMAT**

IDL> INDEX2LM, index, l, m

## **QUALIFIERS**

index Long array containing on INPUT the index

 $i = \ell^2 + \ell + m + 1.$ 

Long array containing on OUTPUT the order  $\ell$ .

It has the same size as index.

m Long array containing on OUTPUT the degree m.

It has the same size as index.

**DESCRIPTION**index2lm converts  $i = \ell^2 + \ell + m + 1$  into  $(\ell, m)$ . Note that the index i is only defined for  $0 \le |m| \le \ell$ .

#### RELATED ROUTINES

This section lists the routines related to index2lm.

idl version 6.4 or more is necessary to run index2lm.

fits2alm reads a FITS file containing  $a_{\ell m}$  values.

alm2fits writes  $a_{\ell m}$  values into a FITS file.

lm2index routine complementary to index2lm: converts

 $(\ell, m)$  into  $i = \ell^2 + \ell + m + 1$ .

#### **EXAMPLE:**

index2lm, index, 1, m

index2lm 85

will return in 1 and m the order  $\ell$  and degree m such that  ${\tt index} = \ell^2 + \ell + m + 1$ 

## init\_healpix

Location in HEALPix directory tree: <a href="mailto:src/idl/misc/init\_healpix.pro">src/idl/misc/init\_healpix.pro</a>

This IDL facility creates an IDL system variable (!HEALPIX) containing various **HEALPix** related quantities

FORMAT IDL>

IDL> INIT\_HEALPIX [,VERBOSE=]

**KEYWORDS** 

VERBOSE= if set, turn on the verbose mode, giving a short

description of the variables just created.

**DESCRIPTION**init\_healpix defines the IDL system variable and structure !HEALPIX containing several quantities and character string necessary to **HEALPix**, eg: allowed resolution parameters Nside, full path to package directory, package version...

#### RELATED ROUTINES

This section lists the routines related to **init\_healpix**.

idl version 6.4 or more is necessary to rur

init\_healpix.

!HEALPIX IDL system variable defined by init healpix.

EXAMPLES: #1

init\_healpix,/verbose

```
init healpix will create the system variable !Healpix, and give
a short description of the tags available, as shown below
Initializing !HEALPIX system variable
This system variable contains some information on Healpix :
!HEALPIX.VERSION = current version number,
!HEALPIX.DATE = date of release,
!HEALPIX.DIRECTORY = directory containing Healpix package,
!HEALPIX.PATH = structure containing:
!HEALPIX.PATH.BIN = structure containing binary path :
!HEALPIX.PATH.BIN.CXX = C++
!HEALPIX.PATH.BIN.F90 = Fortran90
!HEALPIX.PATH.DATA = path to data subdirectory,
!HEALPIX.PATH.DOC = path to doc subdirectories (.html, .pdf,
.epub),
!HEALPIX.PATH.SRC = path to src subdirectory,
!HEALPIX.PATH.TEST = path to test subdirectory,
!HEALPIX.NSIDE = list of all valid values of Nside parameter,
!HEALPIX.BAD_VALUE = value of flag given to missing pixels in
FITS files,
!HEALPIX.COMMENT = this description.
```

## EXAMPLES: #2

help, !healpix, /structure

will print the content of the !Healpix system structure.

## iprocess\_mask

Location in HEALPix directory tree: src/idl/interfaces/iprocess\_mask.pro

This IDL facility provides an interface to F90 'process\_mask' facility. For a given input binary mask, it can determine the angular distance in Radians of each valid (1 valued) pixel to the closest invalid (0 valued) pixel, with the option of ignoring small clusters of invalid pixels. The distance map can then be used to generate an apodized mask.

#### FORMAT

IDL> IPROCESS\_MASK, mask\_in, distance\_map,[ binpath=, filled\_mask=, /help, hole\_arcmin2=, hole\_pixels=, keep\_tmp\_files=, /nested, ordering=, /ring, /silent, tmpdir=]

## **QUALIFIERS**

mask in

required input: input binary mask. It can be a FITS file, or a memory array containing the mask to process.

distance\_map

optional output: double precision angular distance map in Radians. It can be a FITS file, or a memory array. It will have the same ordering as the input mask.

#### **KEYWORDS**

binpath=

full path to back-end routine (**default:** \$HEXE/process\_mask, then \$HEALPIX/bin/process mask)

- a binpath starting with / (or  $\setminus$ ), or \$ is interpreted as absolute
- a binpath starting with ./ is interpreted as relative to current directory
- all other binpaths are relative to \$HEALPIX

iprocess\_mask 89

$filled_mask =$	optional output mask with holes smaller than
	hole_arcmin2 or hole_pixels filled in. Will have the same ordering as the input mask
/1 1	_
/help	if set, prints extended help
hole_arcmin2	Minimal size (in arcmin <sup>2</sup> ) of invalid regions to be kept (can be used together with hole_pixels, the result will be the largest of the two). (default: 0.0)
hole_pixels	Minimal size (in pixels) of invalid regions to be kept (can be used together with hole_arcmin2, the result will be the largest of the two). (default: 0)
/keep_tmp_files	if set, temporary files are not discarded at the end of the run
/nested	if set, signals that the mask read online is in NESTED scheme (does not apply to FITS file), see also /ring and Ordering
ordering=	either 'RING' or 'NESTED', ordering of online mask, see <a href="mailto://ring.ncbi.nlm.nested">ring</a> and <a href="mailto://nested">nested</a>
/ring	see /nested and Ordering above
/silent	if set, works silently
tmpdir =	directory in which are written temporary files ( <b>default:</b> IDL_TMPDIR (see IDL documentation))

**DESCRIPTION**iprocess\_mask is an interface to 'process\_mask' F90 facility. It requires some disk space on which to write the parameter file and the other temporary files. Most data can be provided/generated as an external FITS file, or as a memory array.

#### RELATED ROUTINES

This section lists the routines related to  ${\bf iprocess\_mask}.$ 

idl	version 6.4 or more is necessary to run iprocess_mask.
process_mask	F90 facility called by iprocess_mask.
ialteralm	IDL Interface to F90 alteralm

ianafast IDL Interface to F90 anafast and C++

 $anafast\_cxx$ 

ismoothing IDL Interface to F90 smoothing isynfast IDL Interface to F90 synfast

#### **EXAMPLE:**

npix = nside2npix(256)
mask = replicate(1, npix) & mask[randomu(seed,100)\*npix] = 0
iprocess\_mask, mask, distance, /ring, /silent
mollview, distance

A binary mask in which 100 randomly located pixels are 0-valued (=invalid) is generated. Then the distance (in Radians) of the valid pixels to the closest invalid pixels is computed and plotted.

ismoothing 91

## ismoothing

Location in HEALPix directory tree: src/idl/interfaces/ismoothing.pro

This IDL facility provides an interface to F90 'smoothing' facility. It can be used to smooth a **HEALPix** map by an arbitrary circular 'beam' defined by its Legendre window function (or its FWHM if it is assumed Gaussian)

#### **FORMAT**

IDL> ISMOOTHING, map1\_in, map2\_out,[ beam\_file=, binpath=, /double, fwhm\_arcmin=, /help, iter\_order=, keep\_tmp\_files=, lmax=, nlmax=, /nested, ordering=, plmfile=, regression=, /ring, simul\_type=, /silent, theta\_cut\_deg=, tm-pdir=, /won, w8file=, w8dir=]

## **QUALIFIERS**

map1\_in

map2\_out

required input: input map, can be a FITS file, or a memory array containing the map to smooth required output: output smoothed map, can be a FITS file, or a memory array

## **KEYWORDS**

beam file=

beam window function, either a FITS file or an array (see "Beam window function files" section in the **HEALPix** Fortran Facilities document).

binpath=

full path to back-end routine (**default:** \$HEXE/smoothing, then \$HEALPIX/bin/smoothing)

- a binpath starting with / (or  $\backslash$ ), or \$ is interpreted as absolute
- a binpath starting with ./ is interpreted as relative to current directory

	– all other bin paths are relative to \$HEALPIX
/double	if set, I/O is done in double precision ( <b>default:</b> single precision I/O)
fwhm_arcmin=	gaussian beam Full Width Half Maximum in arcminutes ( <b>default:</b> 0)
/help	if set, prints extended help
$iter\_order=$	order of iteration in the analysis ( <b>default:</b> $0$ )
/keep_tmp_files	if set, temporary files are not discarded at the end of the run
lmax=, nlmax=	maximum multipole of smoothing ( <b>default:</b> determined by back-end routine (ie, smoothing))
/nested	if set, signals that *all* maps and mask read online are in NESTED scheme (does not apply to FITS file), /ring and Ordering
ordering=	either 'RING' or 'NESTED', ordering of online maps and masks, see /ring and /nested
plmfile=	FITS file containing precomputed Spherical Harmonics (deprecated) ( <b>default:</b> no file)
regression=	0, 1 or 2, regress out best fit monopole and/or dipole before alm analysis ( <b>default:</b> 0, analyze raw map)
/ring	see /nested and Ordering above
simul_type=	1 or 2, analyze temperature only or temperature + polarization
/silent	if set, works silently
$theta\_cut\_deg =$	cut around the equatorial plane
$\operatorname{tmpdir}=$	directory in which are written temporary files (default: IDL_TMPDIR (see IDL documentation))
won=	if set to 0, no weighting applied, if set to 1, a ring-based quadrature weighting scheme is applied, if set to 2, a pixel-based quadrature weighting scheme is applied. ( <b>default:</b> 1: apply ring-based weighting)
w8file=	FITS file containing weights ( <b>default:</b> determined automatically by back-end routine). Do not set this keyword unless you really know what you are doing

ismoothing 93

w8dir= directory where the weights are to be found (**default:** determined automatically by back-end routine)

**DESCRIPTION** is moothing is an interface to 'smoothing' F90 facility. It requires some disk space on which to write the parameter file and the other temporary files. Most data can be provided/generated as an external FITS file, or as a memory array.

#### RELATED ROUTINES

This section lists the routines related to **ismoothing**.

sion

$\operatorname{idl}$	version 6.4 or more is necessary to run ismoothing.	
smoothing	F90 facility called by ismoothing.	
beam2bl	This IDL facility computes a transfer (or window) function $b(l)$ (such as the ones required by ismoothing) for a given circular beam profile $b(\theta)$	
ialteralm	IDL Interface to F90 alteralm	
ianafast	IDL Interface to F90 anafast and C++ anafast_cxx	
iprocess_mask	IDL Interface to F90 process_mask	
isynfast	IDL Interface to F90 synfast	

#### **EXAMPLE:**

```
whitenoise = randomn(seed, nside2npix(256))
ismoothing, whitenoise, rednoise, fwhm=120, /ring, simul=1,/silent
mollview, whitenoise,title='White noise'
mollview, rednoise, title='Smoothed white Noise'
will generate and plot a white noise map and its smoothed ver-
```

## isynfast

#### Location in HEALPix directory tree: src/idl/interfaces/isynfast.pro

This IDL facility provides an interface to F90 'synfast' facility. It can be used to generate sky maps and/or  $a_{\ell m}$  from power spectra  $(C(\ell))$ , synthesize maps from  $a_{\ell m}$  or simulate maps from  $C(\ell)$  and constraining  $a_{\ell m}$ .

#### **FORMAT**

IDL> ISYNFAST, cl\_in[, map\_out, alm\_in=, alm\_out=, apply\_windows=, beam\_file=, binpath=, double=, fwhm\_arcmin=, help=, iseed=, keep\_tmp\_files=, lmax=, nlmax=, nside=, nsmax=, plmfile=, simul\_type=, silent=, tmpdir=, windowfile=, winfiledir=]

## **QUALIFIERS**

cl\_in  $\,$  input power spectrum, can be a FITS file, or a

memory array containing the  $C(\ell)$ , used to gener-

ate a map or a set of gaussian alm

If empty quotes (") or a zero (0) are provided, it will be interpreted as "No input C(l)", in which

case some input alm's (alm\_in) are required.

map\_out optional output: RING ordered map synthetised from the power spectrum or from constraining alm

#### **KEYWORDS**

alm\_in= optional input (constraining) alm (must be a FITS

file) (**default:** no alm)

 $alm\_out = contains on output the effective alm (must be a$ 

FITS file)

/apply\_windows if set, beam and pixel windows are applied to in-

put alm\_in (if any)

beam\_file= beam window function, either a FITS file or an

isynfast 95

	array (see "Beam window function files" section in the <b>HEALPix</b> Fortran Facilities document)
binpath=	full path to back-end routine (default: \$HEXE/synfast, then \$HEALPIX/bin/synfast)  - a binpath starting with / (or \), or \$ is interpreted as absolute  - a binpath starting with ./ is interpreted as relative to current directory  - all other binpaths are relative to \$HEALPIX
/double	if set, I/O is done in double precision (default: single precision I/O)
$fwhm\_arcmin=$	gaussian beam FWHM in arcmin (default: 0)
/help	if set, prints extended help
iseed =	integer seed of radom sequence ( <b>default:</b> 0)
$/ {\rm keep\_tmp\_files}$	if set, temporary files are not discarded at the end of the run
lmax=, nlmax=	maximum multipole simulation ( <b>default:</b> $2*N_{\text{side}}$ )
nside=, nsmax=	Healpix resolution parameter $N_{\rm side}$
plmfile=	FITS file containing precomputed Spherical Harmonics (deprecated) ( <b>default:</b> no file)
simul_type=	<ol> <li>Temperature only</li> <li>Temperature + polarisation</li> <li>Temperature + 1st derivatives</li> <li>Temperature + 1st &amp; 2nd derivatives</li> <li>T+P + 1st derivatives</li> <li>T+P + 1st &amp; 2nd derivates (default: 2: T+P)</li> </ol>
/silent	if set, works silently
$\operatorname{tmpdir}=$	directory in which are written temporary files ( <b>default:</b> IDL_TMPDIR (see IDL documentation))
windowfile=	FITS file containing pixel window ( <b>default:</b> determined automatically by back-end routine). Do not set this keyword unless you really know what you are doing
winfiledir=	directory where the pixel windows are to be found ( <b>default:</b> determined automatically by back-end routine). Do not set this keyword unless you really know what you are doing

**DESCRIPTION**isynfast is an interface to F90 'synfast' F90 facility. It requires some disk space on which to write the parameter file and the other temporary files. Most data can be provided/generated as an external FITS file, or as a memory array.

#### RELATED ROUTINES

This section lists the routines related to **isynfast**.

• 11

101	version 6.4 or more is necessary to run isyntast.
nfast	F90 facility called by isynfast.

synfast F90 facility called by isynfast.

ialteralm IDL Interface to F90 alteralm

ianafast IDL Interface to F90 anafast and C++

 $anafast\_cxx$ 

iprocess\_mask IDL Interface to F90 process\_mask ismoothing IDL Interface to F90 smoothing

#### **EXAMPLE:**

```
isynfast, '$HEALPIX/test/cl.fits', map, fwhm=30, nside=256, /silent
mollview, map, 1, title='I'
mollview, map, 2, title='Q'
```

will synthetize and plot I and Q maps consistent with WMAP-1yr best fit power spectrum and observed with a circular gaussian 30 arcmin beam.

lm2index 97

## lm2index

Location in HEALPix directory tree: src/idl/misc/lm2index.pro

This IDL routine provides a means to convert the  $a_{\ell m}$  degree and order  $(\ell, m)$  into the index  $i = \ell^2 + \ell + m + 1$  (in order to be fed to alm2fits routine for instance)

#### **FORMAT**

IDL> LM2INDEX, l, m, index

## **QUALIFIERS**

1 Long array containing on INPUT the order  $\ell$ .

Long array containing on INPUT the degree m. m index

Long array containing on OUTPUT the index

 $i = \ell^2 + \ell + m + 1.$ 

**DESCRIPTION**lm2index converts  $(\ell, m)$  into  $i = \ell^2 + \ell + m + 1$ . Note that by definition  $0 < |m| < \ell$  (the routine does not check for this).

#### RELATED ROUTINES

This section lists the routines related to **lm2index**.

idl version 6.4 or more is necessary to run lm2index.

fits2alm reads a FITS file containing  $a_{\ell m}$  values.

alm2fits writes  $a_{\ell m}$  values into a FITS file.

index2lm routine complementary to lm2index: converts i =

 $\ell^2 + \ell + m + 1$  into  $(\ell, m)$ .

#### **EXAMPLE:**

lm2index, 1, m, index

will return in index the value  $\ell^2 + \ell + m + 1$ 

## median filter

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/median\_filter.pro">src/idl/toolkit/median\_filter.pro</a>
This IDL facility allows the median filtering of a Healpix map.

**FORMAT** 

IDL> MEDIAN\_FILTER (InputMap, Radius, MedianMap[,ORDERING=, /RING, /NESTED, /FILL\_HOLES, /DEGREES, /ARCMIN])

## **QUALIFIERS**

InputMap (IN) either an IDL array containing a full sky

Healpix map to filter ('online' usage), or the name of an external FITS file containing a full sky or cut

sky map

Radius (IN) radius of the disk on which the median is

computed. It is in Radians, unless /DEGREES or

/ARCMIN are set

MedianMap (OUT) either an IDL variable containing on out-

put the filtered map, or the name of an external FITS file to contain the map. Should be of same type of InputMap. Flagged pixels (ie, having the value !healpix.bad\_value) are left unchanged,

unless /FILL\_HOLES is set.

## **KEYWORDS**

/ARCMIN If set, Radius is in arcmin rather than radians

/DEGREES If set, Radius is in degrees rather than radians

FILL HOLES If set, flagged pixels are replaced with the median

of the valid pixels found within a distance Radius.

If there are any.

/NESTED Same as ORDERING='NESTED'

ORDERING= Healpix map ordering, should be either 'RING' or

'NESTED'. Only applies to 'online' usage.

median filter 99

> /RING Same as ORDERING='RING'

**DESCRIPTION** median\_filter allows the median filtering of a Healpix map. Each pixel of the output map is the median value of the input map pixels found within a disc of given radius centered on that pixel. Flagged pixels can be either left unchanged or 'filled in' with that same scheme.

> If the map is polarized, each of the three Stokes components is filtered separately.

> The input and output can either be arrays or FITS files, but they to be both arrays or both FITS files.

#### RELATED ROUTINES

This section lists the routines related to median filter.

idl version 6.4 or more is necessary to run median filter

#### **EXAMPLE:**

```
median_filter ('map.fits', 10., /arcmin, 'med.fits')
```

Writes in 'med.fits' the median filtered map of 'map.fits' using a disc radius of 10 arcmin

#### **EXAMPLE:**

```
map = randomn(seed, nside2npix(256))
median_filter (map, 0.5, /deg, med)
```

Returns in med the median filtered map of map using a disc radius of 0.5 degrees

## mollcursor

Location in HEALPix directory tree: src/idl/visu/mollcursor.pro

This IDL facility provides a point-and-click interface for finding the astronomical location, value and pixel index of the pixels nearest to the pointed position on a Mollweide projection of a **HEALPix** map.

## **QUALIFIERS**

cursor\_type= cursor type to be used (default: 34)

file\_out= file containing on output the list of point selected

with the cursor.

If set to 1, the file will take its default name: 'cursor\_catalog.txt'.

If set to a non-empty character string, the file name will be that string mollcursor 101

**DESCRIPTION** mollcursor should be run immediately following mollview. It gives the longitude, latitude, map value and pixel number corresponding to the cursor position in the window containing the map generated by mollview. Mouse buttons are used to select the function:

> left button = display the information relative to the current cursor position,

> middle button = print out this information in the IDL command window

right button = quit mollcursor

Note on Mac OS X, X11 and IDL cursor: depending on the Mac OS X version<sup>a</sup> and most importantly on the X Window System being used,  $^{b}$  the IDL function cursor, and therefore **HEALPix** mollcursor, gnomcursor, ... will not work properly under X11. To solve this problem, type the relevant line below at your X11 prompt and restart X11.

If you are using Apple's X11, type under Tiger (10.4): defaults write com.apple.x11 wm\_click\_through -bool true or, under Leopard (10.5), Snow Leopard (10.6), Lion (10.7): defaults write org.x.x11 wm\_click\_through -bool true If you are using Xquartz (from, Montain Lion (10.8) to Sequoia (15.\*):

defaults write org.macosforge.xquartz.X11 wm\_click\_through -bool true for Xquartz < 2.7,

Or defaults write org.xquartz.X11 wm click through -bool true for Xquartz  $\geq 2.8$ ,

and if you are using MacPort's X11 (package xorg-server): defaults write org.macports.X11 wm\_click\_through -bool true (see http://www.idlcoyote.com/misc\_tips/maccursor.html and the section Mac OS X, X11 and IDL cursor in "HEALPix Installation Documentation").

And finally, mollcursor obviously requires the '3 button mouse' to be enabled, which can be done in the X11 Preferences menu, or if Xquartz is used (see man Xquartz) via:

defaults write org.macosforge.xquartz.X11 enable\_fake\_buttons -bool true

 $<sup>^{</sup>a}$ the command  $sw_{vers}$  -productVersion can be used to know the Mac OS X version being used

 $<sup>^{</sup>b}$ the command ls -lrt \$HOME/Library/Preferences/\*[xX]11\*plist can be used to determine the X implementation and its configuration file

#### RELATED ROUTINES

This section lists the routines related to **mollcursor**.

$\operatorname{idl}$	version 6.4 or more is necessary to run mollcursor
ghostview	ghostview or a similar facility is required to view the Postscript image generated by mollcursor.
XV	xv or a similar facility is required to view the GIF/PNG image generated by mollcursor (a browser can also be used).
synfast	This <b>HEALPix</b> facility will generate the FITS format sky map to be input to mollcursor.
cartview	IDL facility to generate a Cartesian projection of a <b>HEALPix</b> map.
cartcursor	interactive cursor to be used with cartview
gnomview	IDL facility to generate a gnomonic projection of a <b>HEALPix</b> map.
gnomcursor	interactive cursor to be used with gnomview
mollview	IDL facility to generate a Mollweide projection of a <b>HEALPix</b> map.
mollcursor	interactive cursor to be used with mollview
orthview	IDL facility to generate an orthographic projection of a <b>HEALPix</b> map.
orthcursor	interactive cursor to be used with orthview

#### **EXAMPLE:**

mollcursor

After mollview reads in a map and generates its mollweide projection, mollcursor is run to know the position and flux of bright synchrotron sources, for example.

mollview 103

## mollview

#### Location in HEALPix directory tree: src/idl/visu/mollview.pro

This IDL facility provides a means to visualise a full sky Moll-weide projection of **HEALPix** and COBE Quad-Cube maps in an IDL environment. It also offers the possibility to generate GIF, JPEG, PDF, PNG and Postscript color-coded images of the projected map. The projected (but not color-coded) data can also be output in FITS files and IDL arrays.

#### **FORMAT**

MOLLVIEW. IDL> File [, Select] [, AS-INH=, BAD COLOR=, BG COLOR=, CHARSIZE=, CHARTHICK=, COLT=, COORD=, /CROP, CUS-TOMIZE=, DEFAULT SETTINGS=, EXECUTE=, FAC-TOR=, FG COLOR=, FITS=, /FLIP, GAL CUT=, GIF=, GLSIZE=, GRATICULE=, /HALF SKY, HBOUND=, /HELP, /HIST\_EQUAL, HXSIZE=, IGLSIZE=, IGRATIC-ULE=, JPEG=, LATEX=, /LOG, MAP OUT=, MAX=, MIN=, /NESTED, /NO\_DIPOLE, /NO\_MONOPOLE, /NOBAR, /NOLABELS, /NOPOSITION, OFFSET=, OUT-LINE=, PDF=, PFONTS=, PNG=, POLARIZATION=, /PREVIEW, PS=, PXSIZE=, PYSIZE=, RESO\_ARCMIN=, RETAIN=, ROT=, /SAVE, /SHADED, /SILENT, SIL-HOUETTE=, STAGGER=, SUBTITLE=, TITLEPLOT=, TRANSPARENT=, TRUECOLORS=, UNITS=, WIN-DOW=, XPOS=, YPOS=

Several visualization routines have a similar interface. Their **qualifiers** and **keywords** are all listed here, and the routines to which they apply are coded in the 'routine' column as: A: azeqview, C: cartview, G: gnomview, M: mollview, O: orthview and all: all of them

Qualifiers should appear in the order indicated. They can take a range of values, and some of them are optional.

Keywords are optional, and can appear in any order. They take the form keyword=value and can be abbreviated to a non ambiguous form (ie, factor=10.0 can be replaced by fac = 10.0). They generally can take a range of values, but some of them (noted as /keyword below) are boolean switches: they are either present (or set to 1) or absent (or set to 0).

## **QUALIFIERS**

name	routi	nes description
File	all	Required
		name of a (possibly gzip compressed) FITS file containing
		the <b>HEALPix</b> map in an extension or in the image field,
		or name of an $online$ variable (either array or structure) con-
		taining the (RING or NESTED ordered) HEALPix map
		(See note below);
		if Save is set: name of an IDL saveset file containing the
		HEALPix map stored under the variable data
		(default: none)
		Note on online data: in order to preserve the integrity of
		the input data, the content of the array or structure File
		is replicated before being possibly altered by the map mak-
		ing process. Therefore plotting online data will require more
		memory than reading the data from disc directly, and is not
		recommended to visualize data sets of size comparable to
		that of the computer memory.
		Note on high resolution cut sky data: cut sky data (in
		which less than 50% of the sky is observed), can be pro-
		cessed with a minimal memory foot-print, by not allocating
		fake full map. In the current release, two restrictions apply:
		the input data set must be read from a FITS file in 'cut4' for-
		mat, and the POLARIZATION IDL keyword (described below)
		must be 0 (default value). See Example #4 on page 121.
C 1 /	11	see also: TrueColors.
Select	all	Optional
		column of the BIN FITS table to be plotted, can be either
		- a name : value given in TTYPEi of the FITS file
		NOT case sensitive and can be truncated,
		(only letters, digits and underscore are valid)
		- an integer: number i of the column containing the data,
		starting with 1 (also valid if File is an online array)
		•
		(default: 1 for full sky maps, 'SIGNAL' column for FITS files containing cut sky maps) (see the Examples below)

mollview 105

## KEYWORDS

name	routine	es description
ASINH=	all	if set, the color table is altered to emulate an non-linear mapping of the input data enhancing the low contrast regions. If asinh=1 the mapping is $y=\sinh^{-1}(x)$ , such that $y\approx x$ when $x\ll 1$ and $y\approx \ln(2x)$ when $x\gg 1$ . If asinh=2 the mapping is $y=\sinh^{-1}(x/2)/\ln(10)$ , such that $y\approx 0.21x$ when $x\ll 1$ and $y\approx \log(x)$ when $x\gg 1$ . Here $x$ is the input data, optionally altered by Factor and Offset. This option can $not$ be used in conjonction with /LOG nor /HIST_EQUAL.
BAD_COLOR=	all	color given to missing pixels (having !healpix.bad_value (= -1.6375 10 <sup>30</sup> ) or NaN value on input). The color can be provided as either:  - a single integer in [0,255], specifying the index to be used in the color table chosen via COLT (in which the indexes 0, 1 and 2 are reserved for black, white and grey respectively),  - a 3 element vector, with each element in [0,255], specifying the amount of RED, GREEN and BLUE  - a 7-character string, starting with '#', specifying the color in HTML Hexadecimal fashion (eg, '#ff0000' for red).  (default: neutral grey (=2, =[175, 175, 175], ='#afafaf')) see also: BG_COLOR, FG_COLOR, TRANSPARENT
BG_COLOR=	all	color given to background pixels (outside the sphere). See BAD_COLOR for expected format. (default: white (=1, =[255, 255, 255], ='#ffffff')) see also: FG_COLOR, TRANSPARENT
CHARSIZE=	all	overall multiplicative factor applied to the size of all characters appearing on the plot ( <b>default:</b> 1.0); see also: CUSTOMIZE
CHARTHICK=	all	character thickness (in TITLEPLOT, SUBTITLE and color bar labeling). Other characters thickness (such as graticule labels), can be controlled with !P.CHARTHICK. (default: 1)

name	routine	es description
COLT=	all	color table index:  — Indexes in [0,40] are reserved for standard IDL color tables, while [41,255] are used for user defined color tables read from disc (created and written to disc with MODIFYCT), if any.  — Indexes 1001 (or 'planck1', case insensitive) and 1002 (or 'planck2') are reserved for Planck color tables 1 and 2 generated by planck_colors. See Example #6 on page 124.  — If the index does not match any existing table, or if it is above 255, the current online table (modifiable with TVLCT, XLOADCT, XPALETTE, or eg, J. Davenport's cubehelix.pro implementation of D. Green 's cubehelix color scheme) is used instead.  —If colt< 0, the IDL color table ABS(colt) is used, but the scale is reversed (ie a red to blue scale becomes a blue to red scale). Note: -0.1 can be used as negative 0. (default: 33 (Blue-Red)) see also: TrueColors
COORD=	all	vector with 1 or 2 elements describing the coordinate system of the map; either  - 'C' or 'Q': Celestial2000 = eQuatorial,  - 'E': Ecliptic,  - 'G': Galactic if coord = ['x','y'] the map is rotated from system 'x' to system 'y' if coord = ['y'] the map is rotated to coordinate system 'y' (with the original system assumed to be Galactic unless indicated otherwise in the input file)
/CROP	all	see also: Rot if set, the image produced (in GIF/JPEG/PDF/PNG/PS and on screen) only contains the projected map and no title, color bar, see also: Gif, Jpeg, Pdf, Png, Ps

mollview 107

#### name

#### routines description

#### CUSTOMIZE=

all

User provided structure containing customization parameters of the produced output, whose default values are listed in DE-FAULT\_SETTINGS. The accepted inputs are

ASPOS.X, ASPOS.Y: X,Y location of astronomical coordinates label (which can be removed altogether with /NOPOSITION, only applicable to gnomview),

CBAR.DX, CBAR.DY: length and width of color bar (which can be removed with /NOBAR), the bar is centered, at an automatically determined height

CBAR. SPACES: 3-element vector listing the strings to be inserted between the map minimum value label, the color bar, the map maximum value, and the map units (read from the FITS file or provided by UNITS) (default: 3 single spaces),

CBAR.TY: vertical offset of the text (min, max and units labels) with respect to the color bar (**default:** 0);

**Note:** the character size of the text accompanying the color bar is fully determined by the keyword Charsize,

CBAR.BOX: thickness of the black box drawn around the color bar (default: 0: no box); the final thickness is F\*cbar.box\*!p.thick with F=2 in PDF and PS, or F=1 otherwise, while !p.thick is assumed to have a value of 1.0 unless specified otherwise.

CRING.DX, CRING.XLL, CRING.YLL: radius and X,Y location of lower left corner of the color disc showing the polarization direction when POLARIZATION=3

PDF.DEBUG: if set to 1, and SILENT is not set, then debugging information on the PDF generation will be printed (when applicable), and the intermediate Postscript file will be kept

SUBTITLE.X, SUBTITLE.Y, SUBTITLE.CHARSIZE: control the X,Y location of the plot subtitle (X=0 is left justified, X=0.5 is centered and X=1 is right justified), and its final character size, which is the product of the number SUBTITLE.CHARSIZE with the one provided in the keyword Charsize

TITLE.X, TITLE.Y, TITLE.CHARSIZE: same as above, applied to the plot title (titleplot),

VSCALE.Y: X,Y location of scale calibrating the polarization rods (whose length and spacing in the main plotting area can be tuned with POLARIZATION=[3, length, spacing]) VSCALE.TY: vertical offset of the text next to the calibrating rod.

See Example #7 on page 125.

name	routines description	
DEFAULT- _SETTINGS=	all	Structure containing on output the default values (slightly projection dependent) of the plotting parameters that can be customized with CUSTOMIZE.  As shown in Example #7 on page 125, the returned structure can be inspected with the routine help_st.
EXECUTE=	all	character string containing IDL command(s) to be executed in the plotting window. See Example #3 on page 122.
FACTOR=	all	scalar multiplicative factor to be applied to the valid data the data plotted is of the form Factor*(data + Offset) This does not affect the flagged pixels Can be used together with ASINH or LOG When used with TRUECOLORS, FACTOR can be a 3-element vector. see also: ASINH, Offset, LOG, Truecolors (default: 1.0)
FG_COLOR=	all	color of title and subtile characters, graticule lines and labels, units, outlines  See BAD_COLOR for expected format.  (default: black (=0, =[0, 0, 0], ='#000000'))  see also: BAD_COLOR, BG_COLOR
FITS=	all	string containing the name of an output FITS file with the projected map in the primary image  if set to 1: output the plot in plot_proj.fits, where proj is either cartesian, gnomic, mollweide, or orthographic depending on the projection in use;  if set to a file name: output the plot in that file.  (default: 0: no .FITS done)  In the case of Orthographic projection, HALF_SKY must be set.  Except for the color mapping, all the keywords and options apply to the projected map, ie: its size is determined by PX-SIZE (and PYSIZE when applicable), its angular resolution by RESO_ARCMIN when applicable, its orientation and coordinates by ROT and COORD respectively,  For compatibility with standard FITS viewers (including STIFF), unobserved pixels, and pixels outside the sphere, take the value NaN (ie !values.f_nan in IDL). The resulting FITS file can be read in IDL with eg. map=readfits(filename). see also: Map_out

name	routine	s description
/FLIP	all	if set the longitude increases to the right, whereas by default (astronomical convention) it increases towards the left
GAL_CUT=	—MO	(positive float) specifies the symmetric galactic cut in degrees outside of which the monopole and/or dipole fitting is done ( <b>default:</b> 0: monopole and dipole fit done on the whole sky) (see also: No_dipole, No_monopole)
GIF=	all	string containing the name of a .GIF output if set to 1: outputs the plot in plot_projection.gif, where projection is either azimequid, cartesian, gnomic, mollweide or orthographic, if set to a file name: outputs the plot in that file Please note that the resulting GIF image might not always look as expected. The reason for this is a problem with 'backing store' in the IDL-routine TVRD. Please read the IDL documentation for more information.  (default: no .GIF done) see also: Crop, Jpeg, Pdf, Png, Preview, Ps and Retain
GLSIZE=	CGMO	character size of the graticule labels in units of Charsize.  Can be a scalar (which applies to both parallel and meridian labels), or a 2 element vector (interpreted as [meridian_label_size, parallel_label_size])  (default: 0: no labeling of graticules).  see also: Charsize, Graticule, Iglsize, Igraticule
GRATICULE=	CGMO	if set, puts a graticule (ie, longitude and latitude grid) in the $output$ astrophysical coordinates with delta_long = delta_lat = gdef degrees if set to a scalar $x > \text{gmin}$ then delta_long = delta_lat = $x$ if set to [x,y] with $x,y > \text{gmin}$ then delta_long = $x$ and delta_lat = $y$ cartview: gdef = 45, gmin = 0 gnomview: gdef = 5, gmin = 0 mollview: gdef = 45, gmin = 10 orthview: gdef = 45, gmin = 10 Note that the graticule will rotate with the sphere if Rot is set. To outline only the equator set graticule=[360,90]. The automatic labeling of the graticule is controlled by Glsize The graticule line thickness is controlled via !P.THICK. (default: 0 [no graticule]) see also: Igraticule, Rot, Coord, Glsize

name	routines description	
/HALF_SKY	<b>—</b> O	if set, only shows only one half of the sky (centered on (0,0) or on the location parametrized by Rot) instead of the full sky
HBOUND=	all	scalar or vector of up to 3 elements. If Hbound[i] is set to a valid $N_{\rm side}$ , the routine will overplot the <b>HEALPix</b> pixel boundaries corresponding to that $N_{\rm side}$ on top of the map. The first $N_{\rm side}$ will be plotted with solid lines, the second one (if any) with dashes and the third one (if any) with dots. Obviously, better results are obtained for Hbounds elements in growing order. Since 0-valued boundaries are not plotted, but used for linestyle assignment, providing Hbound=[0,4] (or [0,0,4]) will plot $N_{\rm side}=4$ boundaries with dashes (resp. dots), while Hbound=4 would plot the same boundaries with solid lines.
/HELP	all	if set, the routine header is printed (by doc_library) and nothing else is done
/HIST_EQUAL	all	if set, uses a histogram equalized color mapping (useful for non gaussian data field) ( <b>default:</b> uses linear color mapping and puts the level 0 in the middle of the color scale (ie, green for Blue-Red) unless Min and Max are not symmetric) see also: Asinh, Log
HXSIZE=	all	horizontal dimension (in cm) of the Postscript printout (default: $26 \text{ cm} \simeq 10 \text{ in}$ ) see also: Pxsize
IGLSIZE=	CGMO	character size of the input coordinates graticule labels in units of Charsize.  Either scalar or 2-element vector (see Glsize).  (default: 0: no labeling of graticules).  see also: Charsize, Igraticule
IGRATICULE=	CGMO	if set, puts a graticule (ie, longitude and latitude grid) in the input astrophysical coordinates. See Graticule for conventions and details. If both Graticule and Igraticule are set, the latter will be represented with dashes.  The automatic labeling of the graticule is controlled by Iglsize (default: 0 [no graticule]) see also: Graticule, Rot, Coord, Iglsize

name	routines	description
JPEG=	all	string containing the name of a lossless .JPEG output file if set to 1: outputs the plot in plot_projection.jpeg, when projection is either azimequid, cartesian, gnomic, mollweid or orthographic, if set to a file name: output the plot in that file (default: no .JPEG done) see also: Crop, Fits, Gif, Map_out, Png, Preview, Pdf, Ps, and Parking and the containing the name of a lossless .JPEG output file in plot_projection.jpeg, when projection is either azimequid, cartesian, gnomic, mollweid or orthographic, if set to a file name: output the plot in that file
LATEX=	all	Retain if set to 1 or 2, enables LATEX handling of character strings such as Titleplot, Subtitle and Units  — if set to 2 with PS or PDF outputs, those strings (and the graticule labels) will be processed by genuine LATEX and in serted in the final PS or PDF file using psfrag package (require the ubiquitous latex and its color, geometry, graphicx and psfrag packages as well as dvips). In this case, the Pfonts setting will be ignored.  Note that cgPStoRASTER, ImageMagick convert and/or GraphicsMagick gm convert can be used to turn a PS or PDF file inthigh resolution GIF, JPEG or PNG file.  Beware that the option latex=2 may not work properly under versions 0.9.5 and older of gdl.  — if set to 1, with whatever output (GIF, JPEG, PDF, PNG-PS, or X) LaTeX is partially emulated with TeXtoIDL routines, which are now shipped with HEALPix (no extra requirements). In this case, Pfonts settings can be used. (default: 0, no LaTeX handling)
/LOG	all	display the log of map. This is intended for application to positive definite maps only, eg. Galactic foreground emission templates; for arbitrary maps, use /ASINH instead. see also: Asinh, Factor, Hist_Equal, Offset
MAP_OUT=	all	variable that will contain the projected map on output. Except for the color mapping, all the keywords and option apply to the projected map, ie: its size is determined by PX SIZE (and PYSIZE when applicable), its angular resolution by RESO_ARCMIN when applicable, its orientation and coordinates by ROT and COORD respectively, Unobserved pixels, and pixels outside the sphere, take value!healpix.bad_value (= $-1.637510^{30}$ ). see also: Fits

name	routine	es description	
MAX=	all	Set the maximum value for the plotted signal (default: is to use the actual signal maximum).	
MIN=	all	Set the minimum value for the plotted signal (default: is to use the actual signal minimum).	
/NESTED	all	specify that the online data is ordered in the nested scheme	
/NO_DIPOLE —MO		if set (and Gal_cut is not set) the best fit monopole *and* dipole over all valid pixels are removed; if Gal_cut is set to $b > 0$ , the best monopole and dipole fit is performed on all valid pixels with  galactic latitude  $> b$ (in deg) and is removed from all valid pixels (default: 0 (no monopole or dipole removal)) can NOT be used together with No_monopole see also: Gal_cut, No_monopole	
/NO_MONOPOLE—MO		if set (and Gal_cut is not set) the best fit monopole over all valid pixels is removed; if Gal_cut is set to $b > 0$ , the best monopole fit is performed on all valid pixels with  galactic latitude  $> b$ (in deg) and is removed from all valid pixels (default: 0 (no monopole removal)) can NOT be used together with No_dipole see also: Gal_cut, No_dipole	
/NOBAR	all	if set, the color bar (or the color wheel used when Polarization=2) is hidden; see also: CUSTOMIZE	
/NOLABELS	all	if set, color bar labels (min and max) are not present, (default: labels are present); see also: CUSTOMIZE	
/NOPOSITION	-G-	if set, the astronomical location of the map central point is not indicated; see also: $\hbox{\tt CUSTOMIZE}$	
OFFSET=	all	scalar additive factor to be applied to the valid data the data plotted is of the form Factor*(data + Offset) This does not affect the flagged pixels can be used together with ASINH or LOG When used with TRUECOLORS, OFFSET can be a 3-element vector. see also: ASINH, Factor, LOG, TRUECOLORS (default: 0.0)	

#### name

#### routines description

#### OUTLINE=

CGMO

IDL structure, array of (same size) structures, or structure of (mixed size) structures (see Note below), containing the description of one (or several) outline(s) to be overplotted on the final map.

For each contour or point list, the corresponding (sub)structure should contain the following fields:

- 'COORD': coordinate system (either 'C'/'Q', 'G' or 'E') of the contour (same meaning as in Coord)
- 'RA': RA/longitude coordinates of the contour vertices (array or scalar)
- 'DEC': Dec/latitude coordinates of the contour vertices (array or scalar)

and can optionally contain the fields:

- 'COL[OR]': (optional, scalar or 2-element vector) index in [0,255] of the colors used to draw the lines and symbols. (**default:** [!p.color, !p.background], ie black and white)
- 'LINE[STYLE]': (optional, scalar) +2: black dashes, +1: black dots, 0: black solid (default), -1: black dots on white background, -2: black dashes on white background
- 'PSY[M]': (optional, scalar) symbol used to represent vertices (same meaning as standard PSYM in IDL. If  $9 \le |psym| \le 46$ , D. Fanning's cgSYMCAT.PRO symbols definition will be used; for example, psym=9 is an open circle). If  $\le 0$ , the vertices are represented with the chosen symbols, and connected by arcs of geodesics; if > 0, only the vertices are shown (default: 0)
- 'SYM[SIZE]': (optional, scalar) vertice symbol size (same meaning as SYMSIZE in IDL), (default: 1)
- 'THI[CK]': (optional, scalar) thickness factor of the lines and symbols. The final thickness is 3\*F\*outline.thick\*!P.thick with F=2 in PDF and PS, or F=1 otherwise.

See for instance the function Outline\_earth and Fig. 6 on page 145 to create a structure outlining the Earth continents, rivers and/or countries.

Note 1: when applicable, the vertices are connected by segments of geodesics. To obtain a better looking outline, increase the number of vertices provided. The outline does not have to be closed. The procedure will NOT attempt to close the outline. See Example #2 below.

Note 2: several outlines (let's say circle and triangle) can be overplotted at once by gathering the respective structures into an array (outline=[circle,triangle]) if they have the same features and in particular the same number of vertices, or in one meta-structure (outline={s1:circle,s2:triangle}) in all cases.

see also: Coord, Graticule

name	routines description	
PDF=	all	string containing the name of a .PDF output if set to 0: no PDF output if set to 1: outputs the plot in plot_projection.pdf, where projection is either azimequid, cartesian, gnomic, mollweide or orthographic, if set to a file name: outputs the plot in that file (default: 0)  The PDF file is produced from a PostScript file using the script epstopdf now shipped with HEALPix. Note that epstopdf usually requires a fully functional implementation of the fairly widespread gs, aka Ghostscript, which may however not be available on the computation dedicated nodes of some computer clusters.  If the resulting PDF file is not properly rotated (ie landscape orientation instead of portrait), and/or has excessive white margins, the scripts pdf90, part of the package pdfjam, and/or pdfcrop, often included in PDFTeX installations, can respectively prove very useful. see also: Preview, Gif, Jpeg, Png, Ps

name	routin	es description
PFONTS=	all	2-element vector of integers $[p_0, p_1]$ selecting the default IDL font of character strings such as the Subtitle, Titleplot and Units.
		$p_0$ must be in $\{-1,0,1\}$ and selects the origin of the fonts among -1: Hershey Vector, 0: Device Specific and 1: True Type Fonts.
		p <sub>1</sub> must be in {2,,20} and selects the starting font of the character strings as described here. The font can be changed within each string with embedded formatting commands, as discussed on http://www.exelisvis.com/docs/Fonts_and_Colors.html. (default: [-1,6], corresponding to the Hershey vector font of type 'Complex Roman', and is equivalent to typing !p.font=-1 and prepending the Subtitle, Titleplot and Units strings with '!6').  Note that PFONTS will be ignored if Latex=2 and PDF or PS
PNG=	all	are set.  string containing the name of a .PNG output  if set to 1: outputs the plot in plot_projection.png, where  projection is either azimequid, cartesian, gnomic, mollweide  or orthographic,  if set to a file name: outputs the plot in that file  Please note that the resulting PNG image might not always look  as expected. The reason for this is problems with 'backing store'  in the IDL-routine TVRD. Please read the IDL documentation  for more information.  (default: no .PNG done)  see also: Crop, Fits, Gif, Jpeg, Map_out, Preview, Pdf, Ps,

and Retain

#### name

#### routines description

#### POLARIZATION=all

if set to

0: no polarization information is plotted;

1: the AMPLITUDE  $P = \sqrt{U^2 + Q^2}$  of the polarization is plotted (as long as the input data contains polarization information (ie, Stokes parameter Q and U for each pixel));

2: the ANGLE  $\phi = \tan^{-1}(U/Q)/2$  of the polarization is plotted Note: the angles are color coded with a fixed color table (independent of Colt);

3: -the temperature is color coded (with a color table defined by Colt),

-and the polarization is overplotted as small RODS (or headless VECTORS).

Polarization can then be a 4-element vector (the first element being 3). The second element controls the average length of the rods (**default:** 1), the third one controls their spacing (**default:** 1), while the fourth one controls their thickness (which also depends in a device dependent manner on !P.THICK) (**default:** 1). Non-positive values are replaced by 1.

see also: Customize

#### (default: 0)

Note 1: The representation of the polarization direction (options 2 and 3 above), include the effects of the rotations and/or changes or astronomical coordinates (controlled by ROT and COORD respectively) but do not include the effects of the distortions induced by the projection from the sphere to the plan. Because the polarization usually has more power at small scales, it must generally be represented on maps of small patches of the sky to remain legible, in which case the projection-induced distortions are small.

Note 2: when polarization=2 or polarization=3, the visualisation routines behavior will depend on the value of the POLCCONV FITS keyword (see note on POLCCONV in The HEALPix Primer)

name	routine	es description
/PREVIEW	all	if set, the external file generated with Gif, Jpeg, Pdf, Png, or Ps will be previewed with the visualisation applications (eg, gv, display or open) chosen during the HEALPix IDL/GDL configuration step
PS=	all	if set to 0: no PostScript output if set to 1: outputs the plot plot_projection.ps, where pro- jection is either azimequid, cartesian, gnomic, mollweide or orthographic, if set to a file name: outputs the plot in that file (default: 0) see also: Preview, Gif, Jpeg, Pdf, Png
PXSIZE=	all	set the number of horizontal screen_pixels or postscript_color_dots of the plot (useful for high definition color printer) or elements of the output map (default: 800 (Mollview and full sky Orthview), 600 (half sky Orthview), 500 (Cartview and Gnomonic)) see also: FITS, GIF, JPEG, MAP_OUT, PDF, PNG, PS.
PYSIZE=	ACG-	set the number of vertical screen_pixels or postscript_color_dots of the plot (default: Pxsize).
RESO_ARCMIN	=ACG-	size of screen_pixels or postscript_color_dots in arcmin (default: 1.5) see also: FITS, GIF, JPEG, MAP_OUT, PDF, PNG, PS.
RETAIN=	all	specifies the type of backing store to use for direct graphics windows in $\{0,1,2\}$ . ( <b>default:</b> 2). See IDL documentation for details.
ROT=	all	vector with 1, 2 or 3 elements specifing the rotation angles in DEGREES to apply to the map in the 'output' coordinate system (see Coord) = (lon0, [lat0, rat0]) lon0: longitude of the point to be put at the center of the plot the longitude increases Eastward, ie to the left of the plot (default: 0) lat0: latitude of the point to be put at the center of the plot (default: 0) rot0: anti clockwise rotation to apply to the sky around the center (lon0, lat0) before projecting (default: 0)

nome	no+	og description
name	routine	es description
/SAVE	all	if set, assumes that File is in IDL saveset format, the variable saved should be DATA
/SHADED	<b>—</b> O	if set, the orthographic sphere is shaded, using a Phong model, to emulate 3D viewing. The sphere is illuminated by isotropic ambiant light plus a single light source. Can NOT be used with GIF.
/SILENT	all	if set, the program runs silently, and extra debugging switches such as <a href="mailto:customize={pdf:{debug:1}}">customize={pdf:{debug:1}}</a> } will be ignored.
SILHOUETTE=	—MO	if set to a scalar or 2-element vector with silhouette[0] $\neq$ 0, a silhouette is drawn around the map. Its thickness is F*abs(silhouette[0])*!P.THICK with F=2 in PDF and PS, or F=1 otherwise. Its color is determined by abs(silhouette[1]) in [0,255] (default: 0:FG_COLOR). See Example #7 on page 125.
STAGGER=	-0	Scalar or 2 element vector:  — if stagger[0] is in ]0,2], three copies of the same sphere centered respectively at [-stagger[0], 0, stagger[0]] (expressed in radius units) along the plot horizontal axis are shown in ORTHOGRAPHIC projection  — if set, stagger[1] defines the angle of rotation (in degrees) applied to the left and right partial spheres: the <i>lhs</i> sphere is rotated downward by the angle provided, while the <i>rhs</i> one is rotated upward. Rotations are swapped if FLIP is set.  Currently can not be used with Graticule nor igraticule
SUBTITLE=	all	String containing the subtitle to the plot see also: Titleplot, Latex, Customize
TITLEPLOT=	all	String containing the title of the plot, if not set the title will be File see also: Subtitle, Latex, Customize
TRANSPARENT	=all	If set to 1, the input data pixels with value <code>!healpix.bad_value</code> (= $-1.637510^{30}$ ) will appear totally transparent on the output PNG file (instead of the usual grey or <code>BAD_COLOR</code> ). If set to 2, the background pixels will be transparent (instead of the usual white or <code>BG_COLOR</code> ) If set to 3, both the grey and white pixels will look transparent. Active only in conjunction with <code>PNG</code>

name	routine	routines description	
TRUECOLORS=	all	if the input data is of the form [Npix,3], then the 3 fields are respectively understood as Red, Green, Blue True-Color channels, and the color table is ignored.  – If set to 1, the mapping field-intensity to color is done for the 3 channels at once. (see also: Factor, Offset)  – If set to 2, that mapping is done for each channel separately (in that case, MIN and MAX keywords are ignored).	
UNITS=	all	String containing the units, to be put on the right hand side of the color bar, overrides the value read from the input file, if any see also: Nobar, Nolabels, Latex	
WINDOW=	all	IDL window index (integer)  — if WINDOW < 0: virtual window: no visible window opened.  Can be used with PNG, JPEG, or GIF, in particular if those files are larger than the screen. Note: The Z buffer will be used instead of the X server, allowing much faster production of the image over a slow network  — if WINDOW in [0,31]: the specified IDL window with index WINDOW is used (or reused). Can be used to have a sequence of images appear in the same window  — if WINDOW > 31: a free (=unused) window with a random index > 31 will be created and used.  (default: 32, if X server properly set; -1, otherwise)	
XPOS=	all	The X position on the screen of the lower left corner of the window, in device coordinate	
YPOS=	all	The Y position on the screen of the lower left corner of the window, in device coordinate	

## **DESCRIPTION**

mollview reads in a **HEALPix** sky map in FITS format and generates a Mollweide projection of it, that can be visualized on the screen or exported in a GIF, JPEG, PNG, PDF or Postscript file. mollview allows the selection of the coordinate system, map size, color table, color bar inclusion, linear, log, hybrid or histogram equalised color scaling, maximum and minimum range for the plot, plot-title *etc*. It also allows the representation of the polarization field.

#### RELATED ROUTINES

This section lists the routines related to **mollview**.

$\operatorname{idl}$	version 6.4 or more is necessary to run mollview
gv, ghostview	gv, ghostview or a similar facility is required to view the Postscript or PDF images generated by mollview.
display, xv	display, xv or a similar facility is required to view the GIF/JPEG/PNG image generated by mol- lview (a browser can also be used).
synfast, smoothing	These F90 <b>HEALPix</b> facilities will generate the FITS format sky maps to be input to mollview.
isynfast, ismoothing	These IDL routines will generate the FITS format sky maps to be input to mollview.
cartview	IDL facility to generate a Cartesian projection of a <b>HEALPix</b> map.
cartcursor	interactive cursor to be used with cartview
gnomview	IDL facility to generate a gnomonic projection of a <b>HEALPix</b> map.
gnomcursor	interactive cursor to be used with gnomview
mollview	IDL facility to generate a Mollweide projection of a <b>HEALPix</b> map.
mollcursor	interactive cursor to be used with mollview
orthview	IDL facility to generate an orthographic projection of a <b>HEALPix</b> map.
orthcursor	interactive cursor to be used with orthview
planck_colors	creates color tables used in Planck 2013 publications

# EXAMPLES: #1

mollview, 'planck100GHZ-LFI.fits', min=-100, max=100, /graticule, \$
 title='Simulated Planck LFI Sky Map at 100GHz'

mollview reads in the map 'planck100GHZ-LFI.fits' and generates an output image in which the temperature scale has been set to lie between  $\pm$  100 ( $\mu$ K), a graticule with a 45 degree step in longitude and latitude is drawn, and the title 'Simulated Planck LFI Sky Map at 100GHz' appended to the image.

## EXAMPLES: #2

```
map = findgen(48)
triangle= create_struct('coord','G','ra',[0,80,0],'dec',[40,45,65])
mollview,map, graticule=[45,30],rot=[10,20,30],$
    title='Mollweide projection',subtitle='mollview', $
    outline=triangle
```

makes a Mollweide projection of a pixel index map (see Figure 1c on page 122) after an arbitrary rotation, with a graticule grid (with a  $45^{\circ}$  step in longitude and  $30^{\circ}$  in latitude) and an arbitrary (triangular) outline

## EXAMPLES: #3

```
map = findgen(48)
mycommand = 'x=findgen(64)/10. & ' + $
    'plot,x,sin(x),pos=[0.8,0.8,0.99,0.99],/noerase &' +$
    'xyouts,0.5,0.5,"Hello World !",/normal,charsize=2,align=0.5'
mollview,map, execute=mycommand, png='plot_example_execute.png',$
    /preview,/graticule,/glsize
```

produces a PNG file containing a Mollweide projection of a pixel index map with labeled graticules, a simple sine wave in the upper right corner, and some greetings, as shown on Figure 2 on page 122

## EXAMPLES: #4

```
pixel = 164indgen(400000)
signal = pixel * 10.0
file = 'cutsky.fits'
write_fits_cut4, file, pixel+100000, signal, nside=32768, /ring
gnomview, file, rot=[0,90], grat=30, title='high res. cut-sky map'
```




Figure 1: Figures produced by cartview, gnomview, mollview and orthview, see respective routine documentation for details.




Figure 2: Figure produced by Example #3 .

produces and plots a high resolution map (6.4 arcsec/pixel), in which only a very small subset of pixels is observed

## EXAMPLES: #5

```
file = 'wmap_band_iqumap_r9_5yr_K_v3.fits'
mollview, file, title='Linear Color Scale', /silent
mollview, file,/asinh,title='Sinh!u-1!n Color Scale', /silent
mollview, file,/hist, title='Histogram Equalized Color Scale', /silent
mollview, file,/log, title='Log Scale', /silent
```

produces Mollweide projections of the same map (here the WMAP-5yr K band) with various color scales: linear, Inverse Hyperbolic Sine, Histogram Equalized, and Log. See Figure  $^3$  on page  $^{123}$ 




Figure 3: Illustration (generated by Example #5) of the various color scales available.

## EXAMPLES: #6

```
mollview, 'HFI_SkyMap_217_2048_R1.10_nominal.fits', $
    colt='planck2', asinh=2, factor=1.e6, offset=-1.33e-4, $
    min=-1.e3, max=1.e7, title='Planck @ 217GHz', charsize=2
```

Illustrates the application of the second color table created by planck\_colors to the visualization of Planck data at 217GHz (see Fig. 4 on page 124)

#### Planck @ 217GHz





Figure 4: Illustration (generated by Example #6) of the application of Planck color table #2 to a Planck sky map.

## EXAMPLES: #7

```
mollview, findgen(12), silhouette=2, default_settings=dsmoll,$
    title='Wider, thicker color bar; left justified title',$
    customize={cbar:{dx:2/3.,dy:1/32.,ty:0.005,box:2},$
        title:{x:0,charsize:2}}
help st, dsmoll
```

will generate a silhouetted Mollweide projection plot with customized thickness and length of a boxed color bar, and modified location of the title (see Fig. 5 on page 125). The default value (in the Mollweide projection) of the available customization parameters is also listed as






Figure 5: Illustration (generated by Example #7) of customization of the title (size and location) and of the color bar (size and box), and overplotting of a silhouette around the project map.

## neighbours\_nest

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/neighbours\_nest.pro">src/idl/toolkit/neighbours\_nest.pro</a>

This IDL facility returns the number and indices of the topological immediate neighbours of a central pixel. The pixels are ordered in a clockwise sense (when watching the sphere from the outside) about the central pixel with the southernmost pixel in first element. For the four pixels in the southern corners of the equatorial faces which have two equally southern neighbours the routine returns the southwestern pixel first and proceeds clockwise.

## **FORMAT**

IDL> neighbours nest (Nside, Ipix0, Listpix[,Nneigh])

## **QUALIFIERS**

Nside	<b>HEALPix</b> resolution parameter (scalar integer), should be a valid Nside (power of 2)
Ipix0	NESTED-scheme index of central pixel in $[0,12*Nside^2-1]$
Listpix	output: list of neighbouring pixel (NESTED scheme index) of size Nneigh
Nneigh	optional output: number of neighbours of pixel #Ipix0. Usually 8, sometimes 7 (for 8 particular pixels) or 6 (if Nside=1)

DESCRIPTION neighbours\_nest calls pix2xy\_nest to find location of central pixel within the pixelation base-face, and then xy2pix nest to find neighbouring pixels within the same face, or one of the bit manipulation routines if the neighbouring pixel is on a different base-face.

#### RELATED ROUTINES

This section lists the routines related to **neighbours** nest.

neighbours\_nest 127

idl	version 6.4 or more is necessary to run neighbours_nest .
neighbours_ring	returns topological immediate neighbouring pixels of a given central pixel, using RING indexing.
query_disc, query_polygon,	
query_strip, query_triangle	render the list of pixels enclosed respectively in a given disc, polygon, latitude strip and triangle
nest2ring, ring2nest	conversion between NESTED and RING indices

### **EXAMPLE:**

neighbours\_nest , 4, 1, list, nneigh
print,nneigh,list

will return:8 90 0 2 3 6 4 94 91, listing the NESTED-indexed 8 neighbors of pixel #1 for Nside=4

# neighbours\_ring

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/neighbours\_ring.pro">src/idl/toolkit/neighbours\_ring.pro</a>

This IDL facility returns the number and indices of the topological immediate neighbours of a central pixel. The pixels are ordered in a clockwise sense (when watching the sphere from the outside) about the central pixel with the southernmost pixel in first element. For the four pixels in the southern corners of the equatorial faces which have two equally southern neighbours the routine returns the southwestern pixel first and proceeds clockwise.

# FORMAT IDL> neighbours\_ring (Nside, Ipix0, List-pix[,Nneigh])

## **QUALIFIERS**

Nside	<b>HEALPix</b> resolution parameter (scalar integer), should be a valid Nside (power of 2)
Ipix0	RING-scheme index of central pixel in $[0,12*Nside^2-1]$
Listpix	output: list of neighbouring pixel (RING scheme index) of size Nneigh
Nneigh	optional output: number of neighbours of pixel #Ipix0. Usually 8, sometimes 7 (for 8 particular pixels) or 6 (if Nside=1)

**DESCRIPTION** neighbours\_ring calls ring2nest, neighbours\_nest and nest2ring

#### RELATED ROUTINES

This section lists the routines related to **neighbours\_ring**.

idl version 6.4 or more is necessary to run neighbours ring .

neighbours\_ring 129

neighbours\_nest

query\_disc, query\_polygon, query\_strip, query\_triangle

nest2ring, ring2nest

returns topological immediate neighbouring pixels of a given central pixel, using NESTED indexing.

render the list of pixels enclosed respectively in a given disc, polygon, latitude strip and triangle conversion between NESTED and RING indices

#### **EXAMPLE:**

neighbours\_ring , 4, 1, list, nneigh
print,nneigh,list

will return:8 16 6 5 0 3 2 8 7 listing the RING-indexed 8 neighbors of pixel #1 for Nside=4

## nest2uniq

Location in HEALPix directory tree: src/idl/toolkit/nest2uniq.pro

This IDL facility turns  $N_{\text{side}}$  and (NESTED) pixel index into the Unique Identifier.

#### **FORMAT**

IDL> nest2uniq, Nside, Pnest, Puniq [,/HELP]

## **QUALIFIERS**

Nside (IN, scalar or vector Integer) The **HEALPix**  $N_{\text{side}}$ 

parameter(s)

Pnest (IN, scalar or vector Integer) (NESTED scheme)

pixel identification number(s) in the range  $\{0.12N_{\rm side}^2-1\}$ . If Nside is a scalar, Pnest can a be a scalar or a vector, if Nside is a vector, Pnest

must be a vector of the same size

Puniq (OUT, same size as Pnest) The HEALPix

Unique pixel identifier(s).

## **KEYWORDS**

/HELP If set, a documentation header is printed out, and

the routine exits

# **DESCRIPTION** nest2uniq turns the parameter $N_{\text{side}}$ (a power of 2) and the pixel index p into the Unique ID number $u = p + 4N_{\text{side}}^2$ . See "The Unique Identifier scheme" section in "**HEALPix** Introduction Document" for more details.

#### **EXAMPLE:**

nest2uniq, [1, 2, 4], [0, 0, 0], puniq print, puniq

nest2uniq 131

returns

4 16 64

since the first pixels (p=0) at  $N_{\rm side}=1,\,2$  and 4 are respectively the pixels with Unique ID numbers 4, 16 and 64.

#### RELATED ROUTINES

This section lists the routines related to **nest2uniq**.

uniq2nest Transforms Unique **HEALPix** pixel ID number

into Nside and Nested pixel number

pix2xxx,... to turn NESTED pixel index into sky coordinates

and back

## npix2nside

Location in HEALPix directory tree: src/idl/toolkit/npix2nside.pro

This IDL facility provides the **HEALPix** resolution parameter Nside corresponding to Npix pixels over the full sky.

FORMAT IDL> Nside=NPIX2NSIDE (Npix [, ER-ROR=])

**QUALIFIERS** 

Npix number of pixels over the full sky (scalar integer),

should be a valid Npix  $(N_{\text{pix}} = 12N_{\text{side}}^2 \text{ with } N_{\text{side}})$ 

power of 2 in  $\{1, ..., 2^{29}\}$ )

Nside on output: resolution parameter if Npix is valid,

-1 otherwise

**KEYWORDS** 

ERROR= error flag, set to 1 on output if Npix is NOT valid,

or stays to 0 otherwise.

**DESCRIPTION** npix2nside checks that the given Npix is valid  $(N_{\text{pix}} = 12N_{\text{side}}^2 \text{ with } N_{\text{side}} \text{ a power of 2 in } \{1, \dots, 2^{29}\})$  and then computes the corresponding resolution parameter  $N_{\text{side}}$ .

#### RELATED ROUTINES

This section lists the routines related to **npix2nside** .

idl version 6.4 or more is necessary to run npix2nside

.

nside2npix computes Npix corresponding to Nside

pix2xxx, ang2xxx, vec2xxx, ... conversion between vector or angles and pixel

index and vice-versa

npix2nside 133

vec2pix, pix2vec nest2ring, ring2nest conversion between vector and pixel index conversion between NESTED and RING indices

#### **EXAMPLE:**

Nside = npix2nside(49152, ERROR=error)

Nside will be 64 because 49152 is a valid pixel number (= $12*64^2$  and 64 is a power of 2), and error will be 0

#### **EXAMPLE:**

Nside = npix2nside(49151, ERROR=error)

Nside will be -1 and error: 1, because 49151 is not a valid number of **HEALPix** pixels over the full sky.

## nside2npix

Location in HEALPix directory tree: src/idl/toolkit/nside2npix.pro

This IDL facility provides the number of pixels  $N_{\rm pix}$  over the full sky corresponding to resolution parameter  $N_{\rm side}$ .

FORMAT IDL> Npix=NSIDE2NPIX (Nside[, ER-ROR=, /HELP])

**QUALIFIERS** 

Nside HEALPix resolution parameter (integer, scalar

or not), should be a valid  $N_{\text{side}}$  (power of  $2 \leq 2^{29}$ )

Npix number of pixels, same size as Nside,  $N_{\text{pix}} =$ 

 $12N_{\text{side}}^2$  if  $N_{\text{side}}$  is a valid resolution parameter or

-1 otherwise

**KEYWORDS** 

ERROR= error flag, set to 1 on output if Nside is NOT valid,

or stays to 0 otherwise.

/HELP if set on input, the documentation header is

printed, and the routine exits (with a returned

value of -1 and an error flag set to 0).

**DESCRIPTION** nside2npix checks that the given Nside is valid (power of 2 in  $\{1, \ldots, 2^{29}\}$ ) and then computes the corresponding number of pixels  $N_{\text{pix}} = 12N_{\text{side}}^2$ .

#### RELATED ROUTINES

This section lists the routines related to **nside2npix**.

idl version 6.4 or more is necessary to run nside2npix.

npix2nside computes Nside corresponding to Npix

nside2npix 135

pix2xxx, ang2xxx, vec2xxx, ...

vec2pix, pix2vec nest2ring, ring2nest conversion between vector or angles and pixel index and vice-versa

conversion between vector and pixel index conversion between NESTED and RING indices

#### **EXAMPLE:**

Npix = nside2npix(256, ERROR=error)

Npix will be 786432 the number of pixels over the full sky for the **HEALPix** resolution parameter 256 and error will be 0

#### **EXAMPLE:**

Npix = nside2npix(248, ERROR=error)

Npix will be -1 and error: 1, because 248 is not a valid value for a **HEALPix** resolution parameter

## nside2npweights

Location in HEALPix directory tree: src/idl/toolkit/nside2npweights.pro

This IDL facility provides the number pixel-based quadrature weights (in compact non-redundant form) for a given resolution parameter Nside. Because of the **HEALPix** layout symmetries,  $N_w \simeq N_{\rm pix}/16$ , allowing economical storage on disc.

FORMAT IDL> Npweights=NSIDE2NPWEIGHTS (Nside [,ERROR=, /HELP])

**QUALIFIERS** 

Nside **HEALPix** resolution parameter (integer, scalar

or not), should be a valid Nside (power of 2 in

 $\{1,\ldots,2^{29}\}$ 

Npweights number of non-redundant weights

**KEYWORDS** 

ERROR= error flag, set to 1 on output if Nside is NOT valid,

or stays to 0 otherwise.

/HELP if set on input, the documentation header is

printed out and the routine exits

DESCRIPTION nside 2 npweights outputs the number of different pixel-based weights

$$N_w = \frac{(N_{\text{side}} + 1)(3N_{\text{side}} + 1)}{4}.$$

If the argument  $N_{\rm side}$  is not valid, a warning is issued and the error flag is raised.

#### RELATED ROUTINES

This section lists the routines related to nside2npweights.

nside2npweights 137

idl version 6.4 or more is necessary to run

nside2npweights.

unfold\_weights generates a full sky map of pixel-based or ring-

based quadrature weights

### **EXAMPLE:**

Npweights = nside2npweights(256, ERROR=error)

Npweights will be 49408 the number of pixel-based weights for the **HEALPix** resolution parameter 256 and error will be 0

## nside2ntemplates

Location in HEALPix directory tree: src/idl/toolkit/nside2ntemplates.pro

This IDL facility provides the number of template pixels Ntemplates corresponding to resolution parameter Nside. Each template pixel has a different shape that can not be matched (by rotation or reflexion) to that of any of the other templates.

**FORMAT** 

Ntemplates=NSIDE2NTEMPLATES IDL> (Nside[,ERROR=])

**QUALIFIERS** 

Nside **HEALPix** resolution parameter (integer, scalar

or not), should be a valid Nside (power of 2 in

 $\{1,\ldots,2^{29}\}$ 

Ntemplates number of templates

**KEYWORDS** 

ERROR= error flag, set to 1 on output if Nside is NOT valid,

or stays to 0 otherwise.

DESCRIPTION nside 2 ntemplates outputs the number of template pixels

$$N_{\text{template}} = \frac{1 + N_{\text{side}}(N_{\text{side}} + 6)}{4}.$$

If the argument  $N_{\text{side}}$  is not valid, a warning is issued and the error flag is raised.

#### RELATED ROUTINES

This section lists the routines related to **nside2ntemplates**.

idl version 6.4 or more is necessary to

nside2ntemplates.

nside2ntemplates 139

template\_pixel\_ring
template\_pixel\_nest
return the template pixel associated with any
HEALPix pixel
same\_shape\_pixels\_ring
same\_shape\_pixels\_nest
return the ordered list of pixels having the same
shape as a given pixel template

#### **EXAMPLE:**

Ntemplates = nside2ntemplates(256, ERROR=error)

Ntemplates will be 16768 the number of template pixels for the **HEALPix** resolution parameter 256 and error will be 0

## orthcursor

#### Location in HEALPix directory tree: src/idl/visu/orthcursor.pro

This IDL facility provides a point-and-click interface for finding the astronomical location, value and pixel index of the pixels nearest to the pointed position on a orthographic projection of a **HEALPix** map.

## **QUALIFIERS**

see mollcursor

**DESCRIPTION** orthcursor should be called immediately after orthview. It gives the longitude, latitude, map value and pixel number corresponding to the cursor position in the window containing the map generated by orthview. For more details, or in case of problems under Mac OS X, see mollcursor.

#### RELATED ROUTINES

This section lists the routines related to **orthcursor**.

see mollcursor

#### **EXAMPLE:**

orthcursor

After orthview has read in a map and generated its orthographic projection, orthcursor is run to determine the position and flux of bright synchrotron sources, for example.

orthview 141

## orthview

#### Location in HEALPix directory tree: src/idl/visu/orthview.pro

This IDL facility provides a means to visualise a full sky or half sky orthographic projection (projection onto a tangent plane from a point located at infinity) of **HEALPix** and COBE Quad-Cube maps in an IDL environment. It also offers the possibility to generate GIF, JPEG, PDF, PNG and Postscript color-coded images of the projected map. The projected (but not color-coded) data can also be output in FITS files and IDL arrays.

#### **FORMAT**

ORTHVIEW, IDL> File [, Select] [, AS-INH=, BAD COLOR=, BG COLOR=, CHARSIZE=, CHARTHICK=, COLT=, COORD=, /CROP, CUS-TOMIZE=, DEFAULT SETTINGS=, EXECUTE=, FAC-TOR=, FG\_COLOR=, FITS=, /FLIP, GAL\_CUT=, GIF=, GLSIZE=, GRATICULE=, /HALF SKY, HBOUND=, /HELP, /HIST EQUAL, HXSIZE=, IGLSIZE=, IGRATIC-ULE=, JPEG=, LATEX=, /LOG, MAP\_OUT=, MAX=, MIN=, /NESTED, /NO\_DIPOLE, /NO\_MONOPOLE, /NOBAR, /NOLABELS, /NOPOSITION, OFFSET=, OUT-LINE=, PDF=, PFONTS=, PNG=, POLARIZATION=, /PREVIEW, PS=, PXSIZE=, PYSIZE=, RESO\_ARCMIN=, RETAIN=, ROT=, /SAVE, /SHADED, /SILENT, SIL-HOUETTE=, STAGGER=, SUBTITLE=, TITLEPLOT=, TRANSPARENT=, TRUECOLORS=, UNITS=, WIN-DOW=, XPOS=, YPOS=

## **QUALIFIERS**

For a full list of qualifiers see mollview

#### **KEYWORDS**

For a full list of keywords see mollview

### **DESCRIPTION**

orthview reads in a **HEALPix** sky map in FITS format and generates an orthographic projection of it, that can be visualized on the screen or exported in a GIF, JPEG, PNG, PDF or Postscript file. orthview allows the selection of the coordinate system, map size, color table, color bar inclusion, linear, log, hybrid or histogram equalised color scaling, maximum and minimum range for the plot, plot-title *etc*. It also allows the representation of the polarization field.

#### RELATED ROUTINES

This section lists the routines related to **orthview**.

see mollview

#### **EXAMPLE:**

```
map = findgen(48)
triangle= create_struct('coord','G','ra',[0,80,0],'dec',[40,45,65])
orthview,map,/online,graticule=[45,30],rot=[10,20,30],$
    title='Orthographic projection',subtitle='orthview' $
    outline=triangle
```

makes an orthographic projection of map (see Figure 1d on page 122) after an arbitrary rotation, with a graticule grid (with a  $45^{o}$  step in longitude and  $30^{o}$  in latitude) and an arbitrary triangular outline

outline earth 143

## outline earth

Location in HEALPix directory tree: <a href="mailto:src/idl/visu/outline\_earth.pro">src/idl/visu/outline\_earth.pro</a>

This IDL facility generates an outline of the Earth continents, coast lines, countries and/or rivers, at various resolution, which can then be overplotted onto **HEALPix** maps using the outline option of cartview, gnomview, mollview or orthview.

## **FORMAT**

IDL> geo = OUTLINE\_EARTH([geo\_in], [BEHAVIOR=, /COASTS, COLOR=, /CONTINENTS, /COUNTRIES, /HELP, HIRES=, LINESTYLE=, /RIVERS, THICK=])

## **QUALIFIERS**

geo output IDL structure

geo\_in optional input IDL structure generated by a pre-

vious call to outline\_earth, which will be included

into the output geo (see Example)

## **KEYWORDS**

BEHAVIOR= either 'GDL', 'IDL' or absent: changes the origin

of the Earth data (see below)

/COASTS if set, adds coastlines, islands, and lakes in-

formation in geo with the features COLOR,

LINESTYLE and THICK.

COLOR= scalar or 2-element array: color index to be given

to geographical data in final plot in [0, 255]. See

outline of mollview for details.

/CONTINENTS if set, adds continental boundaries

/COUNTRIES if set, adds political boundaries (as of 1993)

/HELP if set, prints extended help

HIRES = if set > 0 use high resolution information (if it is

available) instead of default low resolution one.

Either 0 or 1 (and more) in IDL mode;

in 0,1,2,3,4 in GDL mode.

Beware that Hires data are voluminous, longer to process and will result in large PNG or PDF files

when plotted with eg mollview

LINESTYLE= linestyle given to current geographical outline(s).

(**default:** 0). See outline of mollview for details.

/RIVERS if set, adds rivers

THICK =thickness of the geographical lines (**default:** 1.0).

See outline of mollview for details.

**DESCRIPTION** outline\_earth reads Earth data from disk (see below) and generates outlines of the Earth continents, coast lines, countries and/or rivers (in combination or separately), at various resolution, with a user-specified color, linestyle and thickness, which can then be overplotted onto **HEALPix** maps using cartview, gnomview, mollview or orthview.

> - If run under IDL (or if BEHAVIOR='IDL') the Earth data are read from \$IDL DIR/resource/maps/\*/\*.\* with 'low' (HIRES=0) and if available 'high' (HIRES≥1) resolution.

> run under GDL (or if BEHAVIOR='GDL') GSHHS 2.2the data (version or more, https://www.ngdc.noaa.gov/mgg/shorelines/ atdata/gshhg/latest/gshhg-bin-\*.zip) are read \$GSHHS DATA DIR/\*.b with HIRES=0,1,2,3,4 standing for 'coarse', 'low', 'intermediate', 'high' and 'full' resolution respectively.

In GDL mode, Coasts and Continents are degenerate.

- Under FL, BEHAVIOR must be set to either 'IDL' or 'GDL', and the corresponding data must be available.

#### RELATED ROUTINES

This section lists the routines related to **outline\_earth**.

idl version 6.4 or more is necessary to run out-

line earth.

cartview, gnomview

mollview, orthview visualization routines that overplot the Earth geographical outlines generated by outline earth)

outline\_earth 145

#### **EXAMPLE:**

```
geo = outline_earth(/continents,/hires,thick=0.8)
geo = outline_earth(geo, /rivers, thick=0.1,col=20)
mollview, findgen(12), $
   outline=geo, /flip, coord=['C','C'], $
   min=-11,max=11,colt='planck1',/crop
```

Creates a structure containing a thick-lined high-resolution continent outline, adds a thin-lined lower resolution rivers outline, in a different color, and then overplots the combination on a Mollweide projection of a (simple) **HEALPix** map (see Fig. 6 on page 145) Note that since Earth data (generated in Celestial = eQuatorial coordinates) are usually shown with the longitude increasing from left to right (contrary to astronomical data), the flip keyword must be set in mollview.




Figure 6: Illustration of the Earth outlines created by outline\_earth.

# pix2xxx, ang2xxx, vec2xxx, nest2ring, ring2nest

Location in HEALPix directory tree: src/idl/toolkit/

These routines provide conversion between pixel number in the **HEALPix** map and  $(\theta, \phi)$  or (x, y, z) coordinates on the sphere. Some of these routines are listed here.

QUALIFIERS			
name (dim.)	type	in/out	description
nside	scalar integer	IN	$N_{\text{side}}$ parameter for the <b>HEALPix</b> map.
ipnest(n)	vector integer	_	pixel identification number in NESTED scheme over the range $\{0, N_{\text{pix}} - 1\}$ .
ipring(n)	vector integer	_	pixel identification number in RING scheme over the range $\{0, N_{\text{pix}} - 1\}$ .
theta(n)	vector double	_	colatitude in radians measured southward from north pole in $\{0,\pi\}$
phi(n)	vector double		longitude in radians, measured eastward in $\{0,2\pi\}$ .
vector(n,3) vertex(n,3,4)	array double	optional OUT	three dimensional cartesian position vector $(x, y, z)$ . The north pole is $(0, 0, 1)$ . An output vector is normalised to unity. The coordinates are ordered as follows $x(0), \ldots, x(n-1), y(0), \ldots, y(n-1), z(0), \ldots, z(n-1)$ . three dimensional cartesian position vector $(x, y, z)$ . Contains the location of the four vertices (=corners) of a pixel in the order North, West, South, East. The coordinates are ordered as follows $x_N(0), \ldots, x_N(n-1), y_N(0), \ldots, y_N(n-1), z_N(0), \ldots, z_N(n-1), x_W(0), \ldots, x_W(n-1), y_W(0), \ldots, y_W(n-1), x_W(0), x_W(n-1), x_W(0), x_W(n-1$
			$z_W(0), \ldots, z_W(n-1)$ , and so on with South and East vertices

#### **ROUTINES:**

pix2ang\_ring, nside, ipring, theta, phi

renders theta and phi coordinates of the nominal pixel center given the pixel number ipring and a map resolution parameter nside.

pix2vec\_ring, nside, ipring, vector [,vertex]

renders cartesian vector coordinates of the nominal pixel center given the pixel number **ipring** and a map resolution parameter **nside**. Optionally returns the location of the 4 vertices for the pixel(s) under consideration

ang2pix\_ring, nside, theta, phi, ipring

renders the pixel number ipring for a pixel which, given the map resolution parameter nside, contains the point on the sphere at angular coordinates theta and phi.

vec2pix\_ring, nside, vector, ipring

renders the pixel number ipring for a pixel which, given the map resolution parameter nside, contains the point on the sphere at cartesian coordinates vector.

pix2ang\_nest, nside, ipnest, theta, phi

renders theta and phi coordinates of the nominal pixel center given the pixel number ipnest and a map resolution parameter nside.

pix2vec\_nest, nside, ipnest, vector [,vertex]

renders cartesian vector coordinates of the nominal pixel center given the pixel number **ipnest** and a map resolution parameter **nside**. Optionally returns the location of the 4 vertices for the pixel(s) under consideration

ang2pix\_nest, nside, theta, phi, ipnest

renders the pixel number **ipnest** for a pixel which, given the map resolution parameter **nside**, contains the point on the sphere at angular coordinates **theta** and **phi**.

vec2pix nest, nside, vector, ipnest

renders the pixel number ipnest for a pixel which, given the map resolution parameter nside, contains the point on the sphere at cartesian coordinates vector.

nest2ring, nside, ipnest, ipring

performs conversion from NESTED to RING pixel number.

ring2nest, nside, ipring, ipnest

performs conversion from RING to NESTED pixel number.

#### RELATED ROUTINES

This section lists the routines related to pix2xxx, ang2xxx, vec2xxx, nest2ring, ring2nest.

idl version 6.4 or more is necessary to run pix2xxx,

ang2xxx,... .

npix2nside computes  $N_{\text{side}}$  (resolution) corresponding to Npix

(total pixel number)

nside2npix computes  $N_{pix}$  corresponding to  $N_{side}$ 

ang2vec, vec2ang geometrical conversion between position angles

and position vector

nest2uniq, uniq2nest conversion of standard pixel index to/from Unique

ID number

#### **EXAMPLE:**

pix2ang\_ring, 256, [17,1000], theta, phi print, theta, phi

returns

0.0095683558 0.070182078

2.8797933 5.4620872

position of the two pixels #17 and 1000 in the RING scheme

with parameter  $N_{\text{side}} = 256$ .

planck\_colors 149

#### planck\_colors

Location in HEALPix directory tree: <a href="mailto:src/idl/visu/planck\_colors.pro">src/idl/visu/planck\_colors.pro</a>

This IDL facility provides RGB color tables suitable for visualization of sky maps dominated by CMB or featuring foreground, and modify current color table. Those color tables can then be implemented in cartview, gnomview, mollview or orthview and were used in Planck 2013 publications

FORMAT IDL> PLANCK\_COLORS, option, [GET=rgb, /HELP, /SHOW]

#### **QUALIFIERS**

option

required input for color table generation, must be either 1 or 2:

1: creates the 'parchment' Blue-red color table suitable for maps dominated by Gaussian signal (eg, CMB)

2: creates a Blue-red-white color table suitable for maps with high dynamic signal (eg, Galactic foreground)

#### **KEYWORDS**

GET=rgb optional ouput, contains the newly created RGB

color table in a [256, 3] array

/HELP if set, prints extended help

/SHOW if set, the chosen color table is shown in a new

window

**DESCRIPTION**planck\_colors creates a set of RGB color tables suitable for specific purpose, and modify the current IDL color table accordingly (using TVLCT). See below the example applications. The created color table can also be output as a 256\*3 array, or shown in a new window

#### RELATED ROUTINES

This section lists the routines related to planck\_colors.

idl version 6.4 or more is necessary to run

planck\_colors.

cartview, gnomview mollview, orthview

visualization routines that can make use of the

color tables created in planck\_colors (via keyword

colt)

loadct IDL routine to set current color table to one of

the predefined IDL color tables (thus reverting the

effect of planck\_colors).

#### **EXAMPLE:**

planck\_colors, 1, /show
planck\_colors, 2, /show

Create and show the two color tables (see Fig. 7 on page 150)




Figure 7: Illustration of the color tables created by planck\_colors.

query\_disc 151

## query\_disc

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/query\_disc.pro">src/idl/toolkit/query\_disc.pro</a>

This IDL facility provides a means to find the index of all pixels within an angular distance Radius from a defined center.

#### **FORMAT**

IDL> query\_disc , Nside, Vector0, Radius, Listpix, [Nlist, /DEG, /NESTED, /INCLU-SIVE]

#### **QUALIFIERS**

Nside **HEALPix** resolution parameter used to index

the pixel list (scalar integer)

Vector0 position vector of the disc center (3 elements vec-

tor) NB: the norm of Vector0 does not have to be one, what is consider is the intersection of the

sphere with the line of direction Vector0.

Radius radius of the disc (in radians, unless DEG is set),

(scalar real)

Listpix on output: list of ordered index for the pixels

found within a radius Radius of the position defined by vector0. The RING numbering scheme is used unless the keyword NESTED is set. (=-1 if the

radius is too small and no pixel is found)

Nlist on output: number of pixels in Listpix (=0 if no

pixel is found).

#### **KEYWORDS**

/DEG if set Radius is in degrees instead of radians

/NESTED if set, the output list uses the NESTED numbering

scheme instead of the default RING

/INCLUSIVE if set, all the pixels overlapping (even partially)

with the disc are listed, otherwise only those

whose center lies within the disc are listed

**DESCRIPTION**query\_disc finds the pixels within the given disc in a selective way WITHOUT scanning all the sky pixels. The numbering scheme of the output list and the inclusiveness of the disc can be changed

#### RELATED ROUTINES

This section lists the routines related to query\_disc .

idl	version $6.4$ or more is necessary to run query_disc
ang2pix, pix2ang	conversion between angles and pixel index
vec2pix, pix2vec	conversion between vector and pixel index
query_disc, query_polygon,	
query_strip, query_triangle	render the list of pixels enclosed respectively in
	a given disc, polygon, latitude strip and triangle

#### **EXAMPLE:**

query\_disc , 256L, [.5,.5,0.], 10., listpix, nlist, /Deg, /Nest

On return listpix contains the index of the (5982) pixels within 10 degrees from the point on the sphere having the direction [.5,.5,0.]. The pixel indices correspond to the Nested scheme with resolution 256.

query\_polygon 153

#### query\_polygon

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/query\_polygon.pro">src/idl/toolkit/query\_polygon.pro</a>

This IDL facility provides a means to find the index of all pixels belonging to a sperical polygon defined by its vertices

**FORMAT** 

IDL> query\_polygon , Nside, Vlist, Listpix, [Nlist, HELP=, NESTED=, INCLUSIVE=]

**QUALIFIERS** 

Nside **HEALPix** resolution parameter used to index

the pixel list (scalar integer)

Vlist 3D cartesian position vector of the polygon ver-

tices. Array of dimension (n,3) where n is the

number of vertices

Listpix on output: list of ordered index for the pixels

found in the polygon. The RING numbering scheme is used unless the keyword NESTED is set. (=-1 if the polygon is too small and no pixel is

found)

Nlist on output: number of pixels in Listpix (=0 if no

pixel is found).

**KEYWORDS** 

HELP= if set, the documentation header is printed out

and the routine exits

NESTED if set, the output list uses the NESTED numbering

scheme instead of the default RING

INCLUSIVE if set, all the pixels overlapping (even partially)

with the polygon are listed, otherwise only those

whose center lies within the polygon are listed

DESCRIPTION query polygon finds the pixels within the given polygon in a selective way WITHOUT scanning all the sky pixels. The polygon should be convex, or have only one concave vertex. The edges should not intersect each other. The numbering scheme of the output list and the inclusiveness of the polygon can be changed

#### RELATED ROUTINES

This section lists the routines related to query\_polygon.

idl	version 6.4 or more is necessary to run query_polygon.
ang2pix, pix2ang	conversion between angles and pixel index
vec2pix, pix2vec	conversion between vector and pixel index
query_disc, query_polygon,	
query_strip, query_triangle	render the list of pixels enclosed respectively in a given disc, polygon, latitude strip and triangle

#### **EXAMPLE:**

query\_polygon , 256L, [[0,1,1,0],[0,0,1,1],[1,0,-1,0]], listpix, nlist

On return listpix contains the index of the (131191) pixels contained in the polygon with vertices of cartesian coordinates (0,0,1), (1,0,0), (1,1,-1) and (0,1,0). The pixel indices correspond to the RING scheme with resolution 256.

query\_strip 155

## query\_strip

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/query\_strip.pro">src/idl/toolkit/query\_strip.pro</a>

This IDL facility provides a means to find the index of all pixels belonging to a latitude strip defined by its bounds

**FORMAT** 

IDL> query\_strip , Nside, Theta1, Theta2,
Listpix, [Nlist, NESTED=, INCLUSIVE=,
HELP=]

**QUALIFIERS** 

Nside **HEALPix** resolution parameter used to index

the pixel list (scalar integer)

Theta1 colatitude lower bound in radians measured from

North Pole (between 0 and  $\pi$ ).

Theta2 colatitude upper bound in radians measured from

North Pole (between 0 and  $\pi$ ). If theta1< theta2, the pixels lying in [theta1,theta2] are output, otherwise, the pixel lying in [0, theta2] and those

lying in [theta1,  $\pi$ ] are output.

Listpix on output: list of ordered index for the pixels

found in the strip. The RING numbering scheme is used unless the keyword NESTED is set. (=-1 if

the strip is too small and no pixel is found)

Nlist on output: number of pixels in Listpix (=0 if no

pixel is found).

**KEYWORDS** 

NESTED= if set, the output list uses the NESTED numbering

scheme instead of the default RING

INCLUSIVE= if set, all the pixels overlapping (even partially)

with the strip are listed, otherwise only those

whose center lies within the strip are listed

/HELP if set, the routine prints its documentation header and exits.

**DESCRIPTION** query\_strip finds the pixels within the given strip in a selective way WITHOUT scanning all the sky pixels. The numbering scheme of the output list and the inclusiveness of the strip can be changed

#### RELATED ROUTINES

This section lists the routines related to query\_strip.

idl	version 6.4 or more is necessary to run query_strip
	•
ang2pix, pix2ang	conversion between angles and pixel index
vec2pix, pix2vec	conversion between vector and pixel index
query_disc, query_polygon,	
$query\_triangle$	render the list of pixels enclosed respectively in a
	given disc, polygon and triangle

#### **EXAMPLE:**

query\_strip , 256, 0.75\*!PI, !PI/5, listpix, nlist, /nest

Returns the NESTED pixel index of all pixels with colatitude in  $[0,\pi/5]$  and those with colatitude in  $[3\pi/4,\pi]$ 

query\_triangle 157

### query\_triangle

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/query\_triangle.pro">src/idl/toolkit/query\_triangle.pro</a>

This IDL facility provides a means to find the index of all pixels belonging to a sperical triangle defined by its vertices

**FORMAT** 

IDL> query\_triangle , Nside, Vector1, Vector2, Vector3, Listpix, [Nlist, NESTED=, IN-CLUSIVE=]

**QUALIFIERS** 

Nside **HEALPix** resolution parameter used to index

the pixel list (scalar integer)

Vector 1 3D cartesian position vector of the triangle first

vertex

Vector 2 3D cartesian position vector of the triangle second

vertex

Vector3 3D cartesian position vector of the triangle third

vertex NB: the norm of Vector\* does not have to be one, what is considered is the intersection of

the sphere with the line of direction Vector\*.

Listpix on output: list of ordered index for the pix-

els found in the triangle. The RING numbering scheme is used unless the keyword NESTED is set. (=-1 if the triangle is too small and no pixel is

found)

Nlist on output: number of pixels in Listpix (=0 if no

pixel is found).

**KEYWORDS** 

NESTED if set, the output list uses the NESTED numbering

scheme instead of the default RING

INCLUSIVE if set, all the pixels overlapping (even partially)

with the triangle are listed, otherwise only those whose center lies within the triangle are listed

HEALPix 3.83

# **DESCRIPTION**query\_triangle finds the pixels within the given triangle in a selective way WITHOUT scanning all the sky pixels. The numbering scheme of the output list and the inclusiveness of the triangle can be changed

#### RELATED ROUTINES

This section lists the routines related to query\_triangle .

idl	version 6.4 or more is necessary to run query_triangle.
ang2pix, pix2ang	conversion between angles and pixel index
vec2pix, pix2vec	conversion between vector and pixel index
query_disc, query_polygon,	
query_strip, query_triangle	render the list of pixels enclosed respectively in a given disc, polygon, latitude strip and triangle

#### **EXAMPLE:**

```
query_triangle , 256L, [1,0,0],[0,1,0],[0,0,1], listpix, nlist
```

On return listpix contains the index of the (98560) pixels lying in the octant (x > 0, y > 0, y > 0). The pixel indices correspond to the RING scheme with resolution 256.

read fits cut4

#### read fits cut4

Location in HEALPix directory tree: <a href="mailto:src/idl/fits/read\_fits\_cut4.pro">src/idl/fits/read\_fits\_cut4.pro</a>

This IDL facility reads a cut sky **HEALPix** map from a FITS file according to the **HEALPix** convention. The format used for the FITS file follows the one used for Boomerang98 and is adapted from COBE/DMR. This routine can also be used to read polarized cut sky map, where each Stokes parameter is stored in a different extension of the same FITS file.

#### **FORMAT**

IDL> READ\_FITS\_CUT4, File, Pixel, Signal[, N\_Obs, Serror, EXTENSION=, HDR=, XHDR=, NSIDE=, ORDERING=, COORDSYS=, HELP=]

#### **QUALIFIERS**

File name of a FITS file in which the map is to be

written

Pixel (OUT, LONG vector),

index of observed (or valid) pixels

Signal (OUT, FLOAT vector),

value of signal in each observed pixel

N Obs (OUT, LONG or INT vector, Optional),

number of observation per pixel

Serror (OUT, FLOAT vector, Optional),

rms of signal in pixel. For white noise, this is

 $\propto 1/\sqrt{\text{n}_{\text{obs}}}$ 

#### **KEYWORDS**

EXTENSION= (IN, optional),

0 based number of extension to read. Extension 0 contains the temperature information, while extensions 1 and 2 contain respectively the  ${\bf Q}$  and  ${\bf U}$  Stokes parameters related information.

(default: 0)

HDR= (OUT, optional),

String array containing the primary header.

XHDR= (OUT, optional),

String array containing the extension header.

NSIDE = (OUT, optional),

returns on output the **HEALPix** resolution parameter, as read from the FITS header. Set to -1

if not found

ORDERING= (OUT, optional),

returns on output the pixel ordering, as read from

the FITS header. Either 'RING' or 'NESTED' or

' ' (if not found).

COORDSYS= (OUT, optional),

returns on output the astrophysical coordinate system used, as read from FITS header (value of

keywords COORDSYS or SKYCOORD)

HELP= (IN, optional),

if set, an extensive help is displayed, and no file is

read

**DESCRIPTION**For more information on the FITS file format supported in **HEALPix**, including the one implemented in read\_fits\_cut4, see https://healpix.sourceforge.io/data/examples/healpix\_fits\_specs.pdf.

#### RELATED ROUTINES

This section lists the routines related to read\_fits\_cut4.

idl version 6.4 or more is necessary to run

read\_fits\_cut4

write fits cut4 This HEALPix IDL facility can be used to

generate the FITS format cut-sky maps complient with  $\mathbf{HEALPix}$  convention and readable

by read\_fits\_cut4.

read\_fits\_cut4, read\_fits\_partial, read\_fits\_map

read\_tqu, read\_fits\_s

HEALPix IDL routines to read cut-sky maps
and partial maps, full-sky maps, polarized full-sky

maps and arbitrary data sets from FITS files

read\_fits\_cut4 161

sxpar

This IDL routine (included in  ${\bf HEALPix}$  package) can be used to extract FITS keywords from the header(s) HDR or XHDR read with read\_fits\_cut4 .

#### read\_fits\_map

Location in HEALPix directory tree: src/idl/fits/read\_fits\_map.pro
This IDL facility reads in a HEALPix map from a FITS file.

FORMAT

IDL> READ\_FITS\_MAP , File, T\_sky,

[Hdr, Exthdr, PIXEL=, SILENT=, NSIDE=,

ORDERING=, COORDSYS=, EXTEN
SION=, HELP=]

#### **QUALIFIERS**

File name of a FITS file containing the **HEALPix** 

map in an extension or in the image field

T\_sky variable containing on output the **HEALPix** map

Hdr (optional),

string variable containing on output the FITS pri-

mary header

Exthdr (optional),

string variable containing on output the FITS ex-

tension header

PIXEL= (optional),

pixel number to read from or pixel range to read (in the order of appearance in the file), starting

(in the order of appearance in the file), starting

from 0.

if  $\geq 0$  scalar: read from pixel to the end of the

file

if two elements array: reads from pixel[0] to

pixel[1] (included)

if absent: read the whole file

NSIDE= (optional),

returns on output the **HEALPix** resolution pa-

rameter, as read from the FITS header. Set to -1

if not found

ORDERING= (optional),

returns on output the pixel ordering, as read from

read fits map

the FITS header. Either 'RING' or 'NESTED' or

' ' (if not found).

COORDSYS = (optional),

returns on output the astrophysical coordinate system used, as read from FITS header (value of

keywords COORDSYS or SKYCOORD)

EXTENSION = (optional),

extension unit to be read from FITS file: either its 0-based ID number (ie, 0 for first extension after primary array) or the case-insensitive value of its EXTNAME keyword. If absent, all available

extensions are read.

#### **KEYWORDS**

HELP= if set, an extensive help is displayed and no file is

read

SILENT= if set, no message is issued during normal execu-

tion

DESCRIPTION read\_fits\_map reads in a HEALPix sky map from a FITS file, and outputs the variable T\_sky, where the optional variables

and outputs the variable T\_sky, where the optional variables Hdr and Exthdr contain respectively the primary and extension headers. According to HEALPix convention, the map should be is stored as a FITS file binary table extension. Note:the routine read\_tqu which requires less memory is recommended

when reading *large polarized* maps.

#### RELATED ROUTINES

This section lists the routines related to **read\_fits\_map**.

idl version 6.4 or more is necessary to run

read\_fits\_map

read fits cut4, read fits partial, read fits map

read\_tqu, read\_fits\_s HEALPix IDL routines to read cut-sky maps

and partial maps, full-sky maps, polarized full-sky maps and arbitrary data sets from FITS files

sxpar This IDL routine (included in **HEALPix** pack-

age) can be used to extract FITS keywords from the header(s) Hdr or Exthdr read with

read\_fits\_map.

synfast This **HEALPix** facility will generate the

FITS format sky map that can be read by

read\_fits\_map.

write\_fits\_map This HEALPix IDL facility can be used to

generate the FITS format sky maps complient with **HEALPix** convention and readable by

read\_fits\_map.

#### **EXAMPLE:**

read\_fits\_map, 'planck100GHZ-LFI.fits', map, hdr, xhdr, /silent

read\_fits\_map reads in the file 'planck100GHZ-LFI.fits' and outputs the **HEALPix** map in map, the primary header in hdr and the extension header in xhdr.

read\_fits\_partial 165

### read\_fits\_partial

Location in HEALPix directory tree: <a href="mailto:src/idl/fits/read\_fits\_partial.pro">src/idl/fits/read\_fits\_partial.pro</a>

This IDL facility reads FITS file containing incomplete (polarized) sky map.

#### **FORMAT**

IDL> READ\_FITS\_PARTIAL, File, Pixel, IQU[, COORDSYS=, EXTENSION=, HDR=, HELP=, NSIDE=, ORDERING=, UNITS=, XHDR=]

#### **QUALIFIERS**

File name of a FITS file in which the map is to be

written

Pixel (OUT: INT, LONG or LONG64 vector of length

 $n_{\rm p}),$ 

index of observed (or valid) pixels

IQU (OUT: FLOAT or DOUBLE array of size  $(n_p)$ 

 $n_{\rm c})),$ 

value of I or I, Q, U signal in each observed pixel

#### **KEYWORDS**

COORDSYS= (OUT, optional),

returns on output the astrophysical coordinate system used, as read from FITS header (value of

keywords COORDSYS or SKYCOORD)

EXTENSION = (IN, optional),

0 based number of extension to read. (**default:** 0)

HDR= (OUT, optional),

String array containing the primary header.

HELP= (IN, optional),

if set, an extensive help is displayed, and no file is

read

NSIDE= (OUT, optional),

returns on output the **HEALPix** resolution pa-

rameter, as read from the FITS header. Set to -1

if not found

ORDERING= (OUT, optional),

returns on output the pixel ordering, as read from

the FITS header. Either 'RING' or 'NESTED' or

' ' (if not found).

UNITS= (OUT, optional),

physical units of each column of the table (except

PIXEL)

XHDR= (OUT, optional),

String array containing the extension header.

**DESCRIPTION**For more information on the FITS file format supported in **HEALPix**, including the one implemented in read\_fits\_partial, see <a href="https://healpix.sourceforge.io/data/examples/healpix fits specs.pdf">https://healpix.sourceforge.io/data/examples/healpix fits specs.pdf</a>

#### RELATED ROUTINES

This section lists the routines related to read fits partial.

idl version 6.4 or more is necessary to run

read fits partial

write fits partial This HEALPix IDL facility can be used to

generate the FITS format partial maps complient with **HEALPix** convention and readable

by read\_fits\_partial.

read\_fits\_cut4, read\_fits\_partial, read\_fits\_map

read tqu, read fits s HEALPix IDL routines to read cut-sky maps

and partial maps, full-sky maps, polarized full-sky  $\,$ 

maps and arbitrary data sets from FITS files

sxpar This IDL routine (included in **HEALPix** pack-

age) can be used to extract FITS keywords from the header(s) HDR or XHDR read with

read\_fits\_partial.

read fits s 167

#### fits read

Location in HEALPix directory tree: src/idl/fits/read fits s.pro This IDL facility reads a FITS file into an IDL structure.

**FORMAT** IDL> READ FITS S , File, Prim stc. [Xten\_stc, COLUMNS=, EXTENSION=. /HELP, /MERGE]

#### **QUALIFIERS**

File name of a FITS file containing the healpix map(s)

in an extension or in the image field

Prim stc variable containing on output an IDL structure

with the following fields:

- primary header (tag: 0, tag name: HDR)

- primary image (if any, tag: 1, tag name: IMG)

Xten stc (optional).

variable containing on output an IDL structure

with the following fields:

- extension header (tag: 0, tag name: HDR)

- data column 1 (if any, tag: 1, tag name given by TTYPE1 (with all spaces removed and only

letters, digits and underscore)

- data column 2 (if any, tag: 2, tag name given

by TTYPE2)

...

COLUMNS= (optional),

> list of columns to be read from a binary table can be a list of integer (1 based) indexing the columns positions or a list of names matching the TTYPE\*

of the columns by default, all columns are read

EXTENSION= (optional).

> extension unit to be read from FITS file: either its 0-based ID number (ie, 0 for first extension after primary array) or the case-insensitive value of its

EXTNAME keyword. (default: 0)

#### **KEYWORDS**

/HELP if set, an extensive help is displayed and no file is

read

/MERGE if set Prim\_stc contains :

- the concatenated primary and extension header

(tag name : HDR)

- primary image (if any, tag name : IMG)

- data column 1 ...

and Exten\_stc is set to 0

(default: :) not set (or set to 0)

**DESCRIPTION**read\_fits\_s reads in any type of FITS file (Image, Binary table or Ascii table) and outputs the data in IDL structures

#### RELATED ROUTINES

This section lists the routines related to **read\_fits\_s**.

idl

synfast

version 6.4 or more is necessary to run read\_fits\_s This **HEALPix** facility will generate the FITS format sky map that can be read by read fits s

•

read\_fits\_cut4, read\_fits\_partial, read\_fits\_map

read\_tqu, read\_fits\_s

**HEALPix** IDL routines to read cut-sky maps and partial maps, full-sky maps, polarized full-sky maps and arbitrary data sets from FITS files

write fits sb

This **HEALPix** IDL facility can be used to generate FITS format sky maps readable by read\_fits\_s.

#### **EXAMPLE:**

read fits s , 'dmr skymap 90a 4yr.fits', pdata, xdata

read\_fits\_s reads in the file 'dmr\_skymap\_90a\_4yr.fits'. On output, pdata contains the primary header and xdata is a structure whose first field is the extension header, and the other fields are vectors with respective tag names PIXEL, SIGNAL, N\_OBS, SERROR, ... (see help,/struc,xdata)

read\_fits\_s 169

#### read\_tqu

Location in HEALPix directory tree: <a href="mailto:src/idl/fits/read\_tqu.pro">src/idl/fits/read\_tqu.pro</a>

This IDL facility reads a temperature+polarization Healpix map (T,Q,U) from a binary table FITS file, with optionally the error (dT,dQ,dU) and correlation  $(dQU,\,dTU,\,dTQ)$  from separate extensions

#### **FORMAT**

IDL> READ\_TQU, File, TQU, [Extension=, Hdr=, Xhdr=, /HELP, Nside=, Ordering=, Coordsys=]

#### **QUALIFIERS**

File name of a FITS file from which the maps are to

be read

TQU : array of Healpix maps of size  $(N_{\text{pix}}, 3, \text{n\_ext})$ where  $N_{\text{pix}}$  is the total number of Healpix pixels on the sky, and  $\text{n ext} \leq 3$  is the number of

extensions read

Three maps are available in each extension of the

FITS file:

-the temperature+polarization Stokes parameters

maps (T,Q,U) in extension 0

-the error maps (dT,dQ,dU) in extension 1 (if ap-

plicable)

-the correlation maps (dQU, dTU, dTQ) in exten-

sion 2 (if applicable)

Extension = (optional),

extension unit to be read from FITS file: either its 0-based ID number (ie, 0 for first extension after primary array) or the case-insensitive value of its EXTNAME keyword. If absent, all available

extensions are read.

Hdr= (optional),

string variable containing on output the contents of the primary header. (If already present, FITS reserved keywords will be automatically updated). read\_tqu 171

> Xhdr =(optional),

> > string variable containing on output the contents of the extension header. If several extensions are read, then the extension headers are returned ap-

pended into one string array.

Nside= (optional),

> returns on output the **HEALPix** resolution parameter, as read from the FITS header. Set to -1

if not found

Ordering= (optional),

> returns on output the pixel ordering, as read from the FITS header. Either 'RING' or 'NESTED' or

' ' (if not found).

Coordsys= (optional),

> returns on output the astrophysical coordinate system used, as read from FITS header (value of

keywords COORDSYS or SKYCOORD)

#### **KEYWORDS**

/HELP

if set, an extensive help is displayed and no file is read

**DESCRIPTION**read\_tqu reads out Stokes parameters (T,Q,U) maps for the whole sky into a FITS file. It is also possible to read the error per pixel for each map and the correlation between fields, as subsequent extensions of the same FITS file (see qualifiers above). Therefore the file may have up to three extensions with three maps in each. Extensions can be written together or one by one (in their physical order) using the Extension option.

> For more information on the FITS file format supported in **HEALPix**, including the one implemented in read tqu see https://healpix.sourceforge.io/data/examples/ healpix\_fits\_specs.pdf.

#### RELATED ROUTINES

This section lists the routines related to **read** tqu.

idl version 6.4 or more is necessary to run read\_tqu

synfast This **HEALPix** f90 facility can be used to gen-

erate temperature+polarization maps that can be

read with read\_tqu

write\_tqu This HEALPix IDL facility can be used to write

out temperature+polarization that can be read by

read\_tqu.

read\_fits\_cut4, read\_fits\_partial, read\_fits\_map

read\_tqu, read\_fits\_s HEALPix IDL routines to read cut-sky maps

and partial maps, full-sky maps, polarized full-sky maps and arbitrary data sets from FITS files

read\_fits\_s This general purpose **HEALPix** IDL facility can

be used to read into an IDL structure maps con-

tained in binary table FITS files.

sxpar This IDL routine (included in **HEALPix** pack-

age) can be used to extract FITS keywords from the header(s) HDR or XHDR read with read\_tqu.

#### **EXAMPLE:**

read tqu, 'map polarization.fits', TQU, xhdr=xhdr

Reads into TQU the polarization maps contained in the FITS file 'map\_polarization.fits'. The variable xhdr will contain the extension(s) header.

remove dipole 173

#### remove\_dipole

Location in HEALPix directory tree: <a href="mailto:src/idl/misc/remove\_dipole.pro">src/idl/misc/remove\_dipole.pro</a>

This IDL facility provides a means to fit and remove the dipole and monopole from a **HEALPix** map.

**FORMAT** 

IDL> REMOVE\_DIPOLE, Map [, Weight, BAD\_DATA=, GAL\_CUT=, COORD\_IN=, COORD\_OUT=, Covariance\_Matrix=, Dipole=, Monopole=, /NOREMOVE, NSIDE=, /ONLYMONOPOLE, ORDER-ING=, PIXEL=, /SILENT, UNITS=, /HELP]

**QUALIFIERS** 

Map input and output, vector

map from which monopole and dipole are to be removed (also used for output). Assumed to be a full sky data set, unless PIXEL is set and has the

same size as map

Weight input, vector, optional

same size as map, describe weighting scheme to

apply to each pixel for the fit (**default:** uniform weight)

BAD DATA = scalar float, value given on input to bad pixels

(default: !healpix.bad\_value  $\equiv -1.6375 \ 10^{30}$ ).

GAL\_CUT= if set to a value larger than 0, the pixels with

galactic latitude |b| <gal\_cut degrees are not con-

sidered in the fit.

**NB:** the cut is *really* done in Galactic coordinates. If the input coordinates are different (see Coord\_In), the map is rotated into galactic before

applying the cut.

COORD\_IN = string, map coordinate system (either 'Q' or

'C': equatorial, 'G': galactic or 'E': ecliptic; up-

per/lower case accepted)

(**default:** 'G' (galactic))

COORD OUT =string, coordinate system (see above) in which to

output dipole vector in variable Dipole

(**default:** same as coord in)

Covariance Matrix = OUTPUT, scalar (or symmetric 4x4 matrix),

covariance of the statistical errors made on

monopole (and dipole) determination

OUTPUT, 3d vector, Dipole=

coordinates of best fit dipole (done simultaneously

with monopole), same units as input map

Monopole= OUTPUT, scalar float,

> value found for the best fit monopole (done simultaneously with dipole), same units as input map

NSIDE= scalar integer, healpix resolution parameter

ORDERING= string, ordering scheme (either 'RING'

'NESTED')

PIXEL= input, vector, gives the Healpix index of the pixels

> whose temperature is actually given in map (for cut sky maps). If present, must match Map in size. If absent, it is assumed that the map covers

the whole sky.

UNITS= string, units of the input map

#### **KEYWORDS**

/NOREMOVE if set, the best fit dipole and monopole are com-

puted but not removed (ie, Map is unchanged)

/ONLYMONOPOLE if set, fit (and remove) only the monopole

> /HELP if set, only display documentation header

/SILENT if set, the routine works silently

 $\overline{
m DESCRIPTION}$  remove\_dipolemakes a simultaneous least square fit of the monopole and dipole on all the valid pixels of Map (those with a value different from BAD\_DATA) with a galactic latitude larger in magnitude than GAL\_CUT (in degrees). The position of the pixels on the sky is reconstructed from NSIDE and ORDERING. If Map does not cover the full sky, the actual indices of the concerned pixels should be given in PIXEL

remove\_dipole 175

#### RELATED ROUTINES

This section lists the routines related to **remove\_dipole**.

#### reorder

Location in HEALPix directory tree: src/idl/toolkit/reorder.pro

This IDL facility allows the reordering of a full sky map from NESTED to RING scheme and vice-versa.

#### **QUALIFIERS**

Result	variable containing on output the reordered map
$Input\_map$	variable containing the input map

#### **KEYWORDS**

/HELP	if set, the documentation header is printed out and the code exits
In=	specifies the input ordering, can be either 'RING' or 'NESTED'
Out =	specifies the output ordering, can be either 'RING' or 'NESTED'
$/\mathrm{N2R}$	If set, does the NESTED to RING conversion, equivalent to In='NESTED' and Out='RING'
/R2N	If set, does the RING to NESTED conversion, equivalent to In='RING' and Out='NESTED'

**DESCRIPTION**reorder allows the reordering of a full sky map from NESTED to RING scheme and vice-versa

#### RELATED ROUTINES

This section lists the routines related to **reorder** .

idl version 6.4 or more is necessary to run reorder

reorder 177

 $ud\_grade$ 

downgrades or progrades a full-sky or cut-sky  $\mathbf{HEALPix}$  map.

#### **EXAMPLE:**

map\_nest = reorder(map\_ring, in='ring', out='nest')

The RING ordered map  $\mathtt{map\_ring}$  is converted to the NESTED map  $\mathtt{map\_nest}.$ 

#### rotate coord

Location in HEALPix directory tree: src/idl/misc/rotate\_coord.pro

This IDL facility provides a means to rotate a set of 3D position vectors (and their Stokes parameters Q and U) between to astrophysical coordinate systems or by an arbitrary rotation.

#### **FORMAT**

IDL> Outvec = rotate\_coord(Invec [, Delta\_Psi=, Euler\_Matrix=, Inco=, Outco=, Stokes\_Parameters=, /free\_norm, /help])

#### **QUALIFIERS**

Invec input, array of size (n,3): set of 3D position vec-

tors

Outvec output, array of size (n,3): rotated 3D vectors,

with the same norms as the input vectors

Delta\_Psi output, vector of size (n) containing the change in

azimuth  $\Delta \psi$  in Radians resulting from the rotation (measured with respect to the local meridian, from South to East), so that for field of spin s the output Q', U' is related to the input Q, U via  $Q' = Q\cos(s\Delta\psi) - U\sin(s\Delta\psi)$ ,  $U' = U\cos(s\Delta\psi) + Q\sin(s\Delta\psi)$ , with s=2 for polarization Stokes parameters (for which the spenarous)

cific  $\underline{Stokes}$ \_Parameters is also available).

Euler Matrix input, array of size (3,3). Euler Matrix describing

the rotation to apply to vectors. (default: iden-

tity: no rotation).

Can *not* be used together with a change in coor-

dinates.

Inco= input, character string (either 'Q' or 'C': equato-

rial, 'G': galactic or 'E': ecliptic) describing the

input coordinate system

Outco= input, character string (see above) describing the

output coordinate system.

Can not be used together with Euler Matrix

rotate coord 179

Stokes Parameters=

input and output, array of size (n, 2): values of the Q and U Stokes parameters on the sphere for each of the input position vector. Q and U are defined wrt the local meridian and parallel and are therefore transformed in a non-trivial way in case of rotation

#### **KEYWORDS**

/free\_norm if set (and Stokes Parameters and/or Delta Psi

are present) the input (and output) coordinate vectors are not assumed to be normalized to 1. Using this option is therefore safer, but 20 to 30% slower. (Note that 3D vectors produced by ang2vec, pix2vec nest and pix2vec ring are properly normalized). Ignored when Stokes Parameters and Delta Psi are both

absent.

/help if set, the documentation header is printed and

the routine exits

**DESCRIPTION**rotate\_coord is a generalisation of the Astro library routine skycony. It allows a rotation of 3D position vectors between two standard astronomic coordinates system but also an arbitrary active rotation described by its Euler Matrix. It can also compute how the linear polarization Stokes parameters (Q and U, expressed in local coordinates system) of each input location are affected by the solid body rotation, or equivalently it can output the corresponding change in azimuth.

#### RELATED ROUTINES

This section lists the routines related to **rotate\_coord**.

idl version 6.4 or more is necessary to run ro-

tate coord.

constructs the Euler Matrix for a set of three aneuler matrix new

gles and three axes of rotation

can be used to generate the input 3D vectors ang2vec, pix2vec \*

## same\_shape\_pixels\_nest & same\_shape\_pixels\_ring

Location in HEALPix directory tree: src/idl/toolkit/same\_shape\_pixels\_nest.pro, src/idl/toolkit/same\_shape\_pixels\_ring.pro

These IDL facilities provide the ordered list of all **HEALPix** pixels having the same shape as a given template, for a resolution parameter  $N_{\text{side}}$ .

#### **FORMAT**

IDL> same\_shape\_pixels\_nest, Nside, Template, List\_Pixels\_Nest [, Reflexion, NREPLICATIONS=]

IDL> same\_shape\_pixels\_ring, Nside, Template, List\_Pixels\_Ring [, Reflexion, NREPLICATIONS=]

#### **QUALIFIERS**

Nside (IN, scalar) the **HEALPix**  $N_{\text{side}}$  parameter.

Template (IN, scalar) identification number of the template

(this number is independent of the numbering

scheme considered).

List Pixels Nest (OUT, vector) ordered list of NESTED scheme

identification numbers for all pixels having the

same shape as the template provided

List Pixels Ring (OUT, vector) ordered list of RING scheme iden-

tification numbers for all pixels having the same

shape as the template provided

Reflexion (OUT, OPTIONAL, vector) in {0, 3} encodes the

transformation(s) to apply to each of the returned pixels to match exactly in shape and position the template provided. 0: rotation around the polar axis only, 1: rotation + East-West swap (ie, reflexion around meridian), 2: rotation + North-South swap (ie, reflexion around Equator), 3: rotation + East-West and North-South swaps

#### **KEYWORDS**

**NREPLICATIONS** 

(OUT, OPTIONAL, scalar) number of pixels having the same shape as the template. It is also the length of the vectors List\_Pixel\_Nest, List\_Pixel\_Ring and Reflexion. It is either 8, 16,  $4N_{\rm side}$  or  $8N_{\rm side}$ .

**DESCRIPTION** same\_shape\_pixels\_nest & same\_shape\_pixels\_ring provide the ordered list of all **HEALPix** pixels having the same shape as a given template, for a resolution parameter  $N_{\text{side}}$ . Depending on the template considered the number of such pixels is either 8, 16,  $4N_{\text{side}}$  or  $8N_{\text{side}}$ . The template pixels are all located in

the Northern Hemisphere, or on the Equator. They are chosen to have their center located at

$$z = \cos(\theta) \ge 2/3,$$
  $0 < \phi \le \pi/2,$   $2/3 > z \ge 0,$   $\phi = 0,$  or  $\phi = \frac{\pi}{4N_{\text{side}}}.$  (7)

They are numbered continuously from 0, starting at the North Pole, with the index increasing in  $\phi$ , and then increasing for decreasing z.

#### **EXAMPLE:**

same\_shape\_pixels\_ring, 256, 1234, list\_pixels, reflexion, nrep=np

Returns in list\_pixels the RING-scheme index of the all the pixels having the same shape as the template #1234 for  $N_{\rm side} = 256$ . Upon return reflexion will contain the reflexions to apply to each pixel returned to match the template, and np will contain the number of pixels having that same shape (16 in that case).

#### RELATED ROUTINES

This section lists the routines related to same\_shape\_pixels\_nest & same\_shape\_pixels\_ring.

nside2templates returns the number of template pixel shapes avail-

able for a given  $N_{\text{side}}$ .

 $template\_pixel\_ring$ 

template\_pixel\_nest return the template shape matching the pixel pro-

vided

## template\_pixel\_nest & template\_pixel\_ring

Location in HEALPix directory tree: src/idl/toolkit/template\_pixel\_nest.pro, src/idl/toolkit/template\_pixel\_ring.pro

These IDL facilities provide the index of the template pixel associated with a given **HEALPix** pixel, for a resolution parameter  $N_{\rm side}$ .

FORMAT	IDL> template_pixel_nest, Pixel_Nest, Template, Reflexion	Nside,
	IDL> template_pixel_ring, Pixel_Ring, Template, Reflexion	Nside,

## QUALIFIERS

Nside	(IN, scalar) the <b>HEALPix</b> $N_{\rm side}$ parameter.
Pixel_Nest	(IN, scalar or vector) NESTED scheme pixel identification number(s) over the range $\{0.12N_{\rm side}^2-1\}$ .
Pixel_Ring	(IN, scalar or vector) RING scheme pixel identification number(s) over the range $\{0.12N_{\rm side}^2-1\}$ .
Template	(OUT, scalar or vector) identification number(s) of the template matching in shape the pixel(s) provided (the numbering scheme of the pixel templates is the same for both routines).
Reflexion	(OUT, scalar or vector) in $\{0, 3\}$ encodes the transformation(s) to apply to each pixel provided to match exactly in shape and position its respec-

tive template. 0: rotation around the polar axis only, 1: rotation + East-West swap (ie, reflexion around meridian), 2: rotation + North-South swap (ie, reflexion around Equator), 3: rotation

+ East-West and North-South swaps

**DESCRIPTION** template\_pixel\_nest & template\_pixel\_ring provide the index of the template pixel associated with a given **HEALPix** pixel, for a resolution parameter  $N_{\text{side}}$ .

Any pixel can be *matched in shape* to a single of these templates by a combination of a rotation around the polar axis with reflexion(s) around a meridian and/or the equator.

The template pixels are all located in the Northern Hemisphere, or on the Equator. They are chosen to have their center located at

$$z = \cos(\theta) \ge 2/3,$$
  $0 < \phi \le \pi/2,$   $2/3 > z \ge 0,$   $\phi = 0,$  or  $\phi = \frac{\pi}{4N_{\text{side}}}.$  (8)

They are numbered continuously from 0, starting at the North Pole, with the index increasing in  $\phi$ , and then increasing for decreasing z.

#### **EXAMPLE:**

template\_pixel\_ring, 256, 500000, template, reflexion

Returns in template the index of the template pixel (16663) whose shape matches that of the pixel #500000 for  $N_{\rm side} = 256$ . Upon return reflexion will contain 2, meaning that the template must be reflected around a meridian and around the equator (and then rotated around the polar axis) in order to match the pixel.

#### RELATED ROUTINES

This section lists the routines related to **template\_pixel\_nest** & **template\_pixel\_ring**.

nside2templates returns the number of template pixel shapes available for a given  $N_{\text{side}}$ .

same\_shape\_pixels\_ring

same\_shape\_pixels\_nest return the ordered list of pixels having the same shape as a given pixel template

\_\_\_.\_

## ud\_grade

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/ud\_grade.pro">src/idl/toolkit/ud\_grade.pro</a>

This IDL facility provides a means to upgrade/degrade or reorder a full sky or cut-sky **HEALPix** map contained in a FITS file or loaded in memory.

#### **FORMAT**

IDL> UD\_GRADE, Map\_in, Map\_out [, BAD\_DATA=, HELP=, NSIDE\_OUT=, ORDER\_IN=, ORDER\_OUT=, /PES-SIMISTIC]

## **QUALIFIERS**

Map\_in input map: either a character string with the

name of a FITS file containing a full-sky or cutsky Healpix data set, or a memory vector (real,

integer, ...) containing a full sky data set.

Map\_out reordered map: if map\_in was a filename,

map\_out should be a filename, otherwise map\_out should point to a memory array

## **KEYWORDS**

BAD DATA = flag value of missing pixels.

(default: !healpix.bad\_value  $\equiv -1.6375 \ 10^{30}$ ).

/HELP if set, the documentation header is printed out

and the code exits

NSIDE OUT = output resolution parameter, can be larger or

smaller than the input one (scalar integer). (**default:** same as input: map unchanged or sim-

ply reordered)

ORDER\_IN = input map ordering (either 'RING' or 'NESTED')

(**default:** same as the input FITS keyword OR-

DERING if applicable).

ud grade 187

 $ORDER\_OUT =$ 

'RING' output map ordering (either 'NESTED') (**default:** same as ORDER IN).

/PESSIMISTIC

if set, during **degradation** each big pixel containing one bad or missing small pixel is also considered as bad,

if not set, each big pixel containing at least one good pixel is considered as good (optimistic) default = 0 (:not set)

DESCRIPTION ud\_grade can upgrade/degrade a HEALPix map using the hierarchical properties of **HEALPix**. It can also reorder a sky map (from NEST to RING and vice-versa). It operates on FITS files as well as on memory variables. Cut-sky operations are only accessible via FITS files. The degradation/upgradation is done assuming an intensive quantity (like temperature) that does not scale with surface area. In case of degradation a big pixel that contains at least one bad small pixel is considered as bad itself. When operating on FITS files, the header information from the input file that is not directly related the ordering/resolution is copied unchanged into the output file.

#### RELATED ROUTINES

This section lists the routines related to **ud\_grade**.

idl

reorder

version 6.4 or more is necessary to run ud grade. reorder a full sky Healpix map.

EXAMPLES: #1

ud\_grade, 'map\_512.fits', 'map\_256.fits', nside\_out = 256

ud\_grade reads the FITS file map\_512.fits (that allegedly contains a map with NSIDE=512), and write in the FITS file map 256.fits a map degraded to resolution 256, with the same ordering.

## EXAMPLES: #2

```
ud_grade, 'map_512.fits', 'map_Nest256.fits', nside_out = 256, $
  order out = 'NESTED'
```

ud\_grade reads the FITS file map\_512.fits (that allegedly contains a map with NSIDE=512), and writes in the FITS file map\_Nest256.fits a map degraded to resolution 256, with NESTED ordering.

## EXAMPLES: #3

```
read_fits_map, 'map_Nest256.fits', mymap
ud_grade, mymap, mymap2, nside_out = 1024, order_in='NESTED', order_out='RING'
```

mymap is IDL variable containing a **HEALPix** NESTED-ordered map with resolution nside=256. ud\_grade upgrades this map to a resolution of 1024, reorder it to RING and write it in the IDL vector mymap2.

unfold\_weights 189

## unfold weights

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/unfold\_weights.pro">src/idl/toolkit/unfold\_weights.pro</a>

This IDL function returns the full sky map of the weights to be applied to a **HEALPix** map in order to improve the quadrature. The input weights can be either ring-based or pixel-based, and read from file with user provided path, or from files with standardized name and location (ie, !healpix.path.data+'weight\_ring\_n????.fits' and !healpix.path.data+'weight\_pixel\_n?????.fits'

## **FORMAT**

IDL> weight\_map = unfold\_weights (File,
[Dim, /HELP, /SILENT])

IDL> weight\_map = unfold\_weights (Nside, [Dim, /PIXEL, /RING, SCHEME=, DIRECTORY=, /HELP, /SILENT])

## **QUALIFIERS**

Nside **HEALPix** resolution parameter (scalar integer),

should be a valid Nside (power of 2 in  $\{1, \dots, 2^{29}\}$ )

File Input weight file to be read. If not provided, the

function will try to guess the relevant file path based on Nside, the optional DIRECTORY, and the weighting scheme which **must** be set, with

either RING, PIXEL or SCHEME

Dim dimension of output, either 1 or 2. (**default:** 1)

weight\_map output: vector of size  $N_{\text{pix}} = 12N_{\text{side}}^2$  if Dim=1,

array of size  $(N_{\text{pix}}, 3)$  if Dim=2 (in the latter case,

all three columns are identical).

## **KEYWORDS**

DIRECTORY= directory in which to look for the weight file

(default: !healpix.path.data)

/HELP	if set on input, the documentation header is printed out and the function exits
/PIXEL	if set, the code will look for the pixel-based weight file corresponding the the Nside provided, in the default or provided Directory
/RING	if set, the code will look for the ring-based weight file corresponding the the Nside provided, in the default or provided Directory
SCHEME=	can be either 'PIXEL' or 'RING', setting the type of weight file the code will look for.
/SILENT	if set on input, the function works silently

**DESCRIPTION** unfold\_weights reads a list of weights, stored in a compact form in a FITS file, and centered on 0, either ring-based (uniform weights on each iso-latitude rings, defined on  $2N_{\text{side}}$  rings), or pixel-based (defined on  $N_w \simeq 0.75N_{\text{side}}^2 \simeq N_{\text{pix}}/16$ ) and turns them into a full sky **HEALPix** map of quadrature weights, with RING indexing and with values centered on 1.

#### RELATED ROUTINES

This section lists the routines related to **unfold weights**.

idl version 6.4 or more is necessary to run un-

 $fold\_weights$  .

nside2npweights returns the number of non-redundant pixel-based

weights used for disc storage

#### **EXAMPLE:**

```
mollview, /hist, unfold_weights(256, /ring), title='Ring-based weights @ Nside=256' mollview, /hist, unfold_weights(256, /pixel), title='Pixel-based weights @ Nside=256' will plot the full sky map of the ring-based and pixel-based quadrature weights for N_{\rm side}=256.
```

uniq2nest 191

## uniq2nest

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/uniq2nest.pro">src/idl/toolkit/uniq2nest.pro</a>

This IDL facility turns the Unique Identifier into the corresponding  $N_{\text{side}}$  and (NESTED) pixel index.

#### **FORMAT**

IDL> uniq2nest, Puniq, Nside, Pnest [,/HELP]

## **QUALIFIERS**

Puniq (IN, scalar or vector Integer) The **HEALPix** 

Unique pixel identifier(s). Must be  $\geq 4$ .

Nside (OUT, same size as Puniq) The **HEALPix**  $N_{\text{side}}$ 

parameter(s)

Pnest (OUT, same size as Puniq) (NESTED scheme)

pixel identification number(s) over the range

 $\{0.12N_{\text{side}}^2 - 1\}.$ 

#### **KEYWORDS**

/HELP If set, a documentation header is printed out, and

the routine exits

# **DESCRIPTION** uniq2nest turns the Unique ID number $u = p + 4N_{\text{side}}^2$ , into the parameter $N_{\text{side}}$ (a power of 2) and the pixel index p. See "The Unique Identifier scheme" section in "**HEALPix** Introduction Document" for more details.

#### **EXAMPLE:**

uniq2nest, [4,16, 64], nside, pnest print, nside, pnest

 $\begin{array}{cccc} 1 & & 2 & & 4 \\ 0 & & 0 & & 0 \end{array}$ 

since the pixels with Unique ID numbers 4, 16 and 64 are the first pixels (p=0) at  $N_{\rm side}=1,\,2$  and 4 respectively.

#### RELATED ROUTINES

This section lists the routines related to **uniq2nest**.

nest2uniq Transforms Nside and Nested pixel number into

Unique **HEALPix** pixel ID number

pix2xxx, ... to turn NESTED pixel index into sky coordinates

and back

vec2ang 193

## vec2ang

Location in HEALPix directory tree: <a href="mailto:src/idl/toolkit/vec2ang.pro">src/idl/toolkit/vec2ang.pro</a>

This IDL facility convert the 3D position vectors of points into their angles on the sphere.

# FORMAT IDL> VEC2ANG, Vector, Theta, Phi[, AS-TRO=]

## **QUALIFIERS**

Vector input, array,

three dimensional cartesian position vector (x, y, z) (not necessarily normalised). The north pole is (0, 0, 1). The coordinates are ordered as follows  $x(0), \ldots, x(n-1), y(0), \ldots, y(n-1), z(0), \ldots, z(n-1)$ 

Theta output, vector,

vector, colatitude in radians measured southward from north pole in  $[0,\pi]$  (mathematical coordinates).

If ASTRO is set, Theta is the latitude in degrees measured northward from the equator, in [-90, 90] (astronomical coordinates).

Phi output, vector,

longitude in radians measured eastward, in  $[0, 2\pi]$  (mathematical coordinates).

If ASTRO is set, Phi is the longitude in degree measured eastward, in [0,360] (astronomical coordinates)

dinates).

#### **KEYWORDS**

ASTRO=

if set Theta and Phi are the latitude and longitude in degrees (astronomical coordinates) instead of the colatitude and longitude in radians (mathematical coordinates). **DESCRIPTION** vec2ang performs the geometrical transform from the 3D position vectors (x, y, z) of points into their angles  $(\theta, \phi)$  on the sphere:  $x = \sin \theta \cos \phi$ ,  $y = \sin \theta \sin \phi$ ,  $z = \cos \theta$ 

#### RELATED ROUTINES

This section lists the routines related to vec2ang.

idl version 6.4 or more is necessary to run vec2ang.

pix2xxx, ... conversion between vector or angles and pixel in-

 $\operatorname{dex}$ 

ang2vec conversion from angles to position vectors

#### **EXAMPLE:**

vec2ang, [[0.,0.],[0.,0.],[1.,-10.]], lat, lon, /astro
print,lat
print,lon

will return 90.0000, -90.0000 and 0.00000, 0.00000, the latitudes and longitudes in Degrees or the North and South poles. Note that in this example the input 3D location of South pole was not normalized.

write fits cut4

## write fits cut4

Location in HEALPix directory tree: src/idl/fits/write\_fits\_cut4.pro

This IDL facility writes out a cut sky **HEALPix** map into a FITS file according to the **HEALPix** convention. The format used for the FITS file follows the one used for Boomerang98 and is adapted from COBE/DMR. This routine can be used to store polarized maps, where the information relative to the Stokes parameters I, Q and U are placed in extension 0, 1 and 2 respectively by successive invocation of the routine.

**FORMAT** 

IDL> WRITE\_FITS\_CUT4, File, Pixel, Signal[, N\_Obs, Serror, COORDSYS=, EXTENSION=, HDR=, /NESTED, NSIDE=, ORDERING=, /POLARISATION, /RING, UNITS=, XHDR=, HELP=]

**QUALIFIERS** 

File name of a FITS file in which the map is to be

written

Pixel (LONG or LONG64 vector),

index of observed (or valid) pixels

Signal (FLOAT or DOUBLE vector, same size as Pixel),

value of signal in each observed pixel

N\_Obs (LONG or INT or LONG64 vector, Optional,

same size as Pixel),

number of observation per pixel.

If absent, the field N\_OBS will take a value of 1 in the output file. If set to a scalar constant, N OBS

will take this value in the output file

Serror (FLOAT or DOUBLE vector, Optional, same size

as Pixel)

rms of signal in pixel, for white noise, this is  $\propto$ 

 $1/\sqrt{n}$  obs

If absent, the field SERROR will take a value of

0.0 in the output file. If set to a scalar constant, SERROR will take this value in the output file

#### **KEYWORDS**

COORDSYS= (optional).

> if set to either 'C', 'E' or 'G', specifies that the Healpix coordinate system is respectively Celestial=equatorial, Ecliptic or Galactic. (The relevant keyword is then added/updated in the extension header, but the map is NOT rotated)

EXTENSION= (optional),

(0 based) extension number in which to write data. (default: 0). If set to 0 (or not set) a new file is written from scratch. If set to a value larger than 1, the corresponding extension is added or updated, as long as all previous extensions already exist. All extensions of the same file should use the same ORDERING, NSIDE and COORDSYS.

HDR =(optional).

String array containing the information to be put

in the primary header.

/NESTED (optional) if set, specifies that the map is in the

NESTED ordering scheme see also: Ordering and Ring

NSIDE= (optional),

> scalar integer, **HEALPix** resolution parameter of the data set. The resolution parameter should be made available to the FITS file, either thru this

qualifier, or via the header (see XHDR).

ORDERING= (optional),

> if set to either 'ring' or 'nested' (case un-sensitive), specifies that the map is respectively in RING or

NESTED ordering scheme see also: Nested and Ring

The ordering information should be made available to the FITS file, either thru a combination of Ordering/Ring/Nested, or via the header (see

XHDR).

/POLARISATION specifies that file will contain the I, Q and U polarisation Stokes parameter in extensions 0, 1 and

HEALPix 3.83

write fits cut4

2 respectively, and sets the FITS header keywords

accordingly

/RING if set, specifies that the map is in the RING or-

dering scheme

see also: Ordering and Nested

UNITS= (optional),

string describing the physical units of the data set

(only applies to Signal and Serror)

XHDR= (optional),

String array containing the information to be put

in the extension header.

HELP= (optional),

if set, an extensive help is displayed, and no file is

written

**DESCRIPTION**For more information on the FITS file format supported in **HEALPix**, including the one implemented in write\_fits\_cut4, see <a href="https://healpix.sourceforge.io/data/examples/healpix fits specs.pdf">https://healpix.sourceforge.io/data/examples/healpix fits specs.pdf</a>.

#### RELATED ROUTINES

This section lists the routines related to write fits cut4.

idl version 6.4 or more is necessary to run

write\_fits\_cut4

read\_fits\_cut4 This HEALPix IDL facility can be used to read

in maps written by write fits cut4.

write\_fits\_cut4, write\_fits\_partial, write\_fits\_map

write\_tqu, write\_fits\_sb HEALPix IDL routines to write cut-sky and par-

tial maps, full-sky maps, polarized full-sky maps

and arbitrary data sets into FITS files

sxaddpar This IDL routine (included in **HEALPix** pack-

age) can be used to update or add FITS keywords

to the header in  ${\tt HDR}$  and  ${\tt XHDR}$ 

## EXAMPLES: #1

## EXAMPLES: #2

```
write_fits_cut4 , 'tqu_cut.fits', pixel, temperature, n_t, s_t, $
    /ring, nside=32, /pol
write_fits_cut4 , 'tqu_cut.fits', pixel, qstokes, n_q, s_q, $
    /ring, nside=32, /pol, ext=1
write_fits_cut4 , 'tqu_cut.fits', pixel, ustokes, n_u, s_u, $
    /ring, nside=32, /pol, ext=2
```

writes in 'tqu\_cut.fits' a FITS file with three extensions, each of them containing information on the observed pixel, the measured signal, the number of observations and noise per pixel, for the three Stokes parameters I, Q and U respectively. The **HEALPix** ring ordered scheme and the resolution  $N_{\rm side}=32$  is assumed.

write fits map

## write\_fits\_map

Location in HEALPix directory tree: src/idl/fits/write\_fits\_map.pro

This IDL facility writes out a **HEALPix** map into a FITS file according to the **HEALPix** convention

FORMAT IDL> WRITE\_FITS\_MAP, File, T\_sky,

[Header, Coordsys=, Error=, Help=, Nested=,

Ring=, Ordering=, Units=]

**QUALIFIERS** 

File name of a FITS file in which the map is to be

written

T\_sky variable containing the **HEALPix** map

Header (optional),

string variable containing on input the information to be added to the extension header. (If already present, FITS reserved keywords will be au-

tomatically updated).

Coordsys= (optional),

if set to either 'C', 'E' or 'G', specifies that the Healpix coordinate system is respectively Celestial=equatorial, Ecliptic or Galactic. (The relevant keyword is then added/updated in the ex-

tension header, but the map is NOT rotated)

Error (optional output),

will take value 1 if file can not be written

Ordering (optional),

if set to either 'ring' or 'nested' (case un-sensitive), specifies that the map is respectively in RING or

NESTED ordering scheme

see also: Nested and Ring

Units= (optional),

string describing the physical units of the data set

#### KEYWORDS

Help if set, an extensive help is displayed and no file is

written

Nested if set, specifies that the map is in the NESTED

ordering scheme

see also: Ordering and Ring

Ring if set, specifies that the map is in the RING or-

dering scheme

see also: Ordering and Nested

# DESCRIPTION write\_fits\_map writes out the full sky HEALPix map T\_sky

into the FITS file File. Extra information about the map can be given in Header according to the FITS header conventions. Coordinate systems can also be specified by Coordsys. Specifying the ordering scheme is compulsary and can be done either in Header or by setting Ordering or Nested or Ring to the correct value. If Ordering or Nested or Ring is set, its value overrides what is given in Header.

For more information on the FITS file format supported in **HEALPix**, including the one implemented in write\_fits\_map, see https://healpix.sourceforge.io/data/examples/healpix\_fits\_specs.pdf.

#### RELATED ROUTINES

This section lists the routines related to write fits map.

idl version 6.4 or more is necessary to run

write\_fits\_map

read\_fits\_map This HEALPix IDL facility can be used to read

in maps written by write\_fits\_map.

sxaddpar This IDL routine (included in **HEALPix** pack-

age) can be used to update or add FITS keywords

to Header

reorder This **HEALPix** IDL routine can be used to re-

order a map from NESTED scheme to RING

scheme and vice-versa.

write fits cut4, write fits partial, write fits map

write\_fits\_map 201

write\_tqu, write\_fits\_sb

**HEALPix** IDL routines to write cut-sky and partial maps, full-sky maps, polarized full-sky maps and arbitrary data sets into FITS files

write\_fits\_sb

routine to write multi-column binary FITS table

### **EXAMPLE:**

## write\_fits\_partial

Location in HEALPix directory tree: <a href="mailto:src/idl/fits/write\_fits\_partial.pro">src/idl/fits/write\_fits\_partial.pro</a>

This IDL facility writes out a unpolarized or polarized **HEALPix** map into a FITS file for a fraction of the sky.

### **FORMAT**

IDL> WRITE\_FITS\_PARTIAL, File, Pixel, IQU [, COLNAMES=, COORDSYS=, EXTENSION=, HDR=, HELP=, /NESTED, NSIDE=, ORDERING=, /RING, UNITS=, VERBOSE=, XHDR=]

## **QUALIFIERS**

File name of a FITS file in which the map is to be

written

Pixel (INT, LONG or LONG64 vector of length  $n_{\rm p}$ ),

index of observed (or valid) pixels. Will be the

first column of the FITS binary table

IQU (FLOAT or DOUBLE array of size  $(n_p, n_c)$ ),

I, Q and U Stokes parameters of each pixel (if I)

 $n_{\rm c}=3$ ), or I of each pixel (if  $n_{\rm c}=1$ )

## **KEYWORDS**

COLNAMES= STRING vector with FITS table column names

(beside PIXEL) (not case sensitive: [A-Z,0-9,\_\_])

(default: TEMPERATURE, for 1 column,

TEMPERATURE, Q POLARISATION,

U\_POLARISATION, for 3 columns, or CO1, CO2, CO3, CO4, ... otherwise)

If provided the number of COLNAMES must be

> the number of columns

COORDSYS= if set to either 'C', 'E' or 'G', specifies that the

Healpix coordinate system is respectively Celestial=equatorial, Ecliptic or Galactic. (The rele-

write fits partial

vant keyword is then added/updated in the ex-

tension header, but the map is NOT rotated) EXTENSION= (0 based) extension number in which to write data. (**default:** 0). If set to 0 (or not set) a new file is written from scratch. If set to a value larger than 1, the corresponding extension is added or updated, as long as all previous extensions already exist. All extensions of the same file should use the same ORDERING, NSIDE and COORDSYS. HDR =String array containing the information to be put in the primary header. HELP =if set, an extensive help is displayed, and no file is written /NESTED if set, specifies that the map is in the NESTED ordering scheme see also: Ordering and Ring NSIDE= scalar integer, **HEALPix** resolution parameter of the data set. The resolution parameter should be made available to the FITS file, either thru this qualifier, or via the header (see XHDR). ORDERING= if set to either 'ring' or 'nested' (case un-sensitive), specifies that the map is respectively in RING or NESTED ordering scheme see also: Nested and Ring The ordering information should be made available to the FITS file, either thru a combination of Ordering/Ring/Nested, or via the header (see XHDR). /RING if set, specifies that the map is in the RING ordering scheme see also: Ordering and Nested UNITS= STRING scalar or vector describing the physical units of the table columns (except for the PIXEL one) if scalar, same units for all columns; if vector, each column can have its own units; if needed, the last UNITS provided will be replicated for the remaining columns VERBOSE= if set, the routine is verbose while writing the FITS file XHDR =String array containing the information to be put in the extension header.

# **DESCRIPTION**For more information on the FITS file format supported in **HEALPix**, including the one implemented in write\_fits\_partial, see <a href="https://healpix.sourceforge.io/data/examples/healpix fits specs.pdf">https://healpix.sourceforge.io/data/examples/healpix fits specs.pdf</a>

#### RELATED ROUTINES

This section lists the routines related to write\_fits\_partial.

read\_fits\_partial

read\_fits\_partial

This HEALPix IDL facility can be used to read in maps written by write\_fits\_partial.

write\_fits\_cut4, write\_fits\_partial, write\_fits\_map

write\_tqu, write\_fits\_sb

HEALPix IDL routines to write cut-sky and partial maps, full-sky maps, polarized full-sky maps and arbitrary data sets into FITS files

sxaddpar

This IDL routine (included in HEALPix package) can be used to update or add FITS keywords to the header in HDR and XHDR

#### **EXAMPLE:**

```
nside = 512
pixel = lindgen(nside2npix(nside)/10)
write_fits_partial, 'map_part_T.fits', pixel, pixel*100., $
    nside=nside, units='K', /ring
write_fits_partial, 'map_part_TQU.fits', pixel, pixel#[100.,1.,1.], $
    nside=nside, units='K', /ring
write_fits_partial, 'map_part_xxxx.fits', pixel, pixel#[1.,-2.,3.,-4.], $
    nside=nside,colnames=['c1',B2','xx','POWER'],units=['K','m','s','W'],$
    /ring
```

will write in 'map\_part\_T.fits' a FITS binary table with the columns PIXEL and TEMPERATURE; in 'map\_part\_TQU.fits' a table with the columns PIXEL, TEMPERATURE, Q\_POLARISATION and U\_POLARISATION; and in 'map\_part\_xxxx.fits' a table with the columns PIXEL, C1, B2, XX and POWER.

write fits sb 205

## write fits sb

Location in HEALPix directory tree: <a href="mailto:src/idl/fits/write\_fits\_sb.pro">src/idl/fits/write\_fits\_sb.pro</a>

This IDL facility writes out a **HEALPix** map into a FITS file according to the **HEALPix** convention. It can also write an arbitray data set into a FITS binary table

#### **FORMAT**

IDL> WRITE\_FITS\_SB, File, Prim\_Stc[, Xten\_stc, Coordsys=, /Nested, /Ring, Ordering=, /Partial, Nside=, Extension=, /Nothealpix]

## **QUALIFIERS**

File name of a FITS file in which the map is to be

written

Prim\_stc IDL structure containing the following fields:

primary headerprimary image

Set it to 0 to get an empty primary unit

Xten\_stc (optional),

IDL structure containing the following fields:

extension headerdata column 1

- data column 2

• • •

NB: because of some astron routines limitation, avoid using the single letters 'T' or 'F' as tagnames in the structures Prim stc and Xten stc.

## **KEYWORDS**

Coordsys = (optional),

if set to either 'C', 'E' or 'G', specifies that the Healpix coordinate system is respectively Celestial=equatorial, Ecliptic or Galactic. (The relevant keyword is then added/updated in the ex-

tension header, but the map is NOT rotated)

Ordering= (optional),

if set to either 'ring' or 'nested' (case un-sensitive), specifies that the map is respectively in RING or

NESTED ordering scheme see also: Nested and Ring

Nside= (optional),

scalar integer, **HEALPix** resolution parameter of the data set. Must be used when the data set does

not cover the whole sky

Extension = (optional),

scalar integer, extension in which to write the data

(0 based). (**default:** 0)

/Nested (optional),

if set, specifies that the map is in the NESTED

ordering scheme

see also: Ordering and Ring

/Ring (optional),

if set, specifies that the map is in the RING or-

dering scheme

see also: Ordering and Nested

/Partial (optional),

if set, the data set does not cover the whole sky. In that case the information on the actual map resolution should be given by the qualifier Nside (see above), or included in the FITS header enclosed

in the Xten stc.

/Nothealpix (optional),

if set, the data set can be arbitrary, and the restriction on the number of pixels do not apply. The keywords Ordering, Nside, Nested, Ring

and Partial are ignored.

write fits sb 207

 ${f DESCRIPTION}$  write\_fits\_sb writes out the information contained in Prim\_stc and Exten stc in the primary unit and extension of the FITS file File respectively. Coordinate systems can also be specified by Coordsys. Specifying the ordering scheme is compulsary for **HEALPix** data sets and can be done either in **Header** or by setting Ordering or Nested or Ring to the correct value. If Ordering or Nested or Ring is set, its value overrides what is given in Header.

> The data is assumed to represent a full sky data set with the number of data points npix = 12\*Nside\*Nside unless

> Partial is set or the input FITS header contains OBJECT = 'PARTIAL'

AND

the Nside qualifier is given a valid value or the FITS header contains a NSIDE.

In the **HEALPix** scheme, invalid or missing pixels should be given the value !healpix.bad value=  $-1.6375010^{30}$ .

If Nothealpix is set, the restrictions on Nside are void.

#### RELATED ROUTINES

This section lists the routines related to write\_fits\_sb.

idl version 6.4 or more is necessary to

write fits sb

read fits map This **HEALPix** IDL facility can be used to read

in maps written by write fits sb.

read\_fits\_s This **HEALPix** IDL facility can be used to

read into an IDL structure maps written by

write fits sb.

This IDL routine (included in **HEALPix** packsxaddpar

age) can be used to update or add FITS keywords to the header in Prim\_stc and Exten\_stc

write\_fits\_cut4, write\_fits\_partial, write\_fits\_map

write\_tqu, write\_fits\_sb **HEALPix** IDL routines to write cut-sky and partial maps, full-sky maps, polarized full-sky maps

and arbitrary data sets into FITS files

write\_tqu

This **HEALPix** IDL facility based on write\_fits\_sb is designed to write temperature+polarization (T,Q,U) maps

#### **EXAMPLE:**

```
npix = nside2npix(128)
f= randomn(seed,npix)
n= lindgen(npix)+3
map_FN = create_struct('HDR',[' '],'FLUX',f,'NUMBER',n)
write_fits_sb, 'map_fluxnumber.fits', 0, map_FN, coord='G', /ring
```

The structure map\_FN is defined to contain a fictitious Flux+number map, where one field is a float and the other an integer. write\_fits\_sb writes out the contents of map\_FN into the extension of the FITS file 'map\_fluxnumber.fits'.

209 write\_tqu

#### write tqu

Location in HEALPix directory tree: src/idl/fits/write\_tqu.pro

This IDL facility writes a temperature+polarization Healpix map (T,Q,U) into a binary table FITS file, with optionally the error (dT,dQ,dU) and correlation (dQU, dTU, dTQ) in separate extensions

### **FORMAT**

IDL> WRITE\_TQU, File, TQU, [Coordsys=, Nested=, Ring=, Ordering=, Error=, Extension=, Help=, Hdr=, Xhdr=, Units=, Help=]

File name of a FITS file in which the maps are to be written

> array of Healpix maps of size  $(N_{pix}, 3, n_{ext})$  where  $N_{\rm pix}$  is the total number of Healpix pixels on the sky, and n ext  $\leq 3$ .

> > Three maps are written in each extension of the FITS file:

> > -the temperature+polarization Stokes parameters maps (T,Q,U) in extension 0

> > -the error maps (dT,dQ,dU) (if  $n_{ext} \geq 2$ ) in extension 1

> > -the correlation maps (dQU, dTU, dTQ) (if n ext = 3) in extension 2

> > it is also possible to write 3 maps directly in a given extension (provided the preceding extension, if any, is already filled in) by setting Extension to the extension number in which to write (0 based) and if  $n_{ext} + Extension \leq 3$

(optional),

if set to either 'C', 'E' or 'G', specifies that the Healpix coordinate system is respectively Celestial=equatorial, Ecliptic or Galactic. (The relevant keyword is then added/updated in the extension header, but the map is NOT rotated)

**QUALIFIERS** 

TQU

Coordsys=

Error (optional output),

will take value 1 if file can not be written

Extension (optional),

extension unit a which to put the data (0 based). The physical interpretation of the maps is determined by the extension in which they are written

see also: TQU

Hdr= (optional),

string variable containing on input the information to be added to the primary header. (If already present, FITS reserved keywords will be au-

tomatically updated).

Ordering= (optional),

if set to either 'ring' or 'nested' (case un-sensitive), specifies that the map is respectively in RING or

NESTED ordering scheme see also: Nested and Ring

Units= (optional),

string describing the physical units of the data set

Xhdr = (optional),

string variable containing on input the information to be added to the extension headerx. (If already present, FITS reserved keywords will be automatically updated). It will be repeated in each extension, except for TTYPE\* and EXTNAME which are generated by the routine and depend

on the extension

### **KEYWORDS**

Help if set, an extensive help is displayed and no file is

written

Nested if set, specifies that the map is in the NESTED

ordering scheme

see also: Ordering and Ring

Ring if set, specifies that the map is in the RING or-

dering scheme

see also: Ordering and Nested

211 write\_tqu

**DESCRIPTION** write\_tqu writes out Stokes parameters (T,Q,U) maps for the whole sky into a FITS file. It is also possible to write the error per pixel for each map and the correlation between fields, as subsequent extensions of the same FITS file (see qualifiers above). Therefore the file may have up to three extensions with three maps in each. Extensions can be written together or one by one (in their physical order) using the Extension option. For more information on the FITS file format supported in **HEALPix**, including the one implemented in write tqu , see https://healpix.sourceforge.io/data/ examples/healpix fits specs.pdf.

#### RELATED ROUTINES

This section lists the routines related to write\_tqu.

sxaddpar

idl version 6.4 or more is necessary to run write\_tqu

read tqu This **HEALPix** IDL facility can be used to read

in maps written by write\_tqu.

read fits s This **HEALPix** IDL facility can be used to read

into an IDL structure maps written by write tqu.

This IDL routine (included in **HEALPix** package) can be used to update or add FITS keywords

to the header(s) HDR or XHDR

write\_fits\_cut4, write\_fits\_partial, write\_fits\_map

write\_tqu, write\_fits\_sb **HEALPix** IDL routines to write cut-sky and partial maps, full-sky maps, polarized full-sky maps

and arbitrary data sets into FITS files

#### **EXAMPLE:**

npix = nside2npix(64)TQU = randomn(seed,npix,3) write tqu, 'map polarization.fits', TQU, coord='G', /ring

> The array TQU is defined to contain a fictitious polarisation map, with the 3 Stokes parameters T, Q and U. The map is assumed to be in Galactic coordinates, with a RING ordering of the pixels and  $N_{\text{side}} = 64$ . write\_tqu writes out the contents of TQU into the extension of the FITS file 'map polarization.fits'.