

Name:


## Homework 2 Due 1 Sep 2020


1. If the load shown causes the point C to displace 15 mm find the strain in the ropes BD and CE.







- $\bullet$  We use similar triangles to find the displacement at  $B,\,\delta_B=7.5\,\mathrm{mm}$
- We can now find the strain in both ropes  $\epsilon_{BD}=\frac{7.5}{400}=0.0188$  and  $\epsilon_{CE}=\frac{16}{600}=0.025$
- 2. A flexible cable, AB, connects to a rigid member CB as part of an airplane control mechanism. A force as shown causes a strain in the cable of  $400\mu\epsilon$ , find the angle  $\theta$  that the rigid member rotates due to this strain.






- We see that  $\theta = 0.03^{\circ}$
- 3. Determine the shear strain,  $\gamma_{xy}$  at corners C and D for the plate shown.






4. The polysulfone block is glued at its top and bottom to rigid plates. A tangential force applied to the top plate causes the sides to deform so that they are described by the equation  $y = 3x^{1/3}$ . Find the shear strain at corners A and B.



- Since we do not have straight lines, for this problem we need to consider the slope of the curved surface at the two points of interest, A and B.
- We can find these slopes using the derivative

- $y' = x^{-2/3}$
- The next thing we need to determine is the x-coordinate at B (when y=2), we find  $x=(2/3)^3=0.2963$
- Now we can substitute the two known values of x into the derivative,  $y'(0) = \infty$ , y'(0.2963) = 2.25.
- The slope at A is infinite, meaning a vertical line, which means  $\gamma_{xy,A} = 0$
- The slope at B is 2.25, and we can find the associated angle  $\gamma_{xy,B} = -0.418$




5. A tension test was performed on a steel specimen with a cross-sectional area of  $0.5 \, \text{in}^2$  and a gage length of 2 in. Plot the stress-strain diagram and find the modulus of elasticity, the yield stress, and the ultimate tensile strength.

Table 1: tensile test data Load (kip)   Elongation (in)	
0	0
1.50	0.0005
4.60	0.0015
8.00	0.0025
11.00	0.0035
11.80	0.0050
11.80	0.0080
12.00	0.0200
16.60	0.0400
20.00	0.1000
21.50	0.2800
19.50	0.4000
18.50	0.4600


• My solution for this problem was performed in Excel, stress and strain were calculated from the load and elongation, then a best-fit line in the linear region

was used to find E and  $\sigma_Y$ , the ultimate tensile strength is the highest stress found.

•  $E = 13 \,\mathrm{Msi}, \, \sigma_Y = 23.6 \,\mathrm{ksi}, \, \sigma_{ult} = 43 \,\mathrm{ksi}$ 




6. The rigid beam shown is supported by a pin at C and an A-36 steel wire AB. If the wire diameter is 0.25 in determine what the load w is when B is displaced 0.50 in downward.





- Since the beam is "rigid" the displacement at B will be entirely due to stretch of the wire.
- ullet We can look up E for A-36 steel in the back cover of the text,  $E=29.0\,\mathrm{Msi}$
- For  $\Delta L = 0.5$  in we know that  $\epsilon = 0.5/12/11.55 = 0.00361$

- Using Hook's Law we know that  $\sigma = E\epsilon = 29.0\,\mathrm{Msi.00361}$  which gives  $\sigma = 104.6\,\mathrm{ksi}$ , which for the given diameter means a force of 5.14 kip
- Using statics we can relate the force in the wire to the distributed load




- since  $F_B = 5.14 \,\mathrm{kip} = 10w$  we know that  $w = 514 \,\mathrm{lb/ft}$
- 7. The two bars shown are made from the material given in the stress-strain diagram shown. Find the cross-sectional area of each bar such that they fail under the same load P. Neglect any effects from buckling, consider only tensile and compressive failure.





• We start by doing some statics to determine whether a bar is in tension or compression. Notice that since all forces/reactions occur at pins at the end, these are both 2-force members, so all reaction forces need to act along the axis of the bars



- We see that for a positive P that AB is in compression while BC is in tension. This means that AB will fail at 25 ksi and BC will fail at 5 ksi
- We can now find the areas such that the load P will cause failure in both
- $\bullet$  We will find both areas in terms of the unknown load P
- $A_{AB} = 5P/3/25 = \frac{1}{15}P$  where P is in k-lb.
- $A_{BC} = 4P/3/5 = \frac{4}{15}P$  where P is in k-lb., we see that BC needs an area 4 times the size of AB.

- 8. Dr. Smith made a rubber band gun for his son. If the gun is 9 in long, compare the strain in 0.5 in, 1 in, and 2 in diameter rubber bands when stretched over the barrel of the gun.
  - If the rubber bands are perfectly flexible, and we treat them as folding into nearly a straight line, then their initial length is one-half their circumference
  - The final length will be the length of the rubber band gun, this gives strains of 10.5, 4.7, 1.9
  - Rubber deforms much more than most engineering materials (steel, aluminum, wood) and thus has much higher strain values than we are used to seeing