
NF PROCESSOR EFFECTS

Dual reverb / effects processor

User Manual - V1.0.0



VST3 - Audio Unit - AAX (Pro Tools)

NF Audio Tools by Nenno Fernando - (C) 2026 NF Audio Tools. All rights reserved.

Contents

1. Introduction . . . 3

2. Installation . . . 3

3. Quick start . . . 3

As an insert (guitar, vocal, instrument track) . . . 3

As a send effect (bus / aux) . . . 3

Try a setting without a source . . . 4

4. The front panel . . . 4

5. Routings and signal flow . . . 5

Wet, dry and wet-only effects . . . 5

6. Using the plug-in . . . 5

Loading programs . . . 5

Editing . . . 5

Tap tempo . . . 6

Storing programs . . . 6

Menu (three lines) . . . 6

7. Effects reference . . . 6

7.1 Reverbs . . . 6

7.2 Delays . . . 7

7.3 Dynamics . . . 8

7.4 Modulation and pitch . . . 8

8. Factory programs . . . 8

9. Tips and technical notes . . . 11

1. Introduction

NF Processor Effects is a dual reverb and effects processor. It has two independent processors, and each one can hold any of 32 effects: 16 reverbs, 6 delays, 8 modulation and pitch effects and 2 dynamics processors. The two processors can be combined in four different ways (routings), so you can use them as two separate effects, one after the other, or side by side.

- **32 effects**: reverbs (halls, plates, room, chamber, gated, reverse, ambience, studio, arena, spring), delays (studio, digital, tape, pong, modulated, reverse), de-esser, compressor, chorus, flanger, phaser, tremolo/pan, rotary, vibrato, pitch shift and detune.
- **4 routings**: Dual Mono, Cascade, Dual Stereo (parallel) and Mono Split.
- **99 factory programs** and **99 user programs**, with Store.
- Three controls per processor that change meaning with the effect, plus Mix, Bypass and Tap Tempo.
- Audition: five built-in sounds to try a setting without any audio source.
- Formats: VST3, Audio Unit and AAX, for macOS 10.15 or later (Apple Silicon and Intel).

> **About the sound.** The algorithms of NF Processor Effects were designed by NF Audio Tools to follow the description of each effect in this manual. The factory programs are starting points: use the knobs to adjust each one to your material.

2. Installation

Open the DMG and double-click **Install NF Processor Effects**. The installer lets you choose which formats to install on the **Customize** step. The installer is not signed by Apple: the first time, right-click the installer and choose **Open** (or use **System Settings > Privacy & Security > Open Anyway**).

Format	Location
VST3	/Library/Audio/Plug-Ins/VST3/NF Processor Effects.vst3
Audio Unit	/Library/Audio/Plug-Ins/Components/NF Processor Effects.component
AAX	/Library/Application Support/Avid/Audio/Plug-Ins/NF Processor Effects.aaxplugin

Restart your DAW and rescan the plug-ins if it does not appear. The plug-in is listed under **Reverb** (manufacturer **NF Audio Tools**). Logic Pro and Luna use the Audio Unit; Pro Tools uses AAX.

3. Quick start

Reverbs and delays are normally used as **send effects** (parallel); modulation effects and dynamics are normally used as **inserts** (in series). The plug-in works both ways.

As an insert (guitar, vocal, instrument track)

- Put the plug-in in an insert slot of the track.
- Choose a program with the **Program Select** knob, or with the preset tab at the top right (the default factory bank is **Serial**, made for this use).
- Adjust **Input** so the input LEDs light only occasionally in red, and **Mix 1** / **Mix 2** for the amount of effect.

As a send effect (bus / aux)

- Insert the plug-in on an aux or FX track and send audio to it from the other tracks.
- In the menu (three lines) choose **Factory programs: Parallel bank**. In this bank the Mix knobs are set to 100 % wet, which is what a send needs.

- Use the routing **3 (Dual Stereo)** or **4 (Mono Split)** for two effects side by side.

Try a setting without a source

Press **Audition**: a short built-in sound (drum stick, snare, kick, voice, guitar) plays through the processors.

4. The front panel




Figure 1 - The panel with numbered controls.


No.	Control	What it does
1	Input meters	Two columns of six LEDs (left and right input level). Red = the signal is at its limit.
2	Input	Input level of both channels. Twelve o'clock = 0 dB.
3	Mix 1	Wet/dry mix of Processor 1 (level control for wet-only effects).
4	Mix 2	Wet/dry mix of Processor 2.
5	Routing	Cycles through the four routings. The small diagram shows the current one.
6	Reverb matrix	Shows the active reverbs: green LED = Processor 1, red LED = Processor 2.
7	Delay / effects matrix	The same for delays, dynamics and modulation effects.
8	Preset tab	Name of the program. Arrows step through the factory programs; click the name for the list, Save, Load and Restore default.
9	Menu (three lines)	Utility settings, audition sound and About.
10	Store	Stores the current settings in one of the 99 user programs.
11	Audition	Plays a built-in sound through the processors. Shift-click chooses the sound.
12	Program display	Two-digit display: program number (dot lit = user program) and the value of the knob you are turning.
13	Program Select	Drag or use the wheel to choose a program (the number blinks); click it to load it.
14	Effect Select	The up/down buttons choose the effect of the processor.
15	Effect name	Shows the effect loaded in the processor (green = Processor 1, red = Processor 2).
16	Tempo	Tap twice to set the delay tempo. The LED blinks with the tempo.
17	Bypass	Bypasses the processor (lit red = bypassed).
18	Value readouts	The value of each knob, in the unit of the effect.
19	Effect knobs	Three knobs whose names and ranges change with the effect (see chapter 7).
20	Change LED	Lights when the knob differs from the stored program.

The NF logo (top left) returns the window to its default size after you have resized it with the handle at the bottom right corner.

5. Routings and signal flow

Press **Routing** to cycle through the four routings. The number of the routing is also shown on the program display when you press the button.


1 Dual Mono




2 Cascade



3 Dual Stereo (parallel)



4 Mono Split



Routing	Description
1 Dual Mono	The left input goes through Processor 1 to the left output; the right input goes through Processor 2 to the right output. Two completely independent mono effects.
2 Cascade	Left and right go through Processor 1 and then through Processor 2, in stereo. The usual choice for inserts.
3 Dual Stereo	Left and right go through both processors at the same time; the two outputs are mixed together. The usual choice for send / return use.
4 Mono Split	The left input goes through Processor 1, the right input through Processor 2, and the two outputs are mixed together to both channels.

Wet, dry and wet-only effects

For most effects the **Mix** knob blends the dry input with the effect (fully clockwise = 100 % wet). The **wet-only** effects (De-Esser, Compressor, Tremolo/Pan, Rotary and Vibrato) process the whole signal, so there is nothing to blend: for them Mix works as a **level control**, and fully clockwise is the normal setting.

Some effects take a mono signal (they sum left and right) and give a stereo result: Gated, Reverse, Spring, Digital, Tape, Pong and Reverse delays and Rotary. This is shown as "mono in / stereo out" in chapter 7.

> **Bypass.** By default a bypassed processor lets the dry signal through. In the menu you can change it to **mute**. Do not use mute with the Cascade routing: if a processor is muted, the whole chain is silent.

6. Using the plug-in

Loading programs

- Drag the **Program Select** knob (or use the mouse wheel over it). The number blinks while it is only selected; **click the knob** to load it. Programs 1-99 are the factory programs; the next 99 are the user programs (dot lit).
- With **Program AutoLoad** on (menu, the default) the program loads as soon as you select it.
- You can also use the preset tab: arrows for the next / previous factory program, or click the name to pick by application (Vocal, Live Sound, Instrumental, Drums & Percussion, Special) or a user program.

Editing

- Choose the effects with the **Effect Select** buttons. Each effect loads its own default knob positions.

- Turn the three knobs: the program display shows the value while you turn. A small **change LED** next to the knob lights when the value is different from the stored program, and the red LED near **Store** shows the program has been edited.
- Double-click a knob to return it to the default value of the effect. Use the mouse wheel or Shift for fine adjustments.

Tap tempo

When a delay is loaded, press **Tempo** twice in time with the music. The LED blinks at the new tempo, and the delay times follow it. **Time Range** sets the length relative to the tempo: 36 (twelve o'clock) is one quarter note, 12 is an eighth, 24 a dotted eighth, 54 a dotted quarter and 72 a half note. Each processor has its own tempo. In the menu, **Sync delays to the host tempo** makes both follow the tempo of the DAW.

Storing programs

- Press **Store**. The display alternates between "St" and the user program number.
- Drag the **Program Select** knob to choose the user location (1-99).
- Press **Store** again to save. Any other button cancels.

User programs are saved as files in *Documents/NF Audio Tools/NF Processor Effects/User Programs*, so they are shared by every instance of the plug-in. Complete presets (with every setting) can be saved and loaded from the preset tab (*Save Preset File* / *Load Preset File*).

Menu (three lines)

Option	What it does
Output: Stereo / Mono	Mono sums left and right to both outputs; effects such as Pong then lose their left-to-right movement.
Bypass: pass dry / mute	What a bypassed processor does (dry signal passes, or silence).
Factory programs: Serial / Parallel bank	Serial: Mix settings for in-line use (default). Parallel: Mix at 100 % wet, for send / return. Applies to the next program you load.
Sync delays to the host tempo	Both processors use the tempo of the DAW instead of the tap tempo.
Program AutoLoad	Loads each program as soon as it is selected.
Audition sound	All samples in turn, or a single one: drum stick, snare, kick, female vocal "Doo", acoustic guitar arpeggio.

7. Effects reference

The three knobs of each processor change name and range with the effect. The values below are the ones shown on the display and in the value readouts.

7.1 Reverbs

Pre Delay adds a short time between the sound and the start of the reverb (10-25 ms is natural; more can help a busy mix). Decay is the length of the tail and Liveliness the amount of high frequencies in it.

Small Hall (Stereo)
A concert hall in a small size: natural, open, and it stays behind the source without changing it.
Pre Delay: 0-100 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Large Hall (Stereo)
A large hall with a long, smooth tail and slowly growing density. The most natural choice for orchestral or big ambient sounds.
Pre Delay: 0-200 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Small Plate (Stereo)
A bright, dense metal plate with no early reflections. Thickens and brightens the sound; classic for pop music and percussion.
Pre Delay: 0-100 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Large Plate (Stereo)
A bigger plate with a longer decay and a smooth, colored tail.
Pre Delay: 0-200 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Room (Stereo)
A small room with strong early reflections. Good for dialog, voice-over and for adding body to electric guitar.
Pre Delay: 0-100 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Chamber (Stereo)
An even reverb with little colour as it decays. Works on almost anything, especially the spoken voice.
Pre Delay: 0-100 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Gated (Mono in / stereo out)
A dense burst of reverb that is cut off abruptly. The Decay knob sets how long the gate stays open. Great on snare and toms.
Pre Delay: 0-200 ms | **Decay (hold time)**: 0-60 | **Diffusion**: 0-99

Reverse (Mono in / stereo out)
The tail swells up and then stops, the opposite of a normal reverb. Use for special effects and transitions.
Pre Delay: 0-200 ms | **Decay (segment length)**: 0-60 | **Diffusion**: 0-99

Vocal Hall (Stereo)
A hall tuned for voices: lower diffusion, so soft transients stay clear.
Pre Delay: 0-200 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Vocal Plate (Stereo)
A plate tuned for voices: smooth and present without hiding the words.
Pre Delay: 0-200 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Drum Hall (Stereo)
A hall with higher diffusion, to smooth out fast drum and percussion transients.
Pre Delay: 0-100 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Drum Plate (Stereo)
A very dense, bright plate for drums.
Pre Delay: 0-100 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Ambience (Stereo)
The feeling of a small or medium space without an audible decay. Shape moves the energy from the early reflections to the tail.
Pre Delay: 0-100 ms | **Shape**: 0-99 | **Liveliness**: 0-99

Studio (Stereo)
A well-controlled recording room, like the live rooms of a studio. Useful on voice and on single instruments.
Pre Delay: 0-100 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Arena (Stereo)
A huge space with very long reflections and little high-frequency content. A special-effect reverb: keep it low in a busy mix.
Pre Delay: 0-200 ms | **Decay**: 0-99 | **Liveliness**: 0-99

Spring (Mono in / stereo out)
A spring tank. Boing sets how much the springs rattle when hit by loud transients: the classic rockabilly and guitar-amp sound.
Pre Delay: 0-200 ms | **Decay**: 0-99 | **Boing**: 0-99

7.2 Delays

Feedback sets the number of repeats. On the Studio, Digital and Pong delays, turning it fully clockwise engages **Hold**: the repeats loop forever and new sound is no longer fed in.

Studio Delay (Stereo)
Stereo delay up to 2.5 s with a ducker: while the input is loud, the repeats are lowered by 6 dB so they do not muddy the original. Feedback fully up holds the repeats.
Time Range: 0-72 | **Feedback**: 0-99 + Hold | **Duck Threshold**: -70 to 0 dB

Digital Delay (Mono in / stereo out)
The cleanest delay: mono delay up to 5 s, exact repeats, with the ducker.
Time Range: 0-72 | **Feedback**: 0-99 + Hold | **Duck Threshold**: -70 to 0 dB

Tape Delay (Mono in / stereo out)
Warm delay up to 5 s with wow and flutter, saturation and high-frequency loss in every repeat. Smear darkens and blurs the repeats.
Time Range: 0-72 | **Feedback**: 0-99 | **Smear**: 0-99

Pong Delay (Mono in / stereo out)
A ping-pong delay: the repeats move from left to right. Tap Ratio at 12 gives an even alternation; lower values bring the first tap earlier.
Time Range: 0-72 | **Feedback**: 0-99 + Hold | **Tap Ratio**: 0-23

Mod Delay (Stereo)
A stereo delay with a chorus-like movement in the repeats. Up to 2.5 s.
Time Range: 0-72 | **Feedback**: 0-99 | **Mod Depth**: 0-99

Reverse Delay (Mono in / stereo out)
Backwards repeats that build up from soft to loud, as if the delay came before the sound. Up to 5 s.
Time Range: 0-72 | **Feedback**: 0-99 | **Smear**: 0-99

7.3 Dynamics

De-Esser (Mono wet only)
Reduces harsh "s" sounds. Only the chosen frequency band is compressed, so the rest of the voice is untouched. Set Freq Range on the sibilance, then raise Ratio.
Ratio: 1:1 to Inf:1 | **Freq Range**: 1600 Hz to 10 kHz (41 steps) | **Bandwidth**: 1/4 to 1/24 octave (0-5)

Compressor (Mono wet only)
A smooth compressor with a soft knee. Gain restores the level lost to compression. Because it is a wet-only effect, the Mix knob works as a level control.
Threshold: -70 to 0 dB | **Ratio**: 1:1 to Inf:1 | **Gain**: 0 to +12 dB

7.4 Modulation and pitch

Chorus (Stereo)
Thickens the sound by mixing delayed copies that move slowly in pitch. Voices adds up to 8 extra voices.
Speed: 0-99 | **Depth**: 0-99 | **Voices**: 0-99

Flanger (Stereo)
A sweeping comb filter, from a light swish to a jet-plane sound. Regen adds a metallic resonance.
Speed: 0-99 | **Depth**: 0-99 | **Regen**: 0-99

Phaser (Stereo)
Notches that move up and down the spectrum. Great on keyboards, pads and guitar.
Speed: 0-99 | **Depth**: 0-99 | **Regen**: 0-99

Tremolo/Pan (Stereo wet only)
Rhythmic level changes. With Phase at 0 both channels move together (tremolo); at 99 they alternate (auto-pan).
Speed: 0-99 | **Depth**: 0-99 | **Phase**: 0-99

Rotary (Mono in / stereo out, wet only)
A rotating-speaker cabinet with a horn and a drum rotor that speed up and slow down with inertia. Doppler sets the pitch effect, Spread the stereo image.
Speed: 0-99 | **Doppler**: 0-99 | **Spread**: 0-99

Vibrato (Stereo wet only)
A smooth pitch variation. Phase offsets left and right for a panning motion.
Speed: 0-99 | **Depth**: 0-99 | **Phase**: 0-99

Pitch Shift (Stereo)
Shifts the pitch by up to two octaves, up or down. Cutoff Freq rolls off the highs of the shifted signal.
Shift: 0-24 semitones | **Up / Down**: Up or Down | **Cutoff Freq**: 0-55

Detune (Stereo)
A slightly detuned copy for a "double-tracked" sound. Spread moves the two detuned voices apart in the stereo field.
Left Shift: -24 to +24 cents | **Right Shift**: -24 to +24 cents | **Spread**: 0-99

8. Factory programs

The 99 factory programs combine the two processors in the listed routing. They are starting points: the knob values are general settings for each effect and the Mix values depend on the factory bank (Serial or Parallel). An asterisk (*) means the effect is loaded in bypass.

#	Title	Application	Processor 1	Processor 2	Rtg
1	Big Pop Vocal	Vocal	Studio Delay	Vocal Hall	2

#	Title	Application	Processor 1	Processor 2	Rtg
2	Pop Vocals	Vocal	Tape Delay	Studio Reverb	3
3	Retroverb	Vocal	Tape Delay	Vocal Plate	2
4	Chorus + Plate	Vocal	Chorus	Plate	4
5	Vocal Hall+Plate	Vocal	Vocal Hall	Vocal Plate	4
6	Extra Roomy	Live Sound	Room	Small Hall	2
7	Tuned Room	Live Sound	Detune	Room	2
8	Echoverb	Live Sound	Digital Delay	Small Hall	2
9	Quickie	Live Sound	Small Hall	Digital Delay	2
10	Acoustic Chamber	Instrumental	Tape Delay*	Chamber	2
11	Ambient Chamber	Instrumental	Ambience	Chamber	4
12	Acoustic Bliss	Instrumental	Detune	Large Hall	4
13	Guitar World	Instrumental	Chorus	Modulated Delay	2
14	Springtime	Instrumental	Tremolo/Pan*	Spring	2
15	Giant Snare	Drums & Percussion	Studio Delay	Drum Hall	2
16	Smooth Drm Plate	Drums & Percussion	Compressor	Drum Plate	2
17	Rich Drum Hall	Drums & Percussion	Compressor	Drum Hall	2
18	Big Time	Special	Digital Delay	Large Hall	4
19	Voice Of Evil	Special	Pitch Shifter	Reverse Reverb	2
20	Wayback Machine	Special	Reverse Delay	Reverse Reverb	2
21	Big Vocal Verb	Vocal	Large Plate	Vocal Hall	2
22	Two Rooms	Vocal	Small Hall	Vocal Hall	1
23	Big Easy	Vocal	Chorus	Vocal Hall	2
24	Nashville	Vocal	Vocal Plate	Room	4
25	La-La Land	Vocal	Compressor	Vocal Hall	2
26	Smooth Vocals	Vocal	Compressor	Small Hall	2
27	Compressed Vox	Vocal	Compressor	Vocal Hall	2
28	No "S" Vocals	Vocal	De-Esser	Vocal Plate	2
29	De-Esser+Compr	Vocal	De-Esser	Compressor	2
30	Compressor	Vocal	Compressor	Compressor*	4
31	De-Esser	Vocal	De-Esser	De-Esser*	4
32	Studio Delay	Vocal	Studio Delay	Vocal Hall*	2
33	60's Delay	Vocal	Tape Delay	Spring	2
34	Slapback	Vocal	Detune*	Tape Delay	2
35	Delay + Verb	Vocal	Studio Delay	Vocal Hall	1
36	Vocal Chorus	Vocal	Chorus	Vocal Hall*	2
37	Choral Hall	Vocal	Chorus	Large Hall	2
38	Tape Chorus	Vocal	Tape Delay	Chorus	2
39	Core Us	Vocal	Chorus	Chorus	1
40	Double Tracks	Vocal	Detune	Chorus	2
41	Shifted Room	Vocal	Pitch Shift	Room Reverb	3
42	Like That!	Vocal	Pitch Shifter	Vocal Hall	4

#	Title	Application	Processor 1	Processor 2	Rtg
43	Plate + Hall	Live Sound	Vocal Plate	Small Hall	1
44	Vocal + Inst 1	Live Sound	Vocal Hall	Studio	4
45	Vocal + Inst 2	Live Sound	Vocal Plate	Detune	4
46	Vocal + Inst 3	Live Sound	Vocal Hall	Small Hall	4
47	Get Small	Live Sound	Small Hall	Small Plate	4
48	Alive N' Kicking	Live Sound	Small Hall	Studio	4
49	Muy Grande	Live Sound	Drum Hall	Digital Delay	4
50	Bigger Band	Live Sound	Chorus	Studio Delay	2
51	Taps	Live Sound	Chorus	Tape Delay	2
52	Tap Chamber	Live Sound	Pong Delay	Chamber	2
53	Spaced Out	Live Sound	Large Plate	Modulated Delay	2
54	Dual Halls	Instrumental	Large Hall	Small Hall	1
55	Tried And True	Instrumental	Studio	Small Hall	4
56	More & More	Instrumental	Large Plate	Arena	4
57	Spring Studio	Instrumental	Spring	Studio	4
58	Hit Me	Instrumental	Tape Delay	Studio	2
59	Precision Delay	Instrumental	Digital Delay	Small Hall	2
60	Modulated Delay	Instrumental	Chorus	Modulated Delay	2
61	Rock Lead	Instrumental	Tape Delay	Small Plate	4
62	Pong Verb	Instrumental	Small Plate	Pong Delay	2
63	Mod-U-Verb	Instrumental	Vocal Plate	Chorus	2
64	Roto-Verb	Instrumental	Drum Hall	Rotary Speaker	2
65	Rotary	Instrumental	Rotary	Small Room	4
66	Ham 'n Eggs	Instrumental	Tape Delay	Rotary	2
67	Vibrolux	Instrumental	Rotary Speaker	Spring	1
68	Side By Side	Instrumental	Tremolo	Panner	4
69	Wobblers	Instrumental	Chorus	Small Plate	4
70	Rhodes Panner	Instrumental	Phaser	Tremolo/Panner	4
71	Brewed Awakening	Instrumental	Flanger	Tape Delay	1
72	Jet Flange	Instrumental	Flanger	Arena	2
73	Phase Gate	Instrumental	Gated	Phaser	4
74	Phased Plate	Instrumental	Phaser	Small Plate	2
75	Phame	Instrumental	Phaser	Large Plate	1
76	Phaser Taser	Instrumental	Phaser	Digital Delay	2
77	Dualing Guitars	Instrumental	Pitch Shifter	Pitch Shifter	4
78	The Low Down	Instrumental	Pitch Shift	Modulated Delay	1
79	And Then Some	Instrumental	Reverse Delay	Tremolo	2
80	Squished Kick	Drums & Percussion	Compressor	Drum Hall	2
81	Gated Snare	Drums & Percussion	Gated Reverb	Gated Reverb	3
82	Snare Delay	Drums & Percussion	Studio Delay	Drum Plate	2
83	Drum Delay	Drums & Percussion	Tape Delay	Drum Hall	2

#	Title	Application	Processor 1	Processor 2	Rtg
84	Drum Echo	Drums & Percussion	Tape Delay	Small Hall	2
85	Tempo Gate	Drums & Percussion	Studio Delay	Gated	2
86	Flange Drums	Drums & Percussion	Studio Delay*	Flanger	2
87	Tom-Tom	Drums & Percussion	Studio Delay	Drum Hall	4
88	Snare + Toms	Drums & Percussion	Drum Hall	Room	4
89	Drum Plate/Hall	Drums & Percussion	Drum Plate	Drum Hall	4
90	Vibrato	Special	Vibrato	Vibrato	4
91	Vibra-Slap	Special	Vibrato	Digital Delay	1
92	Spin Cycle	Special	Rotary	Tremolo/Panner	2
93	Role Reversal	Special	TremoloPan	Reverse	2
94	Get Some	Special	Flanger	Reverse Delay	3
95	Rewind	Special	Chamber	Reverse	2
96	Back At Ya	Special	Reverse Delay	Reverse	4
97	Delay Wars	Special	Pong Delay	Modulated Delay	4
98	Pitch Out	Special	Pitch Shifter	Pong Delay	2
99	Huh?	Special	Pitch Shifter	Vocal Plate	2

9. Tips and technical notes

- Keep the red input LEDs off most of the time, and use **Input** to adjust the level that feeds the effects.
- For reverbs on a busy mix try a short **Pre Delay** and a lower **Liveliness**.
- Use the **Studio** or **Digital** delay ducker so the repeats stay out of the way of the singer.
- All parameters can be automated in your DAW (effect choice, knobs, mix, bypass, routing, tempo).

Specification	Value
Formats	VST3, Audio Unit, AAX
Channels	Mono or stereo (in = out)
Sample rates	Any (the effects adapt to the sample rate)
Latency	Zero. The Reverse reverb and Reverse delay are by nature delayed by their segment length.
Delay times	Up to 2.5 s (Studio, Mod) and 5 s (Digital, Tape, Pong, Reverse)
Programs	99 factory + 99 user
Requirements	macOS 10.15 or later, Apple Silicon or Intel

NF Processor Effects (C) 2026 NF Audio Tools by Nenno Fernando. All rights reserved. All other product names mentioned belong to their respective owners.