CMPE 362 Digital Image Processing

Frequency Domain Techniques – Part III

Sampling


Why does a lower resolution image still make sense to us? What do we lose?



Image: http://www.flickr.com/photos/igorms/136916757/


Sampled representations

- How to store and compute with continuous functions?
- Common scheme for representation: samples
- write down the function's values at many points




Reconstruction

- Making samples back into a continuous function
- amounts to "guessing" what the function did in between




Impulse function $\delta(x)$

$$\delta(x) = 1$$
 if $x = 0$
 $\delta(x) = 0$ otherwise




Impulse function $\delta(x-a)$

$$\delta(x - a) = 1$$
 if $x = a$
 $\delta(x - a) = 0$ otherwise




Impulse train


Shah function (Impulse train):



Sampling Theorem




Shah function (Impulse train):



Sampled function:

$$f_s(x) = f(x)s(x) = f(x)\sum_{n=-\infty}^{\infty} \delta(x - nx_0)$$

FT of an "impulse train" is an impulse train!




Sampling Theorem


Sampled function:

$$f_s(x) = f(x)s(x) = f(x)\sum_{n=-\infty}^{\infty} \delta(x - nx_0)$$
 Sampling frequency

Sampling
$$\frac{1}{x_0}$$
 frequency

$$F_S(u) = F(u) * S(u) = F(u) * \frac{1}{x_0} \sum_{n=-\infty}^{\infty} \delta\left(u - \frac{n}{x_0}\right)$$






Sampling Theorem

Sampled function:

$$f_s(x) = f(x)s(x) = f(x)\sum_{n=-\infty}^{\infty} \delta(x - nx_0)$$
 Sampling frequency

Sampling
$$\frac{1}{x_0}$$
 frequency

$$F_S(u) = F(u) * S(u) = F(u) * \frac{1}{x_0} \sum_{n=-\infty}^{\infty} \delta\left(u - \frac{n}{x_0}\right)$$



Nyquist Frequency

If
$$u_{\text{max}} \ge \frac{1}{2x_0}$$

Aliasing

 u_{max}

When can we recover F(u) from $F_s(u)$?

Only if
$$u_{\text{max}} < \frac{1}{2x_0}$$
 (Nyquist Frequency)

We can use

$$C(u) = \begin{cases} x_0 & |u| < \frac{1}{2}x_0 \\ 0 & \text{otherwise} \end{cases}$$

Then
$$F(u) = F_S(u)C(u)$$
 and $f(x) = IFT[F(u)]$


Sampling frequency must be greater than $2u_{\text{max}}$

Nyquist-Shannon Sampling Theorem

- When sampling a signal at discrete intervals, the sampling frequency must be $> 2 \times f_{\text{max}}$
- $f_{max} = max$ frequency of the input signal
- This allows to reconstruct the original perfectly from the sampled version

2D example


fmax = 1/2





Good sampling


1/x0 = 1/2 1/x0 > 2*fmax1/2 > 2*(1/2)

Bad sampling









1/x0 = 1/1.5 1/x0 > 2*fmax1/1.5 > 2*(1/2)

Bad sampling

Slide credit: N. Kumar

Aliasing problem

- Sub-sampling may be dangerous....
- Characteristic errors may appear:
 - "Wagon wheels rolling the wrong way in movies"
 - "Checkerboards disintegrate in ray tracing"
 - "Striped shirts look funny on color television"

Aliasing examples





Check out Moire patterns on the web.


Aliasing in video

fmax =
$$1/90$$

 $1/x0 > 2*(1/90)$
 $x0 < 45$


Imagine a spoked wheel moving to the right (rotating clockwise). Mark wheel with dot so we can see what's happening.

If camera shutter is only open for a fraction of a frame time (frame time = 1/30 sec. for video, 1/24 sec. for film):




Without dot, wheel appears to be rotating slowly backwards! (counterclockwise)

Aliasing in graphics



Sampling and aliasing




Anti-aliasing

Solutions:


Sample more often

- Get rid of all frequencies that are greater than half the new sampling frequency
 - Will lose information
 - But it's better than aliasing
 - Apply a smoothing filter


Sampling low frequency signal




Multiply:




Convolve:



Sampling low frequency signal




Sampling low frequency signal



If there is no overlap, the original signal can be recovered from its samples by low-pass filtering.

Sampling high frequency signal




 $f(x)comb_{M}(x)$

 $F(u)*comb_{\frac{1}{M}}(u)$ $\downarrow \qquad \qquad \downarrow \qquad \downarrow \qquad \qquad \downarrow \qquad$

Overlap: The high frequency energy is folded over into low frequency. It is "aliasing" as lower frequency energy. And you cannot fix it once it has happened.

Slide credit: B. K. Gunturk

Sampling high frequency signal




Slide credit: B. K. Gunturk

Sampling high frequency signal


• Without anti-aliasing filter:

$$f(x)comb_{M}(x)$$



• With anti-aliasing filter:


$$[f(x)*h(x)]comb_{M}(x)$$




Algorithm for downsampling by factor of 2


- I. Start with image
- 2. Apply low-pass filter
- 3. Sample every other pixel

Anti-aliasing



Subsampling without pre-filtering









1/2

1/4 (2x zoom)

1/8 (4x zoom)

Subsampling with Gaussian pre-filtering







Gaussian 1/2

G 1/4

G 1/8

Week 08 – Hands on activity

Prepare and submit a Jupyter Notebook file containing the code and the results for the following Task

Task

Read an image of your choice and convert it into gray-scale image and display it.

Compute Fast Fourier Transform of the gray scale image and visualize its magnitude by using log transform (logarithm of 1 + its absolute value).

Shift the FFT of the image to the center and visualize its magnitude by using log transform (logarithm of 1 + its absolute value).

→ At this point, you should see the reason for shifting FFT to the center before visualization (it becomes easier to see the low frequency details).

Inverse the shifting using ifftshift.

Convert back the image from the Fourier domain to the spatial domain using Inverse Fast Fourier Transform.

Check and see that the image remains the same (after conversion from the spatial domain to the frequency domain and back from the frequency domain to the spatial domain).

→ Actually, the maximum of the absolute differences should be around 10^-13.