



How to create samba share and access it through windows machine:

Steps to follow in linux terminal using root access:

Step 1: Create samba users

```
smbpasswd -a username
```

```
smbpasswd -a test
```

Step 2: create samba group:

```
groupadd groupname
```

```
groupadd worldweb
```

Step 3: add users to samba group

```
usermod -aG username groupname
```

```
usermod -aG test worldweb
```

Step 4: assign permission and group ownership to samba share:

change group owner of samba share directory to our samba group

```
chown :groupname /path/of/dir
```

```
chown :groupname /home/worldweb
```

Step 5: assign following permission to directory and sub directory

```
chmod 755 /home/worldweb
```

now to set permission for subdirectory follow the following rules as per requirement

Suppose there are three valid users (test1 test2 test3) who access samba share worldweb and there are three different directories (client1, client2, client3) are available

Case 1:

suppose you want to share subdirectory client 1 to only test1 user and other user test2 and test3 can only access it and read it but cannot modify it then apply

following permission to test directory

```
chown test1:test1 client1
```

```
chmod 755 client1
```

Case 2:

Suppose you want to share subdirectory client1 to all three users (test1 test2 test3) and all users has full access over it then apply following permission.

```
chown :worldweb client1
```

```
chmod 775 client1
```

Case 3 :

Suppose you want to share subdirectory client1 to only test1 and test2 user then apply following permission

```
Chown test1:test2 client1
```

```
Chmod 775 client1
```

Steps to follow on webmin samba share:

Step 1:

Login into virtualmin click on webmin→click on servers→you find Samba Windows file sharing

Click on that option

Step 2:

Now click on create new share option available and provide following information

- 1 Name of share → give any name
- 2 Directory to share → directory path
- 3 Available Browse able → yes
- 4 share comment → give any comment

Step 3:

Now go into samba global configuration and click on edit conf file and put following entries in it

[global]

```
log file = /var/log/samba/log.%m
load printers = yes
socket options = TCP_NODELAY
force directory mode = 775
deadtime = 1
map to guest = Bad Password
winbind trusted domains only = yes
encrypt passwords = yes
winbind use default domain = yes
passdb backend = tdbsam
wins support = true
netbios name = server.worldweb.com
cups options = raw
writeable = yes
server string = Samba Server Version %v
workgroup = WORKGROUP -> change to your windows workgroup name
force create mode = 775
os level = 20
```

```
security = user
create mode = 775
max log size = 50
winbind cache time = 60
directory mode = 775
  unix charset = UTF-8
  dos charset = CP932
  netbios aliases = srv.worldweb.projects srv.worldweb.wwusers
srv.worldweb.wwweb
```

Step 4:

Now click on the edit share option you will find Security and Access control option below the share information

Now click on the Security and Access control option

Find hosts allow -> add entry of your IP from which you want to access samba share

Find valid groups -> add entry of groups which contain multiple users and you want to allow them access. **(already created group in previous steps in linux terminal for samba)**

Step 5:

Click on the option restart samba server.

Steps to follow on windows machine:

Step 1:

If you want to mount multiple samba share to windows machine then please enter host entry in /etc/hosts file.

```
192.168.1.101 srv.worldweb.projects
192.168.1.101 srv.worldweb.wwusers
192.168.1.101 srv.worldweb.wwweb
```

Step 2:

Mount samba share using two ways

1 Start →run →type //192.168.1.101 you can see various samba share click on any of the share and its asks for username password then enter username and password of samba user

2 You can also mount samba share using following

Goto→computer→Map network drive→

Select drive letter like z or x or y etc

On folder type following //192.168.1.101/worldweb its asks for username and password and enter it

Here **srv.worldweb.projects** etc are samba server name and **worldweb** is samba share name

You can also mount samba share using following names also

```
//srv.worldweb.projects/projects  
//srv.worldweb.wwusers/wwusers  
//srv.worldweb.wwweb/worldweb
```

Step 3:

Unmount samba share using following ways

go into→computer

you found mount drives like Z or Y or X etc where share already mounted from that place after right clicking on that drive Z or Y or X etc you found disconnect option

you can also use net use command on command prompt to disconnect and unmount all shares or specific share.

```
net use \\192.168.1.101\worldweb /delete  
net use /delete
```