
Cisco Data Center Class Trainer: Behrouz Soleimani www.nethightech.com nethightech@gmail.com

Scenario Name: VXLAN BGP EVPN-Anycast-Multi Tenant



Leafl Configuration:

Leaf1(config)# feature bgp Leaf1(config)# feature pim Leaf1(config)# feature interface-vlan Leaf1(config)# feature vn-segment-vlan-based Leaf1(config)# feature nv overlay

Leaf1(config)# fabric forwarding anycast-gateway-mac 0001.0001.0001

Leaf1(config)# ip pim rp-address 10.10.10.10 group-list 224.0.0.0/4

Leaf1(config)# vlan 100,11,12,200,21,22

Leaf1(config-vlan)# vlan 100 Leaf1(config-vlan)# name L3-VNI-VLAN-100 Leaf1(config-vlan)# vn-segment 1000100

Leaf1(config-vlan)# vlan 11 Leaf1(config-vlan)# vn-segment 100011

Leaf1(config-vlan)# vlan 12 Leaf1(config-vlan)# vn-segment 100012

Leaf1(config-vlan)# vlan 200 Leaf1(config-vlan)# name L3-VNI-VLAN-200 Leaf1(config-vlan)# vn-segment 1000200

Leaf1(config-vlan)# vlan 21 Leaf1(config-vlan)# vn-segment 100021

Leaf1(config-vlan)# vlan 22 Leaf1(config-vlan)# vn-segment 100022

Leaf1(config-vlan)# vrf context WomanTenant
Leaf1(config-vrf)# vni 1000100
Leaf1(config-vrf)# rd auto
Leaf1(config-vrf)# address-family ipv4 unicast
Leaf1(config-vrf-af-ipv4)# route-target both auto
Leaf1(config-vrf-af-ipv4)# route-target both auto evpn

Leaf1(config-vrf-af-ipv4)# vrf context ManTenant
Leaf1(config-vrf)# vni 1000200
Leaf1(config-vrf)# rd auto
Leaf1(config-vrf)# address-family ipv4 unicast
Leaf1(config-vrf-af-ipv4)# route-target both auto
Leaf1(config-vrf-af-ipv4)# route-target both auto evpn

Leaf1(config-vrf-af-ipv4)# interface Vlan100 Leaf1(config-if)# no shutdown Leaf1(config-if)# vrf member WomanTenant Leaf1(config-if)# ip forward Leaf1(config-if)# interface Vlan11

Leaf1(config-if)# no shutdown

Leaf1(config-if)# vrf member WomanTenant

Leaf1(config-if)# ip address 192.168.11.1/24

Leaf1(config-if)# fabric forwarding mode anycast-gateway

Leaf1(config-if)# interface Vlan12

Leaf1(config-if)# no shutdown

Leaf1(config-if)# vrf member WomanTenant

Leaf1(config-if)# ip address 192.168.12.1/24

Leaf1(config-if)# fabric forwarding mode anycast-gateway

Leaf1(config-if)# interface Vlan200

Leaf1(config-if)# no shutdown

Leaf1(config-if)# vrf member ManTenant

Leaf1(config-if)# ip forward

Leaf1(config-if)# interface Vlan21

Leaf1(config-if)# no shutdown

Leaf1(config-if)# vrf member ManTenant

Leaf1(config-if)# ip address 192.168.21.1/24

Leaf1(config-if)# fabric forwarding mode anycast-gateway

Leaf1(config-if)# interface Vlan22

Leaf1(config-if)# no shutdown

Leaf1(config-if)# vrf member ManTenant

Leaf1(config-if)# ip address 192.168.22.1/24

Leaf1(config-if)# fabric forwarding mode anycast-gateway

Leaf1(config-if)# interface nve1

Leaf1(config-if-nve)# no shutdown

Leaf1(config-if-nve)# source-interface loopback1

Leaf1(config-if-nve)# host-reachability protocol bgp

Leaf1(config-if-nve)# member vni 1000100 associate-vrf

Leaf1(config-if-nve-vni)# member vni 100011

Leaf1(config-if-nve-vni)# mcast-group 239.1.1.11

Leaf1(config-if-nve-vni)# exit

Leaf1(config-if-nve)# member vni 100012

Leaf1(config-if-nve-vni)# mcast-group 239.1.1.12

Leaf1(config-if-nve-vni)# exit

Leaf1(config-if-nve)# member vni 1000200 associate-vrf

Leaf1(config-if-nve-vni)# member vni 100021

Leaf1(config-if-nve-vni)# mcast-group 239.1.1.21

Leaf1(config-if-nve-vni)# exit

Leaf1(config-if-nve)# member vni 100022

Leaf1(config-if-nve-vni)# mcast-group 239.1.1.22

Leaf1(config-if-nve-vni)# exit

Leaf1(config-if-nve)# interface Ethernet1/1-2
Leaf1(config-if-range)# no switchport
Leaf1(config-if-range)# medium p2p
Leaf1(config-if-range)# ip unnumbered loopback1
Leaf1(config-if-range)# ip router ospf 1 area 0.0.0.0
Leaf1(config-if-range)# ip pim sparse-mode
Leaf1(config-if-range)# no shutdown

Leaf1(config-if-range)# interface Ethernet1/5 Leaf1(config-if)# switchport Leaf1(config-if)# switchport mode access Leaf1(config-if)# switchport access vlan 11

Leaf1(config-if)# interface Ethernet1/6 Leaf1(config-if)# switchport Leaf1(config-if)# switchport mode access Leaf1(config-if)# switchport access vlan 12

Leaf1(config-if)# interface Ethernet1/7
Leaf1(config-if)# switchport
Leaf1(config-if)# switchport mode access
Leaf1(config-if)# switchport access vlan 21

Leaf1(config-if)# interface Ethernet1/8 Leaf1(config-if)# switchport Leaf1(config-if)# switchport mode access Leaf1(config-if)# switchport access vlan 22

Leaf1(config-if)# interface loopback1 Leaf1(config-if)# ip address 11.11.11.11/32 Leaf1(config-if)# ip router ospf 1 area 0.0.0.0 Leaf1(config-if)# ip pim sparse-mode

Leaf1(config-if)# router ospf 1 Leaf1(config-router)# router-id 11.11.11.11

Leaf1(config)# router bgp 1
Leaf1(config-router)# router-id 11.11.11.11
Leaf1(config-router)# address-family ipv4 unicast
Leaf1(config-router-af)# address-family l2vpn evpn

Leaf1(config-router-af)# vrf WomanTenant Leaf1(config-router-vrf)# address-family ipv4 unicast Leaf1(config-router-vrf-af)# advertise l2vpn evpn

Leaf1(config-router-vrf-af)# vrf ManTenant Leaf1(config-router-vrf)# address-family ipv4 unicast Leaf1(config-router-vrf-af)# advertise l2vpn evpn Leaf1(config-router-vrf-af)# template peer Spine-Peers
Leaf1(config-router-neighbor)# remote-as 1
Leaf1(config-router-neighbor)# update-source loopback1
Leaf1(config-router-neighbor)# address-family ipv4 unicast
Leaf1(config-router-neighbor-af)# address-family l2vpn evpn
Leaf1(config-router-neighbor-af)# send-community extended

Leaf1(config-router-neighbor-af)# neighbor 21.21.21.21 Leaf1(config-router-neighbor)# inherit peer Spine-Peers

Leaf1(config-router-neighbor)# neighbor 22.22.22.22 Leaf1(config-router-neighbor)# inherit peer Spine-Peers

Leaf1(config-router-vrf-neighbor)# evpn Leaf1(config-evpn)# vni 100011 l2 Leaf1(config-evpn-evi)# rd auto Leaf1(config-evpn-evi)# route-target import auto Leaf1(config-evpn-evi)# route-target export auto

Leaf1(config-evpn-evi)# evpn Leaf1(config-evpn)# vni 100012 l2 Leaf1(config-evpn-evi)# rd auto Leaf1(config-evpn-evi)# route-target import auto Leaf1(config-evpn-evi)# route-target export auto

Leaf1(config-evpn-evi)# evpn Leaf1(config-evpn)# vni 100021 l2 Leaf1(config-evpn-evi)# rd auto Leaf1(config-evpn-evi)# route-target import auto Leaf1(config-evpn-evi)# route-target export auto

Leaf1(config-evpn-evi)# evpn Leaf1(config-evpn)# vni 100022 l2 Leaf1(config-evpn-evi)# rd auto Leaf1(config-evpn-evi)# route-target import auto Leaf1(config-evpn-evi)# route-target export auto

Leaf2 Configuration:

Leaf2(config)# feature bgp Leaf2(config)# feature pim Leaf2(config)# feature interface-vlan Leaf2(config)# feature vn-segment-vlan-based Leaf2(config)# feature nv overlay

Leaf2(config)# fabric forwarding anycast-gateway-mac 0001.0001.0001

Leaf2(config)# ip pim rp-address 10.10.10.10 group-list 224.0.0.0/4

Leaf2(config)# vlan 100,11,12,200,21,22

Leaf2(config-vlan)# vlan 100 Leaf2(config-vlan)# name L3-VNI-VLAN-100 Leaf2(config-vlan)# vn-segment 1000100

Leaf2(config-vlan)# vlan 11 Leaf2(config-vlan)# vn-segment 100011

Leaf2(config-vlan)# vlan 12 Leaf2(config-vlan)# vn-segment 100012

Leaf2(config-vlan)# vlan 200 Leaf2(config-vlan)# name L3-VNI-VLAN-200 Leaf2(config-vlan)# vn-segment 1000200

Leaf2(config-vlan)# vlan 21 Leaf2(config-vlan)# vn-segment 100021

Leaf2(config-vlan)# vlan 22 Leaf2(config-vlan)# vn-segment 100022

Leaf2(config-vlan)# vrf context WomanTenant
Leaf2(config-vrf)# vni 1000100
Leaf2(config-vrf)# rd auto
Leaf2(config-vrf)# address-family ipv4 unicast
Leaf2(config-vrf-af-ipv4)# route-target both auto
Leaf2(config-vrf-af-ipv4)# route-target both auto evpn

Leaf2(config-vrf-af-ipv4)# vrf context ManTenant Leaf2(config-vrf)# vni 1000200 Leaf2(config-vrf)# rd auto Leaf2(config-vrf)# address-family ipv4 unicast Leaf2(config-vrf-af-ipv4)# route-target both auto Leaf2(config-vrf-af-ipv4)# route-target both auto evpn

Leaf2(config-vrf-af-ipv4)# interface Vlan100 Leaf2(config-if)# no shutdown Leaf2(config-if)# vrf member WomanTenant Leaf2(config-if)# ip forward Leaf2(config-if)# interface Vlan11

Leaf2(config-if)# no shutdown

Leaf2(config-if)# vrf member WomanTenant

Leaf2(config-if)# ip address 192.168.11.1/24

Leaf2(config-if)# fabric forwarding mode anycast-gateway

Leaf2(config-if)# interface Vlan12

Leaf2(config-if)# no shutdown

Leaf2(config-if)# vrf member WomanTenant

Leaf2(config-if)# ip address 192.168.12.1/24

Leaf2(config-if)# fabric forwarding mode anycast-gateway

Leaf2(config-if)# interface Vlan200

Leaf2(config-if)# no shutdown

Leaf2(config-if)# vrf member ManTenant

Leaf2(config-if)# ip forward

Leaf2(config-if)# interface Vlan21

Leaf2(config-if)# no shutdown

Leaf2(config-if)# vrf member ManTenant

Leaf2(config-if)# ip address 192.168.21.1/24

Leaf2(config-if)# fabric forwarding mode anycast-gateway

Leaf2(config-if)# interface Vlan22

Leaf2(config-if)# no shutdown

Leaf2(config-if)# vrf member ManTenant

Leaf2(config-if)# ip address 192.168.22.1/24

Leaf2(config-if)# fabric forwarding mode anycast-gateway

Leaf2(config-if)# interface nve1

Leaf2(config-if-nve)# no shutdown

Leaf2(config-if-nve)# source-interface loopback1

Leaf2(config-if-nve)# host-reachability protocol bgp

Leaf2(config-if-nve)# member vni 1000100 associate-vrf

Leaf2(config-if-nve-vni)# member vni 100011

Leaf2(config-if-nve-vni)# mcast-group 239.1.1.11

Leaf2(config-if-nve-vni)# exit

Leaf2(config-if-nve)# member vni 100012

Leaf2(config-if-nve-vni)# mcast-group 239.1.1.12

Leaf2(config-if-nve-vni)# exit

Leaf2(config-if-nve)# member vni 1000200 associate-vrf

Leaf2(config-if-nve-vni)# member vni 100021

Leaf2(config-if-nve-vni)# mcast-group 239.1.1.21

Leaf2(config-if-nve-vni)# exit

Leaf2(config-if-nve)# member vni 100022

Leaf2(config-if-nve-vni)# mcast-group 239.1.1.22

Leaf2(config-if-nve-vni)# exit

Leaf2(config-if-nve)# interface Ethernet1/1-2
Leaf2(config-if-range)# no switchport
Leaf2(config-if-range)# medium p2p
Leaf2(config-if-range)# ip unnumbered loopback1
Leaf2(config-if-range)# ip router ospf 1 area 0.0.0.0
Leaf2(config-if-range)# ip pim sparse-mode
Leaf2(config-if-range)# no shutdown

Leaf2(config-if-range)# interface Ethernet1/5 Leaf2(config-if)# switchport Leaf2(config-if)# switchport mode access Leaf2(config-if)# switchport access vlan 11

Leaf2(config-if)# interface Ethernet1/6 Leaf2(config-if)# switchport Leaf2(config-if)# switchport mode access Leaf2(config-if)# switchport access vlan 12

Leaf2(config-if)# interface Ethernet1/7
Leaf2(config-if)# switchport
Leaf2(config-if)# switchport mode access
Leaf2(config-if)# switchport access vlan 21

Leaf2(config-if)# interface Ethernet1/8 Leaf2(config-if)# switchport Leaf2(config-if)# switchport mode access Leaf2(config-if)# switchport access vlan 22

Leaf2(config-if)# interface loopback1 Leaf2(config-if)# ip address 12.12.12.12/32 Leaf2(config-if)# ip router ospf 1 area 0.0.0.0 Leaf2(config-if)# ip pim sparse-mode

Leaf2(config-if)# router ospf 1 Leaf2(config-router)# router-id 12.12.12.12

Leaf2(config)# router bgp 1 Leaf2(config-router)# router-id 12.12.12.12 Leaf2(config-router)# address-family ipv4 unicast Leaf2(config-router-af)# address-family l2vpn evpn

Leaf2(config-router-af)# vrf WomanTenant Leaf2(config-router-vrf)# address-family ipv4 unicast Leaf2(config-router-vrf-af)# advertise l2vpn evpn

Leaf2(config-router-vrf-af)# vrf ManTenant Leaf2(config-router-vrf)# address-family ipv4 unicast Leaf2(config-router-vrf-af)# advertise l2vpn evpn Leaf2(config-router-vrf-af)# template peer Spine-Peers
Leaf2(config-router-neighbor)# remote-as 1
Leaf2(config-router-neighbor)# update-source loopback1
Leaf2(config-router-neighbor)# address-family ipv4 unicast
Leaf2(config-router-neighbor-af)# address-family l2vpn evpn
Leaf2(config-router-neighbor-af)# send-community extended

Leaf2(config-router-neighbor-af)# neighbor 21.21.21.21 Leaf2(config-router-neighbor)# inherit peer Spine-Peers

Leaf2(config-router-neighbor)# neighbor 22.22.22.22 Leaf2(config-router-neighbor)# inherit peer Spine-Peers

Leaf2(config-router-vrf-neighbor)# evpn Leaf2(config-evpn)# vni 100011 l2 Leaf2(config-evpn-evi)# rd auto Leaf2(config-evpn-evi)# route-target import auto Leaf2(config-evpn-evi)# route-target export auto

Leaf2(config-evpn-evi)# evpn Leaf2(config-evpn)# vni 100012 l2 Leaf2(config-evpn-evi)# rd auto Leaf2(config-evpn-evi)# route-target import auto Leaf2(config-evpn-evi)# route-target export auto

Leaf2(config-evpn-evi)# evpn Leaf2(config-evpn)# vni 100021 l2 Leaf2(config-evpn-evi)# rd auto Leaf2(config-evpn-evi)# route-target import auto Leaf2(config-evpn-evi)# route-target export auto

Leaf2(config-evpn-evi)# evpn Leaf2(config-evpn)# vni 100022 l2 Leaf2(config-evpn-evi)# rd auto Leaf2(config-evpn-evi)# route-target import auto Leaf2(config-evpn-evi)# route-target export auto

Leaf3 Configuration:

Leaf3(config)# feature bgp Leaf3(config)# feature pim Leaf3(config)# feature interface-vlan Leaf3(config)# feature vn-segment-vlan-based Leaf3(config)# feature nv overlay

Leaf3(config)# fabric forwarding anycast-gateway-mac 0001.0001.0001

Leaf3(config)# ip pim rp-address 10.10.10.10 group-list 224.0.0.0/4

Leaf3(config)# vlan 100,11,12,200,21,22

Leaf3(config-vlan)# vlan 100 Leaf3(config-vlan)# name L3-VNI-VLAN-100 Leaf3(config-vlan)# vn-segment 1000100

Leaf3(config-vlan)# vlan 11 Leaf3(config-vlan)# vn-segment 100011

Leaf3(config-vlan)# vlan 12 Leaf3(config-vlan)# vn-segment 100012

Leaf3(config-vlan)# vlan 200 Leaf3(config-vlan)# name L3-VNI-VLAN-200 Leaf3(config-vlan)# vn-segment 1000200

Leaf3(config-vlan)# vlan 21 Leaf3(config-vlan)# vn-segment 100021

Leaf3(config-vlan)# vlan 22 Leaf3(config-vlan)# vn-segment 100022

Leaf3(config-vlan)# vrf context WomanTenant Leaf3(config-vrf)# vni 1000100 Leaf3(config-vrf)# rd auto Leaf3(config-vrf)# address-family ipv4 unicast Leaf3(config-vrf-af-ipv4)# route-target both auto Leaf3(config-vrf-af-ipv4)# route-target both auto evpn

Leaf3(config-vrf-af-ipv4)# vrf context ManTenant Leaf3(config-vrf)# vni 1000200 Leaf3(config-vrf)# rd auto Leaf3(config-vrf)# address-family ipv4 unicast Leaf3(config-vrf-af-ipv4)# route-target both auto Leaf3(config-vrf-af-ipv4)# route-target both auto evpn

Leaf3(config-vrf-af-ipv4)# interface Vlan100 Leaf3(config-if)# no shutdown Leaf3(config-if)# vrf member WomanTenant Leaf3(config-if)# ip forward Leaf3(config-if)# interface Vlan11

Leaf3(config-if)# no shutdown

Leaf3(config-if)# vrf member WomanTenant

Leaf3(config-if)# ip address 192.168.11.1/24

Leaf3(config-if)# fabric forwarding mode anycast-gateway

Leaf3(config-if)# interface Vlan12

Leaf3(config-if)# no shutdown

Leaf3(config-if)# vrf member WomanTenant

Leaf3(config-if)# ip address 192.168.12.1/24

Leaf3(config-if)# fabric forwarding mode anycast-gateway

Leaf3(config-if)# interface Vlan200

Leaf3(config-if)# no shutdown

Leaf3(config-if)# vrf member ManTenant

Leaf3(config-if)# ip forward

Leaf3(config-if)# interface Vlan21

Leaf3(config-if)# no shutdown

Leaf3(config-if)# vrf member ManTenant

Leaf3(config-if)# ip address 192.168.21.1/24

Leaf3(config-if)# fabric forwarding mode anycast-gateway

Leaf3(config-if)# interface Vlan22

Leaf3(config-if)# no shutdown

Leaf3(config-if)# vrf member ManTenant

Leaf3(config-if)# ip address 192.168.22.1/24

Leaf3(config-if)# fabric forwarding mode anycast-gateway

Leaf3(config-if)# interface nve1

Leaf3(config-if-nve)# no shutdown

Leaf3(config-if-nve)# source-interface loopback1

Leaf3(config-if-nve)# host-reachability protocol bgp

Leaf3(config-if-nve)# member vni 1000100 associate-vrf

Leaf3(config-if-nve-vni)# member vni 100011

Leaf3(config-if-nve-vni)# mcast-group 239.1.1.11

Leaf3(config-if-nve-vni)# exit

Leaf3(config-if-nve)# member vni 100012

Leaf3(config-if-nve-vni)# mcast-group 239.1.1.12

Leaf3(config-if-nve-vni)# exit

Leaf3(config-if-nve)# member vni 1000200 associate-vrf

Leaf3(config-if-nve-vni)# member vni 100021

Leaf3(config-if-nve-vni)# mcast-group 239.1.1.21

Leaf3(config-if-nve-vni)# exit

Leaf3(config-if-nve)# member vni 100022

Leaf3(config-if-nve-vni)# mcast-group 239.1.1.22

Leaf3(config-if-nve-vni)# exit

Leaf3(config-if-nve)# interface Ethernet1/1-2 Leaf3(config-if-range)# no switchport Leaf3(config-if-range)# medium p2p Leaf3(config-if-range)# ip unnumbered loopback1 Leaf3(config-if-range)# ip router ospf 1 area 0.0.0.0 Leaf3(config-if-range)# ip pim sparse-mode Leaf3(config-if-range)# no shutdown

Leaf3(config-if-range)# interface Ethernet1/5 Leaf3(config-if)# switchport Leaf3(config-if)# switchport mode access Leaf3(config-if)# switchport access vlan 11

Leaf3(config-if)# interface Ethernet1/6 Leaf3(config-if)# switchport Leaf3(config-if)# switchport mode access Leaf3(config-if)# switchport access vlan 12

Leaf3(config-if)# interface Ethernet1/7
Leaf3(config-if)# switchport
Leaf3(config-if)# switchport mode access
Leaf3(config-if)# switchport access vlan 21

Leaf3(config-if)# interface Ethernet1/8 Leaf3(config-if)# switchport Leaf3(config-if)# switchport mode access Leaf3(config-if)# switchport access vlan 22

Leaf3(config-if)# interface loopback1 Leaf3(config-if)# ip address 13.13.13.13/32 Leaf3(config-if)# ip router ospf 1 area 0.0.0.0 Leaf3(config-if)# ip pim sparse-mode

Leaf3(config-if)# router ospf 1 Leaf3(config-router)# router-id 13.13.13.13

Leaf3(config)# router bgp 1 Leaf3(config-router)# router-id 13.13.13.13 Leaf3(config-router)# address-family ipv4 unicast Leaf3(config-router-af)# address-family l2vpn evpn

Leaf3(config-router-af)# vrf WomanTenant Leaf3(config-router-vrf)# address-family ipv4 unicast Leaf3(config-router-vrf-af)# advertise l2vpn evpn

Leaf3(config-router-vrf-af)# vrf ManTenant Leaf3(config-router-vrf)# address-family ipv4 unicast Leaf3(config-router-vrf-af)# advertise l2vpn evpn Leaf3(config-router-vrf-af)# template peer Spine-Peers
Leaf3(config-router-neighbor)# remote-as 1
Leaf3(config-router-neighbor)# update-source loopback1
Leaf3(config-router-neighbor)# address-family ipv4 unicast
Leaf3(config-router-neighbor-af)# address-family l2vpn evpn
Leaf3(config-router-neighbor-af)# send-community extended

Leaf3(config-router-neighbor-af)# neighbor 21.21.21.21 Leaf3(config-router-neighbor)# inherit peer Spine-Peers

Leaf3(config-router-neighbor)# neighbor 22.22.22.22 Leaf3(config-router-neighbor)# inherit peer Spine-Peers

Leaf3(config-router-vrf-neighbor)# evpn Leaf3(config-evpn)# vni 100011 l2 Leaf3(config-evpn-evi)# rd auto Leaf3(config-evpn-evi)# route-target import auto Leaf3(config-evpn-evi)# route-target export auto

Leaf3(config-evpn-evi)# evpn Leaf3(config-evpn)# vni 100012 l2 Leaf3(config-evpn-evi)# rd auto Leaf3(config-evpn-evi)# route-target import auto Leaf3(config-evpn-evi)# route-target export auto

Leaf3(config-evpn-evi)# evpn Leaf3(config-evpn)# vni 100021 l2 Leaf3(config-evpn-evi)# rd auto Leaf3(config-evpn-evi)# route-target import auto Leaf3(config-evpn-evi)# route-target export auto

Leaf3(config-evpn-evi)# evpn Leaf3(config-evpn)# vni 100022 l2 Leaf3(config-evpn-evi)# rd auto Leaf3(config-evpn-evi)# route-target import auto Leaf3(config-evpn-evi)# route-target export auto

Leaf4 Configuration:

Leaf4(config)# feature bgp Leaf4(config)# feature pim Leaf4(config)# feature interface-vlan Leaf4(config)# feature vn-segment-vlan-based Leaf4(config)# feature nv overlay

Leaf4(config)# fabric forwarding anycast-gateway-mac 0001.0001.0001

Leaf4(config)# ip pim rp-address 10.10.10.10 group-list 224.0.0.0/4

Leaf4(config)# vlan 100,11,12,200,21,22

Leaf4(config-vlan)# vlan 100 Leaf4(config-vlan)# name L3-VNI-VLAN-100 Leaf4(config-vlan)# vn-segment 1000100

Leaf4(config-vlan)# vlan 11 Leaf4(config-vlan)# vn-segment 100011

Leaf4(config-vlan)# vlan 12 Leaf4(config-vlan)# vn-segment 100012

Leaf4(config-vlan)# vlan 200 Leaf4(config-vlan)# name L3-VNI-VLAN-200 Leaf4(config-vlan)# vn-segment 1000200

Leaf4(config-vlan)# vlan 21 Leaf4(config-vlan)# vn-segment 100021

Leaf4(config-vlan)# vlan 22 Leaf4(config-vlan)# vn-segment 100022

Leaf4(config-vlan)# vrf context WomanTenant
Leaf4(config-vrf)# vni 1000100
Leaf4(config-vrf)# rd auto
Leaf4(config-vrf)# address-family ipv4 unicast
Leaf4(config-vrf-af-ipv4)# route-target both auto
Leaf4(config-vrf-af-ipv4)# route-target both auto evpn

Leaf4(config-vrf-af-ipv4)# vrf context ManTenant Leaf4(config-vrf)# vni 1000200 Leaf4(config-vrf)# rd auto Leaf4(config-vrf)# address-family ipv4 unicast Leaf4(config-vrf-af-ipv4)# route-target both auto Leaf4(config-vrf-af-ipv4)# route-target both auto evpn

Leaf4(config-vrf-af-ipv4)# interface Vlan100 Leaf4(config-if)# no shutdown Leaf4(config-if)# vrf member WomanTenant Leaf4(config-if)# ip forward Leaf4(config-if)# interface Vlan11

Leaf4(config-if)# no shutdown

Leaf4(config-if)# vrf member WomanTenant

Leaf4(config-if)# ip address 192.168.11.1/24

Leaf4(config-if)# fabric forwarding mode anycast-gateway

Leaf4(config-if)# interface Vlan12

Leaf4(config-if)# no shutdown

Leaf4(config-if)# vrf member WomanTenant

Leaf4(config-if)# ip address 192.168.12.1/24

Leaf4(config-if)# fabric forwarding mode anycast-gateway

Leaf4(config-if)# interface Vlan200

Leaf4(config-if)# no shutdown

Leaf4(config-if)# vrf member ManTenant

Leaf4(config-if)# ip forward

Leaf4(config-if)# interface Vlan21

Leaf4(config-if)# no shutdown

Leaf4(config-if)# vrf member ManTenant

Leaf4(config-if)# ip address 192.168.21.1/24

Leaf4(config-if)# fabric forwarding mode anycast-gateway

Leaf4(config-if)# interface Vlan22

Leaf4(config-if)# no shutdown

Leaf4(config-if)# vrf member ManTenant

Leaf4(config-if)# ip address 192.168.22.1/24

Leaf4(config-if)# fabric forwarding mode anycast-gateway

Leaf4(config-if)# interface nve1

Leaf4(config-if-nve)# no shutdown

Leaf4(config-if-nve)# source-interface loopback1

Leaf4(config-if-nve)# host-reachability protocol bgp

Leaf4(config-if-nve)# member vni 1000100 associate-vrf

Leaf4(config-if-nve-vni)# member vni 100011

Leaf4(config-if-nve-vni)# mcast-group 239.1.1.11

Leaf4(config-if-nve-vni)# exit

Leaf4(config-if-nve)# member vni 100012

Leaf4(config-if-nve-vni)# mcast-group 239.1.1.12

Leaf4(config-if-nve-vni)# exit

Leaf4(config-if-nve)# member vni 1000200 associate-vrf

Leaf4(config-if-nve-vni)# member vni 100021

Leaf4(config-if-nve-vni)# mcast-group 239.1.1.21

Leaf4(config-if-nve-vni)# exit

Leaf4(config-if-nve)# member vni 100022

Leaf4(config-if-nve-vni)# mcast-group 239.1.1.22

Leaf4(config-if-nve-vni)# exit

Leaf4(config-if-nve)# interface Ethernet1/1-2 Leaf4(config-if-range)# no switchport Leaf4(config-if-range)# medium p2p Leaf4(config-if-range)# ip unnumbered loopback1 Leaf4(config-if-range)# ip router ospf 1 area 0.0.0.0 Leaf4(config-if-range)# ip pim sparse-mode Leaf4(config-if-range)# no shutdown

Leaf4(config-if-range)# interface Ethernet1/5 Leaf4(config-if)# switchport Leaf4(config-if)# switchport mode access Leaf4(config-if)# switchport access vlan 11

Leaf4(config-if)# interface Ethernet1/6 Leaf4(config-if)# switchport Leaf4(config-if)# switchport mode access Leaf4(config-if)# switchport access vlan 12

Leaf4(config-if)# interface Ethernet1/7
Leaf4(config-if)# switchport
Leaf4(config-if)# switchport mode access
Leaf4(config-if)# switchport access vlan 21

Leaf4(config-if)# interface Ethernet1/8 Leaf4(config-if)# switchport Leaf4(config-if)# switchport mode access Leaf4(config-if)# switchport access vlan 22

Leaf4(config-if)# interface loopback1 Leaf4(config-if)# ip address 12.12.12.12/32 Leaf4(config-if)# ip router ospf 1 area 0.0.0.0 Leaf4(config-if)# ip pim sparse-mode

Leaf4(config-if)# router ospf 1 Leaf4(config-router)# router-id 12.12.12.12

Leaf4(config)# router bgp 1 Leaf4(config-router)# router-id 14.14.14.14 Leaf4(config-router)# address-family ipv4 unicast Leaf4(config-router-af)# address-family l2vpn evpn

Leaf4(config-router-af)# vrf WomanTenant Leaf4(config-router-vrf)# address-family ipv4 unicast Leaf4(config-router-vrf-af)# advertise l2vpn evpn

Leaf4(config-router-vrf-af)# vrf ManTenant Leaf4(config-router-vrf)# address-family ipv4 unicast Leaf4(config-router-vrf-af)# advertise l2vpn evpn Leaf4(config-router-vrf-af)# template peer Spine-Peers
Leaf4(config-router-neighbor)# remote-as 1
Leaf4(config-router-neighbor)# update-source loopback1
Leaf4(config-router-neighbor)# address-family ipv4 unicast
Leaf4(config-router-neighbor-af)# address-family l2vpn evpn
Leaf4(config-router-neighbor-af)# send-community extended

Leaf4(config-router-neighbor-af)# neighbor 21.21.21.21 Leaf4(config-router-neighbor)# inherit peer Spine-Peers

Leaf4(config-router-neighbor)# neighbor 22.22.22.22 Leaf4(config-router-neighbor)# inherit peer Spine-Peers

Leaf4(config-router-vrf-neighbor)# evpn Leaf4(config-evpn)# vni 100011 l2 Leaf4(config-evpn-evi)# rd auto Leaf4(config-evpn-evi)# route-target import auto Leaf4(config-evpn-evi)# route-target export auto

Leaf4(config-evpn-evi)# evpn Leaf4(config-evpn)# vni 100012 l2 Leaf4(config-evpn-evi)# rd auto Leaf4(config-evpn-evi)# route-target import auto Leaf4(config-evpn-evi)# route-target export auto

Leaf4(config-evpn-evi)# evpn Leaf4(config-evpn)# vni 100021 l2 Leaf4(config-evpn-evi)# rd auto Leaf4(config-evpn-evi)# route-target import auto Leaf4(config-evpn-evi)# route-target export auto

Leaf4(config-evpn-evi)# evpn Leaf4(config-evpn)# vni 100022 l2 Leaf4(config-evpn-evi)# rd auto Leaf4(config-evpn-evi)# route-target import auto Leaf4(config-evpn-evi)# route-target export auto

Spinel Configuration:

Spine1(config)# nv overlay evpn Spine1(config)# feature ospf Spine1(config)# feature bgp Spine1(config)# feature pim

Spine1(config)# ip pim rp-address 10.10.10.10 group-list 224.0.0.0/4

Spine1(config)# interface loopback 0 Spine1(config-if)# ip address 10.10.10.10/32 Spine1(config-if)# ip router ospf 1 area 0.0.0.0 Spine1(config-if)# ip pim sparse-mode

Spine1(config-if)# interface loopback 1 Spine1(config-if)# ip address 21.21.21.21/32 Spine1(config-if)# ip router ospf 1 area 0.0.0.0 Spine1(config-if)# ip pim sparse-mode

Spine1(config)# interface Ethernet1/1-4
Spine1(config-if-range)# no switchport
Spine1(config-if-range)# medium p2p
Spine1(config-if-range)# ip unnumbered loopback1
Spine1(config-if-range)# ip router ospf 1 area 0.0.0.0
Spine1(config-if-range)# ip pim sparse-mode
Spine1(config-if-range)# no shutdown

Spine1(config-if)# router ospf 1 Spine1(config-router)# router-id 21.21.21.21

Spine1(config-router)# router bgp 1 Spine1(config-router)# router-id 21.21.21.21 Spine1(config-router)# address-family ipv4 unicast Spine1(config-router-af)# address-family l2vpn evpn

Spine1(config-router-af)# template peer Leaf-Peers
Spine1(config-router-neighbor)# remote-as 1
Spine1(config-router-neighbor)# update-source loopback 1
Spine1(config-router-neighbor)# address-family ipv4 unicast
Spine1(config-router-neighbor-af)# send-community both
Spine1(config-router-neighbor-af)# route-reflector-client
Spine1(config-router-neighbor-af)# address-family l2vpn evpn
Spine1(config-router-neighbor-af)# send-community both
Spine1(config-router-neighbor-af)# route-reflector-client

Spine1(config-router-neighbor-af)# neighbor 11.11.11.11 Spine1(config-router-neighbor)# inherit peer Leaf-Peers

Spine1(config-router-neighbor)# neighbor 12.12.12.12 Spine1(config-router-neighbor)# inherit peer Leaf-Peers Spine1(config-router-neighbor)# neighbor 13.13.13.13 Spine1(config-router-neighbor)# inherit peer Leaf-Peers

Spine1(config-router-neighbor)# neighbor 14.14.14.14 Spine1(config-router-neighbor)# inherit peer Leaf-Peers

Spine2 Configuration:

Spine2(config)# nv overlay evpn Spine2(config)# feature ospf Spine2(config)# feature bgp Spine2(config)# feature pim

Spine2(config)# ip pim rp-address 10.10.10.10 group-list 224.0.0.0/4

Spine2(config)# interface Ethernet1/1-4
Spine2(config-if-range)# no switchport
Spine2(config-if-range)# medium p2p
Spine2(config-if-range)# ip unnumbered loopback1
Spine2(config-if-range)# ip router ospf 1 area 0.0.0.0
Spine2(config-if-range)# ip pim sparse-mode
Spine2(config-if-range)# no shutdown

Spine2(config-if-range)# interface loopback 0 Spine2(config-if)# ip address 10.10.10.10/32 Spine2(config-if)# ip router ospf 1 area 0.0.0.0 Spine2(config-if)# ip pim sparse-mode

Spine2(config-if)# interface loopback 1 Spine2(config-if)# ip address 22.22.22.22/32 Spine2(config-if)# ip router ospf 1 area 0.0.0.0 Spine2(config-if)# ip pim sparse-mode

Spine2(config-if)# router ospf 1 Spine2(config-router)# router-id 22.22.22.22

Spine2(config-router)# router bgp 1 Spine2(config-router)# router-id 22.22.22.22 Spine2(config-router)# address-family ipv4 unicast Spine2(config-router-af)# address-family l2vpn evpn

Spine2(config-router-af)# template peer Leaf-Peers
Spine2(config-router-neighbor)# remote-as 1
Spine2(config-router-neighbor)# update-source loopback 1
Spine2(config-router-neighbor)# address-family ipv4 unicast
Spine2(config-router-neighbor-af)# send-community both
Spine2(config-router-neighbor-af)# route-reflector-client
Spine2(config-router-neighbor-af)# address-family l2vpn evpn
Spine2(config-router-neighbor-af)# send-community both
Spine2(config-router-neighbor-af)# route-reflector-client

Spine2(config-router-neighbor-af)# neighbor 11.11.11.11 Spine2(config-router-neighbor)# inherit peer Leaf-Peers

Spine2(config-router-neighbor)# neighbor 12.12.12.12 Spine2(config-router-neighbor)# inherit peer Leaf-Peers Spine2(config-router-neighbor)# neighbor 13.13.13.13 Spine2(config-router-neighbor)# inherit peer Leaf-Peers

Spine2(config-router-neighbor)# neighbor 14.14.14.14 Spine2(config-router-neighbor)# inherit peer Leaf-Peers

Monitoring Command

Leaf1# show ip ospf neighbors
Leaf1# show ip bgp summary
Leaf1# show vxlan
Leaf1# show nve vni
Leaf1# show nve interface
Leaf1# show nve peers
Leaf1# show bgp l2vpn evpn
Leaf1# show bgp l2vpn evpn vni-id 100011
Leaf1# show bgp l2vpn evpn vni-id 100012
Leaf1# show bgp l2vpn evpn vni-id 100021
Leaf1# show bgp l2vpn evpn vni-id 100022
Leaf1# show bgp l2vpn evpn vni-id 100022
Leaf1# show l2route evpn mac-ip all

Spine1# show bgp l2vpn evpn