
Cisco SD-WAN Class Trainer: Behrouz Soleimani www.nethightech.com nethightech@gmail.com

Scenario Name: Single Home - Underlay Configuration

Cisco SD-WAN LAB-1 Trainer: Behrouz Soleimani



vManagel Configuration:

vmanage# config terminal

vmanage(config)# vpn 0
vmanage(config-vpn-0)# ip route 0.0.0.0/0 172.16.1.1
vmanage(config-vpn-0)# no interface
vmanage(config-vpn-0)# interface eth1
vmanage(config-interface-eth1)# ip address 172.16.1.101/24
vmanage(config-interface-eth1)# no shutdown
vmanage(config-interface-eth1)# tunnel-interface
vmanage(config-tunnel-interface)# color mpls
vmanage(config-tunnel-interface)# allow-service all
vmanage(config-tunnel-interface)# exit
vmanage(config-interface-eth1)# exit
vmanage(config-vpn-0)# exit

vmanage(config)# vpn 512 vmanage(config-vpn-512)# no interface vmanage(config-vpn-512)# interface eth0 vmanage(config-interface-eth0)# ip address 192.168.100.101/24 vmanage(config-interface-eth0)# no shutdown vmanage(config-interface-eth0)# exit vmanage(config-vpn-512)# exit

vmanage(config)# system vmanage(config-system)# host-name vManage1 vmanage(config-system)# site-id 1 vmanage(config-system)# system-ip 1.1.1.101 vmanage(config-system)# organization-name NetHighTech vmanage(config-system)# clock timezone Europe/Lisbon vmanage(config-system)# vbond 172.16.1.111

vmanage(config-system)# ntp vmanage(config-ntp)# server 192.168.100.1 vmanage(config-server-192.168.100.1)# commit and-quit

vManage1#

vBondl Configuration:

vedge# config terminal

vedge(config)# vpn 0
vedge(config-vpn-0)# ip route 0.0.0.0/0 172.16.1.1
vedge(config-vpn-0)# interface ge0/0
vedge(config-interface-ge0/0)# ip address 172.16.1.111/24
vedge(config-interface-ge0/0)# no shutdown
vedge(config-interface-ge0/0)# no tunnel-interface
vedge(config-interface-ge0/0)# tunnel-interface
vedge(config-tunnel-interface)# color mpls
vedge(config-tunnel-interface)# encapsulation ipsec
vedge(config-tunnel-interface)# allow-service all
vedge(config-tunnel-interface)# exit
vedge(config-interface-ge0/0)# exit
vedge(config-vpn-0)# exit

vedge(config)# vpn 512 vedge(config-vpn-512)# interface eth0 vedge(config-interface-eth0)# ip address 192.168.100.111/24 vedge(config-interface-eth0)# no shutdown vedge(config-interface-eth0)# exit vedge(config-vpn-512)# exit

vedge(config)# system vedge(config-system)# host-name vBond1 vedge(config-system)# site-id 1 vedge(config-system)# system-ip 1.1.1.111 vedge(config-system)# organization-name NetHighTech vedge(config-system)# clock timezone Europe/Lisbon vedge(config-system)# vbond 172.16.1.111 local

vedge(config-system)# ntp vedge(config-ntp)# server 192.168.100.1 vedge(config-server-192.168.100.1)# commit and-quit vBond1#

vSmart1 Configuration:

vsmart# config terminal

vsmart(config)# vpn 0
vsmart(config-vpn-0)# ip route 0.0.0.0/0 172.16.1.1
vsmart(config-vpn-0)# no interface
vsmart(config-vpn-0)# interface eth1
vsmart(config-interface-eth1)# ip address 172.16.1.121/24
vsmart(config-interface-eth1)# no shutdown
vsmart(config-interface-eth1)# no tunnel-interface
vsmart(config-interface-eth1)# tunnel-interface
vsmart(config-tunnel-interface)# color mpls
vsmart(config-tunnel-interface)# allow-service all
vsmart(config-tunnel-interface)# exit
vsmart(config-interface-eth1)# exit
vsmart(config-vpn-0)# exit

vsmart(config)# vpn 512 vsmart(config-vpn-512)# no interface vsmart(config-vpn-512)# interface eth0 vsmart(config-interface-eth0)# ip address 192.168.100.121/24 vsmart(config-interface-eth0)# no shutdown vsmart(config-interface-eth0)# exit vsmart(config-vpn-512)# exit

vsmart(config)# system vsmart(config-system)# host-name vSmart1 vsmart(config-system)# site-id 1 vsmart(config-system)# system-ip 1.1.1.121 vsmart(config-system)# clock timezone Europe/Lisbon vsmart(config-system)# vbond 172.16.1.111

vsmart(config-system)# ntp vsmart(config-ntp)# server 192.168.100.1 vsmart(config-server-192.168.100.1)# commit and-quit vSmart1#

vEdgel Configuration:

vedge# config terminal

```
vedge(config)# vpn 512
vedge(config-vpn-512)# no interface
vedge(config-vpn-512)# interface eth0
vedge(config-interface-eth0)# ip address 192.168.100.201/24
vedge(config-interface-eth0)# no shutdown
vedge(config-interface-eth0)# exit
vedge(config-vpn-512)# exit
vedge(config)# vpn 0
vedge(config-vpn-0)# ip route 0.0.0.0/0 172.16.101.1
vedge(config-vpn-0)# no interface
vedge(config-vpn-0)# interface ge0/0
vedge(config-interface-ge0/0)# ip address 172.16.101.101/24
vedge(config-interface-ge0/0)# no shutdown
vedge(config-interface-ge0/0)# no tunnel-interface
vedge(config-interface-ge0/0)# tunnel-interface
vedge(config-tunnel-interface)# color mpls
vedge(config-tunnel-interface)# encapsulation ipsec
vedge(config-tunnel-interface)# allow-service all
vedge(config-tunnel-interface)# exit
vedge(config-interface-ge0/0)# exit
vedge(config-vpn-0)# exit
vedge(config)# system
vedge(config-system)# host-name vEdge1
vedge(config-system)# site-id 101
vedge(config-system)# system-ip 1.1.1.201
vedge(config-system)# organization-name NetHighTech
vedge(config-system)# clock timezone Europe/Lisbon
vedge(config-system)# vbond 172.16.1.111
vedge(config-system)# ntp
vedge(config-ntp)# server 192.168.100.1
vedge(config-server-192.168.100.1)# commit and-quit
vEdge1#
vEdge1# vshell
vEdge1:~$ scp behrouz@192.168.100.247:/home/behrouz/Downloads/Root.cer /home/admin/.
vEdge1:~$ exit
vEdge1# request root-cert-chain install /home/admin/Root.cer
vEdge1# request csr upload /home/admin/vEdge1.csr
       Enter organization-unit name
                                          : NetHighTech
       Re-enter organization-unit name
                                         : NetHighTech
vEdge1:~$ scp /home/admin/vEdge1.csr behrouz@192.168.100.247:/home/behrouz/Downloads/.
vEdge1:~$ scp behrouz@192.168.100.247:/home/behrouz/Downloads/vEdge1.cer /home/admin/.
vEdge1:~$ exit
vEdge1# request certificate install /home/admin/vEdge1.cer
vEdge1# request vedge-cloud activate chassis-number ...... token .......
```

vEdge2 Configuration:

vedge# config terminal

vedge(config)# vpn 512 vedge(config-vpn-512)# no interface vedge(config-vpn-512)# interface eth0 vedge(config-interface-eth0)# ip address 192.168.100.202/24 vedge(config-interface-eth0)# no shutdown vedge(config-interface-eth0)# exit vedge(config-vpn-512)# exit vedge(config)# vpn 0 vedge(config-vpn-0)# ip route 0.0.0.0/0 172.16.102.1 vedge(config-vpn-0)# no interface vedge(config-vpn-0)# interface ge0/0 vedge(config-interface-ge0/0)# ip address 172.16.102.102/24 vedge(config-interface-ge0/0)# no shutdown vedge(config-interface-ge0/0)# no tunnel-interface vedge(config-interface-ge0/0)# tunnel-interface vedge(config-tunnel-interface)# color mpls vedge(config-tunnel-interface)# encapsulation ipsec vedge(config-tunnel-interface)# allow-service all vedge(config-tunnel-interface)# exit vedge(config-interface-ge0/0)# exit vedge(config-vpn-0)# exit vedge(config)# system vedge(config-system)# host-name vEdge2 vedge(config-system)# site-id 102 vedge(config-system)# system-ip 1.1.1.202 vedge(config-system)# organization-name NetHighTech vedge(config-system)# clock timezone Europe/Lisbon vedge(config-system)# vbond 172.16.1.111 vedge(config-system)# ntp vedge(config-ntp)# server 192.168.100.1 vedge(config-server-192.168.100.1)# commit and-quit vEdge2# vEdge2# vshell vEdge2:~\$ scp behrouz@192.168.100.247:/home/behrouz/Downloads/Root.cer /home/admin/. vEdge2:~\$ exit vEdge2# request root-cert-chain install /home/admin/Root.cer vEdge2# request csr upload /home/admin/vEdge2.csr Enter organization-unit name : NetHighTech Re-enter organization-unit name : NetHighTech vEdge2:~\$ scp /home/admin/vEdge2.csr behrouz@192.168.100.247:/home/behrouz/Downloads/. vEdge2:~\$ scp behrouz@192.168.100.247:/home/behrouz/Downloads/vEdge2.cer /home/admin/. vEdge2:~\$ exit vEdge2# request certificate install /home/admin/vEdge2.cer vEdge2# request vedge-cloud activate chassis-number token

vEdge3 Configuration:

vedge# config terminal

vedge(config)# vpn 512 vedge(config-vpn-512)# no interface vedge(config-vpn-512)# interface eth0 vedge(config-interface-eth0)# ip address 192.168.100.203/24 vedge(config-interface-eth0)# no shutdown vedge(config-interface-eth0)# exit vedge(config-vpn-512)# exit vedge(config)# vpn 0 vedge(config-vpn-0)# ip route 0.0.0.0/0 172.16.103.1 vedge(config-vpn-0)# no interface vedge(config-vpn-0)# interface ge0/0 vedge(config-interface-ge0/0)# ip address 172.16.103.103/24 vedge(config-interface-ge0/0)# no shutdown vedge(config-interface-ge0/0)# no tunnel-interface vedge(config-interface-ge0/0)# tunnel-interface vedge(config-tunnel-interface)# color mpls vedge(config-tunnel-interface)# encapsulation ipsec vedge(config-tunnel-interface)# allow-service all vedge(config-tunnel-interface)# exit vedge(config-interface-ge0/0)# exit vedge(config-vpn-0)# exit vedge(config)# system vedge(config-system)# host-name vEdge3 vedge(config-system)# site-id 103 vedge(config-system)# system-ip 1.1.1.203 vedge(config-system)# organization-name NetHighTech vedge(config-system)# clock timezone Europe/Lisbon vedge(config-system)# vbond 172.16.1.111 vedge(config-system)# ntp vedge(config-ntp)# server 192.168.100.1 vedge(config-server-192.168.100.1)# commit and-quit vEdge3# vEdge3# vshell vEdge3:~\$ scp behrouz@192.168.100.247:/home/behrouz/Downloads/Root.cer /home/admin/. vEdge3:~\$ exit vEdge3# request root-cert-chain install /home/admin/Root.cer vEdge3# request csr upload /home/admin/vEdge3.csr Enter organization-unit name : NetHighTech Re-enter organization-unit name : NetHighTech vEdge3:~\$ scp /home/admin/vEdge3.csr behrouz@192.168.100.247:/home/behrouz/Downloads/. vEdge3:~\$ scp behrouz@192.168.100.247:/home/behrouz/Downloads/vEdge3.cer /home/admin/. vEdge3:~\$ exit vEdge3# request certificate install /home/admin/vEdge3.cer vEdge3# request vedge-cloud activate chassis-number token

vEdge4 Configuration:

vedge# config terminal

vedge(config)# vpn 512 vedge(config-vpn-512)# no interface vedge(config-vpn-512)# interface eth0 vedge(config-interface-eth0)# ip address 192.168.100.204/24 vedge(config-interface-eth0)# no shutdown vedge(config-interface-eth0)# exit vedge(config-vpn-512)# exit vedge(config)# vpn 0 vedge(config-vpn-0)# ip route 0.0.0.0/0 172.16.104.1 vedge(config-vpn-0)# no interface vedge(config-vpn-0)# interface ge0/0 vedge(config-interface-ge0/0)# ip address 172.16.104.104/24 vedge(config-interface-ge0/0)# no shutdown vedge(config-interface-ge0/0)# no tunnel-interface vedge(config-interface-ge0/0)# tunnel-interface vedge(config-tunnel-interface)# color mpls vedge(config-tunnel-interface)# encapsulation ipsec vedge(config-tunnel-interface)# allow-service all vedge(config-tunnel-interface)# exit vedge(config-interface-ge0/0)# exit vedge(config-vpn-0)# exit vedge(config)# system vedge(config-system)# host-name vEdge4 vedge(config-system)# site-id 104 vedge(config-system)# system-ip 1.1.1.204 vedge(config-system)# organization-name NetHighTech vedge(config-system)# clock timezone Europe/Lisbon vedge(config-system)# vbond 172.16.1.111 vedge(config-system)# ntp vedge(config-ntp)# server 192.168.100.1 vedge(config-server-192.168.100.1)# commit and-quit vEdge4# vEdge4# vshell vEdge4:~\$ scp behrouz@192.168.100.247:/home/behrouz/Downloads/Root.cer /home/admin/. vEdge4:~\$ exit vEdge4# request root-cert-chain install /home/admin/Root.cer vEdge4# request csr upload /home/admin/vEdge4.csr Enter organization-unit name : NetHighTech Re-enter organization-unit name : NetHighTech vEdge4:~\$ scp /home/admin/vEdge4.csr behrouz@192.168.100.247:/home/behrouz/Downloads/. vEdge4:~\$ scp behrouz@192.168.100.247:/home/behrouz/Downloads/vEdge4.cer /home/admin/. vEdge4:~\$ exit vEdge4# request certificate install /home/admin/vEdge4.cer vEdge4# request vedge-cloud activate chassis-number token