



EXBRAINSDK

NeU License Manager User Manual

For Windows 10 / 11

Version 1.0.1

Compatible SDK	ExBrainSDK v3.2.0
Document version	1.0.1
Issue date	August 31, 2026

CONTENTS

Contents

01	Introduction	3
02	Developer licenses	3
03	Release licenses	3
04	System requirements and preparation	4
05	Installation and startup	4
06	Main window	5
07	Activate a developer license	6
08	Refresh license information	7
09	Deactivate a license	7
10	Create a release license	8
11	Troubleshooting	9
12	Uninstallation and support	10
13	Changelog	10
A	Release license packaging guide	11

First-time users

Start on page 3 to understand the two license types.

Moving to another PC

Complete the deactivation steps on page 7 before moving.

Application developers

See page 8 and Appendix A for release license creation.

GETTING STARTED

Understanding licenses

1. Introduction

Using ExBrainSDK requires a valid license. Without one, SDK initialization or licensed API calls return a license error.

i One place to manage licenses

NeU License Manager is the central application for activating, viewing, checking, reloading, reactivating, and deactivating licenses, and for creating licenses for applications that will be shipped to end users.

2. Developer licenses

How you receive one


NeU issues the developer a license key. Enter that key directly in NeU License Manager to activate the license for the current Windows user.

What it enables

After activation, SDK license checks succeed and development can proceed without API calls returning missing-license errors.

3. Release licenses

A release license is for a completed application delivered to end users. A developer license with release-license creation permission allows License Manager to inspect the installed application, create an application-specific signed license, and produce instructions for adding it to the application installer.



A permitted developer license creates an app-specific release license. The installer deploys it with the application, so end users do not enter a license key.

! Release licenses are application-specific

Create the license from the installed application that will actually be shipped. Create it again whenever any shipped application file changes.

GETTING STARTED

Installation preparation

4. System requirements and preparation

Supported OS	Windows 10 / Windows 11 (64-bit)
Internet connection	Required for activation, reactivation, deactivation, and release license creation
Administrator rights	Required for installation and uninstallation, and when managing licenses stored for the entire PC
License key	A key issued by NeU

5. Installation and startup

- 1 Run `LicenseManager.msi`.
- 2 If Windows displays a confirmation prompt, review it and allow the installation.
- 3 Start “NeU License Manager” from the Start menu.


Default installation folder: `C:\Program Files\NeU\LicenseManager`

Installing a newer version updates the existing application.

MAIN WINDOW

6. Main window

The main window displays installed license information and the controls used to manage each license.



- “操作” (Actions) menu**
Opens the release license creation feature.
- License information**
Shows type, holder, GUID, expiration, status, and application hash.
- Controls for each license**
Resynchronizes with the server or deactivates the license on this PC.
- General controls**
Reloads saved information or activates a new key.


Main status indicators

Status	Meaning	Status	Meaning
有効 (Valid)	Ready to use	期限切れ (Expired)	Past the expiration date
破損 (Corrupted)	Saved data is damaged	ハードウェア不一致 (Hardware mismatch)	Does not match the activated PC
アプリ検証失敗 (App validation failed)	Does not match the registered app	PC の時刻が正しくありません (Incorrect PC time)	Date or time setting problem

ACTIVATION

7. Activate a developer license

- 1 Select “新しいライセンスを有効化” (Activate New License) at the bottom of the main window.
- 2 Enter the license key issued by NeU.
- 3 Select “OK”.
- 4 Confirm that “ライセンスの有効化に成功しました” (License activated successfully) appears.
- 5 Confirm that the license appears in the list with a status of “有効” (Valid).

**i Entering a key**

Spaces and line breaks before or after the key are removed automatically. Do not insert spaces or line breaks within the key.

! Do not interrupt communication

Do not close the application or disconnect from the internet until activation is complete.

Where licenses are stored

A newly activated developer license is stored for the currently signed-in Windows user. It cannot be viewed or used by another Windows user, even on the same PC.

License	Used by	Storage scope
Developer license	Developers building apps with the SDK	Current Windows user
Release license	Users of a completed app	Entire PC (managed by the app installer)

MAINTENANCE

8. Refresh license information

Reload

Reloads the license information stored on the PC and refreshes the display.

Use this after another tool or installer adds a license, or when only the display needs to be refreshed.

Reactivate

Connects to the license server and updates the selected license.

- When NeU informs you of an expiration or configuration change
- After correcting the PC date and time
- When the displayed status is unexpected

9. Deactivate a license

Before changing PCs or using the same license on another PC, deactivate it on the current PC.

- 1 Select “無効化” (Deactivate) for the applicable license.
- 2 Confirm that “ライセンスを無効化しました” (License deactivated) appears.
- 3 Confirm that the license is removed from the list.

Deactivation removes the license saved on the PC and clears its activation status on the license server. Whether it can be activated again depends on the terms of the issued license.

! Before this PC becomes unavailable

Always deactivate the license before replacing, resetting, or disposing of the PC, or reinstalling Windows. If the PC is already unavailable, contact your NeU representative.

i Release licenses stored for the entire PC

Administrator rights are required. Normally, manage these licenses through the release application's installer or uninstaller.

FOR DEVELOPERS

10. Create a release license

This feature is available only with a developer license for which NeU has granted release license creation permission (`CanSpawnLicenses`).

- 1 Install the application under development on the PC in the same way an end user will install it.
- 2 Start NeU License Manager.
- 3 Under “操作” (Actions), select “リリースライセンス作成” (Create release license).
- 4 Select the developer license to use.
- 5 Select the installed application folder, executable file, or script entry point.
- 6 Select an output folder and create the release license.
- 7 Confirm that an instruction file has been created in the output folder.

```
NeUReleaseLicense_<license-guid>_instructions_and_license.txt
```

! Do not select a build folder

Always select the installed application exactly as it will be shipped to end users. Create a new release license whenever any shipped file changes.

Generated content

Signed license

Contains validation information for the selected application.

Integration instructions

Explains how to add the license to the application installer.

For detailed integration instructions, see “Appendix A: Release license packaging guide” beginning on page 11.

TROUBLESHOOTING

11. Troubleshooting

Symptom	Checks and solutions
Activation, reactivation, or deactivation fails	Check the internet connection and the PC date and time, then try again.
“期限切れ” (Expired) appears	Check the license expiration date and ask NeU to renew the license if necessary.
“ハードウェア不一致” (Hardware mismatch) appears	Check whether the license is active on another PC. If the previous PC is available, deactivate it there before activating it again.
“PC の時刻が正しくありません” (Incorrect PC time) appears	Correct the Windows date, time, and time zone, then select “再有効化” (Reactivate).
“アプリ検証失敗” (App validation failed) appears	Check whether the installed application files have changed since the release license was created.
The license does not appear in the list	Select “再読み込み” (Reload). If the problem remains, activate the license again.
A release license cannot be created	Confirm that the developer license is valid and has permission to create release licenses.

i If “不明” (Unknown) appears

Record the detailed status name in parentheses and the operation performed immediately before the problem, then contact support.

Information needed when contacting support

- License Manager version
- ExBrainSDK version
- Windows version

- Complete error message
- Operation that caused the problem
- Date and time of the problem

UNINSTALL & SUPPORT

12. Uninstallation and support

- 1 Open Windows “Settings”.
- 2 Open “Apps” or “Installed apps”.
- 3 Select “NeU License Manager” from the list and uninstall it.

! Licenses are not deactivated automatically

Uninstalling the application does not remove activated licenses. When moving from or disposing of a PC, deactivate the applicable license before uninstalling.

Handling license information

■ Protect confidential information

Do not post license keys or generated release license text in public channels or locations accessible to unspecified users.

Support

If the problem remains, contact your NeU representative and include the information listed under “Information needed when contacting support” on page 9.

This manual	v1.0.1
NeU License Manager	v1.0.1
Compatible ExBrainSDK	v3.2.0
Issue date	August 31, 2026

13. Changelog

Version	Changes
v1.0.1	Added support for Windows computer names containing Japanese or other non-ASCII characters.
v1.0.0	Initial release.

The screen diagrams in this manual are for explanation. Actual displays may vary depending on Windows settings and license type.

APPENDIX A

Release License Packaging Guide


A guide for developers shipping an ExBrainSDK application to end users.

! The most important rule

When creating a release license, select the installed application, not the build folder.

The installed folder represents the customer's runtime environment. A build folder may contain extra files, temporary binaries, debug symbols, or a different layout. If the wrong folder is selected, the release SDK may reject the application as `AppInvalid`.

Release workflow



What happens internally

1. License Manager inspects the installed files.
2. It creates an `AppHash` payload containing hashes and application validation JSON.
3. It sends the payload to the NeU license server.
4. It receives a signed release license from the server.

i After changing the application

Create the release license again whenever any application file to be shipped changes.

PACKAGING DETAILS

Python applications and generated files

Python applications

Select the installed folder containing the shipped scripts and native dependencies, or select the installed entry-point script.

Use one of the following methods so that the SDK can identify the root folder to validate.

- Start the application with the installed application folder as its working directory
- Place `ExBrainSdkNative.dll` in the application folder
- Set `NEU_APP_ROOT` to the application folder before loading the SDK

Examples of validated files

`.py` `.pyw` `.pyz` `.pyd` `.dll`

Package data, lock, configuration, and resource files

Examples of exclusions

`__pycache__`, `.pyc`

Top-level `log`, `logs`, `temp`, and `tmp`

Do not store required shipping assets in these folders.

Generated file

```
NeUReleaseLicense_<license-guid>_instructions_and_license.txt
```

This file contains bilingual installer instructions and the complete release license.

Installer registry settings

```
HKEY_LOCAL_MACHINE\Software\NeU\Licenses
```

Value name	The release license GUID
------------	--------------------------

Value data	The complete release license text from the instruction file
------------	---

`HKLM` requires administrator rights. Configure it from the application installer.

VALIDATION

AppInvalid and offline operation

Common causes of AppInvalid

- Legacy bare-hash license: separate validation JSON is missing
- **appHash** does not match the signed payload
- Legacy bare-hash license: validation JSON has an invalid schema

- A validated file is missing
- A file size is different
- SHA-256 content is different

i JSON formatting differences

Whitespace and JSON property order do not matter because the SDK reconstructs a consistent internal representation before validation.

Offline operation

An internet connection is not required for normal release SDK feature checks. A release license is not bound to the developer's or end user's machine ID.

It is valid on any PC only when the installed application matches the signed **AppHash**.

Server synchronization

End-user tools can send a later reactivation request. This makes the PC visible on the server and allows a remotely revoked license to be detected when the application or License Manager synchronizes.

■ Final check before shipment

Install the installer containing the signed license on a clean PC and verify its operation.