


Implementing VLANs and Trunks


Issues in a Poorly Designed Network

- Unbounded failure domains
- Large broadcast domains
- Large amount of unknown MAC unicast traffic
- Unbounded multicast traffic
- Management and support challenges
- Possible security vulnerabilities



VLAN Overview

- Segmentation
- Flexibility
- Security




VLAN = Broadcast Domain = Logical Network (Subnet)

Designing VLANs for an Organization

- VLAN design must take into consideration the implementation of a hierarchical network addressing scheme.
- The benefits of hierarchical addressing are:
 - Ease of management and troubleshooting
 - Minimization of errors
 - Reduced number of routing table entries

Guidelines for Applying IP Address Space



- Allocate one IP subnet per VLAN.
- Allocate IP address spaces in contiguous blocks.

Network Traffic Types

Multicast


Server

Cisco


CallManager

Traffic types to consider when designating VLANs:


- Network management
- IP telephony
- IP Multicast
- Normal data
- Scavenger class




802.1Q Trunking




802.1Q Frame




ISL Encapsulation




Understanding Native VLANs



VTP Features




VTP Modes




VTP Operation

- VTP advertisements are sent as multicast frames.
- VTP servers and clients are synchronized to the latest revision number.
- VTP advertisements are sent every 5 minutes or when there is a change.



VTP Pruning



Configuring VLANs and Trunks

- 1. Configure and verify VTP.
- 2. Configure and verify 802.1Q trunks.
- 3. Create or modify a VLAN on the VTP server switch.
- 4. Assign switch ports to a VLAN and verify.
- 5. Execute adds, moves, and changes.
- 6. Save the VLAN configuration.

VTP Configuration Guidelines

- VTP defaults for the Cisco Catalyst switch:
 - VTP domain name: None
 - VTP mode: Server mode
 - VTP pruning: Enabled or disabled (model specific)
 - VTP password: Null
 - VTP version: Version 1
- A new switch can automatically become part of a domain once it receives an advertisement from a server.
- A VTP client can overwrite a VTP server database if the client has a higher revision number.
- A domain name cannot be removed after it is assigned; it can only be reassigned.


Creating a VTP Domain

```
SwitchX# configure terminal
SwitchX(config)# vtp mode [ server | client | transparent ]
SwitchX(config)# vtp domain domain-name
SwitchX(config)# vtp password password
SwitchX(config)# vtp pruning
SwitchX(config)# end
```

VTP Configuration and Verification Example

```
SwitchX(config) # vtp domain ICND
Changing VTP domain name to ICND
SwitchX(config)# vtp mode transparent
Setting device to VTP TRANSPARENT mode.
SwitchX(config)# end
SwitchX# show vtp status
VTP Version
Configuration Revision
Maximum VLANs supported locally: 64
Number of existing VLANs : 17
VTP Operating Mode
                          : Transparent
VTP Domain Name
                            : ICND
                            : Disabled
VTP Pruning Mode
                            : Disabled
VTP V2 Mode
                        : Disabled
VTP Traps Generation
                               : 0x7D 0x6E 0x5E 0x3D 0xAF 0xAO 0x2F 0xAA
MD5 digest
Configuration last modified by 10.1.1.4 at 3-3-93 20:08:05
SwitchX#
```

802.1Q Trunking Issues



Configuring 802.1Q Trunking

```
SwitchX(config-if)#
switchport mode {access | dynamic {auto | desirable} | trunk}
```

Configures the trunking characteristics of the port

```
SwitchX(config-if)#
switchport mode trunk
```

Configures the port as a VLAN trunk

Verifying a Trunk

SwitchX# show interfaces interface [switchport | trunk]

```
SwitchX# show interfaces fa0/11 switchport
Name: Fa0/11
Switchport: Enabled
Administrative Mode: trunk
Operational Mode: down
Administrative Trunking Encapsulation: dot1q
Negotiation of Trunking: On
Access Mode VLAN: 1 (default)
Trunking Native Mode VLAN: 1 (default)
. . . .
```

```
SwitchX# show interfaces fa0/11 trunk
Port.
          Mode
                                                   Native vlan
                       Encapsulation Status
         desirable
Fa0/11
                        802.1q
                                      trunking
Port
       Vlans allowed on trunk
Fa0/11
           1-4094
           Vlans allowed and active in management domain
Port
Fa0/11
           1-13
```

VLAN Creation Guidelines

- The maximum number of VLANs is switch-dependent.
- Most Cisco Catalyst desktop switches support 128 separate spanning-tree instances, one per VLAN.
- VLAN 1 is the factory default Ethernet VLAN.
- Cisco Discovery Protocol and VTP advertisements are sent on VLAN 1.
- The Cisco Catalyst switch IP address is in the management VLAN (VLAN 1 by default).
- If using VTP, the switch must be in VTP server or transparent mode to add or delete VLANs.

Adding a VLAN

```
SwitchX# configure terminal
SwitchX(config)# vlan 2
SwitchX(config-vlan)# name switchlab99
```

Verifying a VLAN

```
SwitchX# show vlan [brief | id vlan-id || name vlan-name]
```

```
      SwitchX# show vlan id 2

      VLAN Name
      Status
      Ports

      2
      switchlab99
      active
      Fa0/2, Fa0/12

      VLAN Type
      SAID
      MTU
      Parent RingNo BridgeNo Stp
      BrdgMode Trans1 Trans2

      2
      enet 100002
      1500 - - - - - 0 0
      0

      SwitchX#
```

Assigning Switch Ports to a VLAN

```
SwitchX(config-if)#
```

```
switchport access [vlan vlan# | dynamic]
```

```
SwitchX# configure terminal
SwitchX(config)# interface range fastethernet 0/2 - 4
SwitchX(config-if)# switchport access vlan 2

SwitchX# show vlan

VLAN Name

Status Ports

1 default active Fa0/1
2 switchlab99 active Fa0/2, Fa0/3, Fa0/4
```

Verifying VLAN Membership

SwitchX# show vlan brief

	chX# show vlan brief Name	Status	Ports
4 1002	default switchlab99 vlan3 vlan4 fddi-default token-ring-default	active active active active act/unsup act/unsup	Fa0/1 Fa0/2, Fa0/3, Fa0/4
VLAN	Name	Status	Ports
	fddinet-default trnet-default	act/unsup act/unsup	

Verifying VLAN Membership (Cont.)

```
SwitchX(config-if)#
```

show interfaces interface switchport

```
SwitchX# show interfaces fa0/2 switchport
Name: Fa0/2
Switchport: Enabled
Administrative Mode: dynamic auto
Operational Mode: static access
Administrative Trunking Encapsulation: dot1q
Operational Trunking Encapsulation: native
Negotiation of Trunking: On
Access Mode VLAN: 2 (switchlab99)
Trunking Native Mode VLAN: 1 (default)
--- output omitted ----
```

Executing Adds, Moves, and Changes for VLANs

- When using VTP, the switch must be in VTP server or transparent mode to add, change, or delete VLANs.
- When you make VLAN changes from a switch in VTP server mode, the change is propagated to other switches in the VTP domain.
- Changing VLANs typically implies changing IP networks.
- After a port is reassigned to a new VLAN, that port is automatically removed from its previous VLAN.
- When you delete a VLAN, any ports in that VLAN that are not moved to an active VLAN will be unable to communicate with other stations.

#