# Introduction to virtual memory and Mechanism of Address

# Why virtualize memory?

- Because real view of memory is messy!
- Earlier, memory had only code of one running process (and OS code)
- Now, multiple active processes timeshare CPU
  - Memory of many processes must be in memory
  - Non-contiguous too
- Need to hide this complexity from user




Figure 13.2: Three Processes: Sharing Memory

### Abstraction: (Virtual) Address Space

0KB

15KB

**16KB** 

- Virtual address space: every process assumes it has access to a large space of memory from address 0 to a MAX
- Contains program code (and static data), heap (dynamic allocations), and stack (used during function calls)
  - Stack and heap grow during runtime
- CPU issues loads and stores to virtual addresses





Figure 13.3: An Example Address Space


## How is actual memory reached?

- Address translation from virtual addresses (VA) to physical addresses (PA)
  - CPU issues loads/stores to VA but memory hardware accesses PA
- OS allocates memory and tracks location of processes
- Translation done by memory hardware called Memory Management Unit (MMU)
  - OS makes the necessary information available



# Example: Paging

- OS divides virtual address space into fixed size pages, physical memory into frames
- To allocate memory, a page is mapped to a free physical frame
- Page table stores mappings from virtual page number to physical frame number for a process (e.g, page 0 to frame 3)
- MMU has access to page tables, and uses it to translate VA to PA



## Goals of memory virtualization

- Transparency: user programs should not be aware of the messy details
- Efficiency: minimize overhead and wastage in terms of memory space and access time
- Isolation and protection: a user process should not be able to access anything outside its address space

### How can a user allocate memory?

- OS allocates a set of pages to the memory image of the process
- Within this image
  - Static/global variables are allocated in the executable
  - Local variables of a function on stack
  - Dynamic allocation with malloc on the heap





Figure 13.3: An Example Address Space


## Memory allocation system calls

- malloc implemented by C library
  - Algorithms for efficient memory allocation and free space management
- To grow heap, libc uses the brk/sbrk system call
- A program can also allocate a page sized memory using the mmap () system call
  - Gets "anonymous" page from OS



# A subtle point: what is the address space of the OS?

- OS is not a separate process with its own address space
- Instead, OS code is part of the address space of every process
- A process sees OS as part of its code (e.g., library)
- Page tables map the OS addresses to OS code



### How does the OS allocate memory?

- OS needs memory for its data structures
- For large allocations, OS allocates a page
- For smaller allocations, OS uses various memory allocation algorithms (more later)
  - Cannot use libc and malloc in kernel!

### A simple example


Consider a simple C function

```
void func() {
int x = 3000; //
x = x + 3;
```

It is compiled as follows


```
128: movl 0x0(%ebx), %eax ;load 0+ebx into eax ;add 3 to eax register 135: movl %eax, 0x0(%ebx) ;store eax back to mem
```

 Virtual address space is setup by OS during process creation



#### **Address Translation**

- Simplified OS: places entire memory image in one chunk
- Need the following translation from VA to PA
  - 128 to 32896 (32KB + 128)
  - 1KB to 33 KB
  - 20KB? Error!



#### Who performs address translation?

- In this simple example, OS tells the hardware the base (starting address) and bound (total size of process) values
- Memory hardware Memory Management Unit (MMU) calculates PA from VA
- MMu also cliecks in address + base bound
- OS is not involved in every translation

#### Role of hardware in translation

- CPU provides privileged mode of execution
- Instruction set has privileged instructions to set translation information (e.g., base, bound)
- Hardware (MMU) uses this information to perform translation on every memory access
- MMU generates faults and traps to OS when access is illegal (e.g., VA is out of bound)

#### Role of OS in translation


- OS maintains free list of memory
- Allocates space to process during creation (and when asked) and cleans up when done
- Maintains information of where space is allocated to each process (in PCB)
- Sets address translation information (e.g., base & bound) in hardware
- Updates this information upon context switch
- Handles traps due to illegal memory access

#### Segmentation

0KB

64KB

- Generalized base and bounds
- Each segment of memory image placed separately
- Multiple (base, bound) values stored in MMU
- Good for sparse address spaces
- But variable sized allocation leads to external fragmentation
  - Small holes in memory left between segments



# Thank you!!!!