

HISPlayer Unreal SDK

HISPlayer is the most advanced video streaming player for Unreal, supporting local, VOD and live content. It enables premium DASH and HLS video streaming inside your games, metaverses, and VR apps. We include advanced features such as multiple streams or automatic bitrate adaptation to secure the best video quality.

You can find our **complete online documentation** here: [HISPlayer Unreal SDK](#)

This SDK supports the following platforms :

- Android
- iOS
- MacOS
- Windows


QuickStart Guide

Getting started with HISPlayer consists of implementing the following steps:

1. Setup Guide
 - 1.1. Check HISPlayer Plugin
 - 1.2. Set Default Build Settings Version
 - 1.3. Disable Anti-Aliasing
 - 1.4. Import HISPlayer_Blueprint
 - 1.5. Configure HISPlayer Multistream Properties
2. Platform specific setup configurations
 - 2.1. Windows
 - 2.2. Android
 - 2.3. MacOS

It's also possible to use the **HISPlayer Unreal Sample Map**. Before using the sample, it is important to first complete sections 1.1, 1.2, 1.3 and section 2 depending on the platforms that will be used .


The sample is a comprehensive example map using the HISPlayerSDK to help demonstrate features like play, pause, seek, etc. You can find the **HISPlayerUnreal** sample map and **HISPlayerUnrealMultistream** sample map inside the plugin's **Content/Levels** directory.



1. Setup Guide


1.1 Check HISPlayer Plugin

In your Unreal project, go to Edit > Plugins and make sure that the HISPlayer plugin has been installed and enabled.



1.2 Set Default Build Settings Version

It is preferable to use the HISPlayer SDK in a C++ project, rather than in an only blueprint one. To create a C++ project from an only blueprint project, go to **Tools > New C++ Class** and follow the indications to create a new one. Any kind of C++ parent class will work.



Make sure that the "YourProjectName".Target.cs and "YourProjectName"Editor.Target.cs scripts located in the Source directory have the following setup:


```
public class HISPlayerVRSampleTarget : TargetRules
{
    public HISPlayerVRSampleTarget(TargetInfo Target) : base(Target)
    {
        #if UE_5_4_OR_LATER
            Type = TargetType.Game;
            DefaultBuildSettings = BuildSettingsVersion.V5;
            IncludeOrderVersion = EngineIncludeOrderVersion.Unreal5_4;
            ExtraModuleNames.Add("HISPlayerVRSample");
        #else
            Type = TargetType.Game;
            DefaultBuildSettings = BuildSettingsVersion.V2;
            ExtraModuleNames.AddRange(new string[] { "HISPlayerVRSample" });
        #endif
    }
}

public class HISPlayerVRSampleEditorTarget : TargetRules
{
    public HISPlayerVRSampleEditorTarget(TargetInfo Target) : base(Target)
    {
        #if UE_5_4_OR_LATER
            Type = TargetType.Editor;
            DefaultBuildSettings = BuildSettingsVersion.V5;
            IncludeOrderVersion = EngineIncludeOrderVersion.Unreal5_4;
            ExtraModuleNames.Add("HISPlayerVRSample");
        #else
            Type = TargetType.Editor;
            DefaultBuildSettings = BuildSettingsVersion.V2;
            ExtraModuleNames.AddRange(new string[] { "HISPlayerVRSample" });
        #endif
    }
}
```

The HISPlayerSample and HISPlayerVRSample are C++ projects which already include these lines of code so, in case you are using them, you can skip to the next section.


1.3 Disable Anti-Aliasing

If you are experiencing a ghosting effect on the stream, then you will need to disable the anti-aliasing effect on your project. To do that on Unreal 5, go to **Edit > Project Settings > Engine > Rendering > Default Settings > Anti-Aliasing Method** and set it to **None**.




1.4 Import HISPlayer_Blueprint


To use HISPlayer's functionalities in your Level, you need to add the **HISPlayer_Blueprint**. The is located inside **Content Browser > HISPlayer Content > Blueprint**.




If you can't find the **HISPlayer Content** directory in the Content Browser, check "Show Plugin Content" in "View Options".



Add the **HISPlayer_Blueprint**.




To render the content, you need to set an actor with **HISPlayer_Material** as Material.




1.5 Configure HISPlayer Multistream Properties


Set the player's parameters as desired in your **HISPlayer_Blueprint** actor for single stream and multistream. It is possible to add more than one stream using one instance of the **HISPlayer_Blueprint**, by adding more elements to the Stream URL and Target Actors arrays.



You can modify the behavior of the **HISPlayer_Blueprint** as desired or use a custom blueprint, as long as it follows the original structure.



Use the **HISPlayer API** to add your own implementation.




2. Platform specific setup configurations

2.1 Windows

Default RHIs

Make sure that the **Default RHIs** option is settled to **DirectX11** or **DirectX12**. Otherwise, go to **Edit > Project Settings > Platforms > Windows > Targeted RHIs**.



Packaging the Project


In order to package the project, you need to make sure that **Your_Project.uproject** file has been correctly updated on the “**Plugins**” field:

```

{
  "FileVersion": 3,
  "EngineAssociation": "5.1",
  "Category": "",
  "Description": "",
  "Modules": [
    {
      "Name": "HIS",
      "Type": "Runtime",
      "LoadingPhase": "Default"
    }
  ],
  "Plugins": [
    {
      "Name": "ModelingToolsEditorMode",
      "Enabled": true,
      "TargetAllowList": [
        "Editor"
      ]
    },
    {
      "Name": "HISPlayer",
      "Enabled": true
    }
  ]
}


```

You can update this file manually, or by clicking on the Update button when this message appears when opening the project with the plugin installed.



Depending on the Unreal version, it is also possible that you need to generate a visual studio project, if you are working on a Blueprint project.


Finally, after packaging the project, you will need to create a new folder called Plugins inside **Your_BuildRootDirectory > Your_ProjectName folder**, and paste there the HISPlayer folder plugin (similar to the Import Package step)




2.2 Android

Please go to **Edit > Project Settings > Platforms > Android**.

Make sure that you have clicked Configure Android Settings.




Both Vulkan and OpenGL ES3 are supported. You can select either Vulkan or OpenGL ES3 or both according to your project requirement.



2.3 MacOS

Packaging the Project

To package the project, create and test your application as a package.



Additional Information

HISPlayer API

You can find the full information about HISPlayer API for each platform in the following links:

- [Android](#)
- [iOS](#)
- [Windows](#)
- [MacOS](#)

Oculus / Meta Quest

For Oculus/Meta Quest usages and samples, please refer to the [Meta XR Plugin / Meta Quest Setup Guide](#) documentation.