

The ULTRASPEAKER IMAGE LAB

USER GUIDE

Clear, readable photos on every slide

Adjust the light, colour, crop and DuoTone of your photos in the browser and, soon, directly in PowerPoint.

VERSION 1.4 · NOVEMBER 2026

CONTENTS

In this guide

01 Before you start
What Image Lab does, where to find it, web and PowerPoint

02 The interface
The parts of the screen, one by one

03 Adjust a photo
Quick styles, light and colour, tones and detail

04 Histogram, levels and neutral point
Black, midtones, white and colour casts

05 Enhance quality and DuoTone
One-click clean-up, photos in two or three colours

06 Crop and rotation
Formats for slides, social media and print

07 Compare and download
Before / After, Reset and the final file

08 In PowerPoint
Apply to slide and go back to the original

09 Speaker tips
Photos readable on the projector, consistent across slides

10 Frequently asked questions
Common problems and solutions

01 Before you start

Image Lab adjusts the photos on your slides like a photo editor: levels, light, colour, crop, rotation and DuoTone, with the preview always in view.

IN THE BROWSER

Open **niki977.github.io/ultraspeaker-image-lab** on a computer or phone. Load a photo, adjust it and download it: as a JPG, or as a PNG if it has transparent parts.

IN POWERPOINT

Home tab → **The Ultraspeaker** group → **Image Lab**. Select a photo on the slide and the pane replaces it with the adjusted version, keeping the original.


> **COMING SOON**
>
> The PowerPoint pane is being tested and will be available soon. Chapter 08 already describes it in full.

> **PRIVACY**
>
> Photos are processed on your device and are never sent to a server. The browser only stores the language you choose, shared by all The Ultraspeaker Labs.

WHAT YOU NEED	DETAILS
Web version	An up-to-date browser (Chrome, Edge, Safari, Firefox), on a phone too
PowerPoint pane	Microsoft 365: Windows 2601 or later, Mac 16.105 or later, or PowerPoint for the web

02 The interface

The preview stays at the top while you scroll through the adjustments; the buttons to compare and download stay at the bottom.



WEB VERSION · COMPUTER

1. **Language and guide.** Five languages; «Guide» opens this PDF.
2. **Preview.** Shows every adjustment straight away. Drag a photo here to load it.
3. **Tools.** Undo, Redo, Crop, Rotate and Duo & Tri Tone.
4. **Zoom.** Drag the slider up; on a phone, pinch with two fingers.
5. **Try your own photo.** Opens a photo from your computer or phone.
6. **Histogram.** How the tones are spread, from black on the left to white on the right.
7. **Actions.** Reset, Before / After and Download photo.

03 Adjust a photo

Start from a quick style, then fine-tune with the sliders while watching the preview.


1. **Choose a quick style. Stage** raises contrast, shadows and sharpness for the projector; **Enhance** sets the levels for you; **Black & white** and **Warm** change the character of the photo.

2. **Light & colour. Exposure** brightens or darkens everything, **Contrast** separates lights and shadows, **Saturation** doses the colours.

3. **Tones & detail. Highlights** recovers a blown-out sky, **Shadows** opens up dark areas, **Sharpness** and **Reduce noise** work on the detail.

4. **White balance. Temperature** goes from cool to warm, **Tint** from green to magenta.

5. **Double-click** a slider to set it back to zero. **Undo** and **Redo** also work with ⌘Z / Ctrl+Z and ⇧⌘Z / Ctrl+Shift+Z.




«STAGE» STYLE APPLIED

GOOD TO KNOW

Quick styles only change light and colour: crop, rotation, «Enhance quality» and DuoTone stay as you set them.

04 Histogram, levels and neutral point


The histogram shows how many points of the photo sit in each tone. The three handles below decide where black starts, where mid-grey sits and where white ends.



AFTER «AUTO LEVELS»

1. **Read the histogram.** If it is all on the left the photo is dark, if it is all on the right it is light. «SHADOWS CLIPPED» and «HIGHLIGHTS CLIPPED» warn you when detail is lost.
2. **Click Auto levels.** Black and white move to where the data really starts: the photo gains contrast without blowing anything out.
3. **Fine-tune by hand.** Drag **BLACK** to the right for fuller tones, **MIDTONES** to lighten or darken the greys, **WHITE** to the left for more light.
4. **Check a channel.** RGB, R, G, B and LUM show all colours, a single colour or the luminance.

1. **Click Neutral point** when the photo has a colour cast, for example the yellow light of a conference room.
2. **Tap the preview** on a point that should be grey or white: a wall, a lab coat, a sheet of paper. Temperature and Tint adjust themselves.




NEUTRAL POINT ACTIVE

05 Enhance quality and DuoTone


«Enhance quality» cleans up photos taken in low light; Duo & Tri Tone recolours the photo with the colours of your presentation.

ENHANCE QUALITY

Click **Enhance quality**: Image Lab estimates the noise in the photo, reduces it while respecting the edges, sharpens the details and raises the local contrast. With **Strength** you choose how far to go; the photo size does not change.



1. **Open Duo & Tri Tone** with the two-circle button: DuoTone switches on.
2. **Choose DuoTone or TriTone** and one of the eight palettes.
3. **Customise the colours** of Shadows, Midtones (TriTone only) and Highlights with the picker, the hex code or the eyedropper, which takes the colour from the original photo.
4. **Transparent** on Shadows or Highlights makes that part transparent: the photo is saved as a PNG, useful for a logo or a silhouette on a coloured background.
5. **Done** closes the panel; **Remove** removes the DuoTone.



TRITONE, «OCEAN» PALETTE


GOOD TO KNOW

With DuoTone, saturation is not needed and disappears; Temperature and Tint become «Warm/cool filter» and «Green/magenta filter» and shift the light between the colours, like the filters used in black and white photography.

06 Crop and rotation

Each format only sets the aspect ratio: the photo keeps every pixel of the area you choose.

1. **Click Crop** and choose the **Format**: Free, Original, an aspect ratio, a social media format, a slide or a print.
2. **Move the frame** by dragging it and resize it from the corners. You can zoom into the preview: the frame stays still and the photo moves underneath.
3. **Rotate orientation** switches between landscape and portrait.
4. **Apply crop** confirms; **Remove crop** goes back to the whole photo.



INSTAGRAM · PORTRAIT — 4:5


WHERE THE PHOTO GOES	FORMAT IN THE MENU	ASPECT RATIO
Full-screen slide	Slide 16:9	16:9
Square post	Instagram · post	1:1
Portrait post	Instagram · portrait	4:5
Stories, Reels, WhatsApp Status	Instagram / Facebook · Stories and Reels	9:16
Post with a link	Facebook · post, LinkedIn · post	1.91:1
Photo print	Photo 10 × 15 cm	2:3

Need an exact size in pixels or centimetres? Choose **Custom size…**: it is the only format that resizes the photo to that size.

1. **Click Rotate.** The buttons turn the photo 90° left, 90° right or 180°.

2. **Straighten** a crooked horizon by up to ±45° with the slider, the number field or the arrows: 0.5° per click, 0.1° with Shift.

3. A grid appears and the photo zooms in just enough to leave no empty corners. **Done** closes the panel.




STRAIGHTEN 4.5°

07 Compare and download

Before downloading, compare the result with the photo you started from.

1. **Before / After** shows the original photo, labelled «ORIGINAL»; another click goes back to the result.
2. **Reset** removes all adjustments, crop included.
3. **Download photo** saves the adjusted version: a high-quality JPG, or a PNG if there are transparent parts.
4. On a phone the button becomes **Save or share**: choose «Save Image» to add it to Photos, or send it with WhatsApp, Messages or Mail.




PHONE · BEFORE / AFTER

08 In PowerPoint

COMING SOON

The PowerPoint pane is being tested and will be available soon. In the meantime, use the web version and insert the downloaded photo on your slide.

The pane has the same adjustments as the web version; only the last step changes: the photo goes back onto the slide.



PANE · PHOTO SELECTED

1. **Select a photo** on the slide and open **Home → Image Lab**. The line under the logo (1) says «Image selected».

2. **Adjust the photo** while watching the preview (2): PowerPoint does not let add-ins change pixels live, so the slide stays as it is until step 3.

3. **Click Apply to slide** (3). The adjusted photo replaces the original, with the same position, size and rotation; after a crop it stays centred in the same space.

4. **To change your mind** select the photo again: the pane starts from the original with the saved adjustments. **Original**, with confirmation, puts back the photo you started from.

09 Speaker tips

A projector crushes the shadows and dulls the colours: a photo that looks perfect on your screen can turn grey in the room.

SPEAKER TIP

For clinical photos start from **Stage** and check the histogram: important details should not sit in the first or last tenth. If the room is bright, set **Shadows** between +25% and +40%.

SPEAKER TIP

Use the same adjustments for every photo in a sequence, for example before and after a treatment: same style, same temperature, same crop. The audience should notice the clinical result, not a change in the light.

USE	CROP	MINIMUM WIDTH
Full-screen photo	Slide 16:9	1920 px
Photo on half a slide	3:2 or 4:5	1000 px
Two photos side by side (before / after)	the same aspect ratio for both	960 px each

10 Frequently asked questions

Does cropping reduce the resolution?

No. The social media, slide and print formats only set the aspect ratio. Only «Custom size…» resizes the photo to an exact size: if that size is larger than the area you chose, a warning tells you the photo will lose sharpness.

Why is the downloaded photo a PNG?

Because you switched on «Transparent» in DuoTone. When you share from a phone, the transparency may turn black or white.

The slide does not change while I move the sliders.

That is normal: PowerPoint updates the slide only with «Apply to slide». The preview in the pane shows the result straight away.

Where does the original photo go in PowerPoint?

It stays on the same slide, hidden: you can see it in **Home → Arrange → Selection Pane**. Keep it if you want to change the adjustments later.

The pane says «Update PowerPoint».

You need an up-to-date Microsoft 365: Windows 2601 or later, Mac 16.105 or later, or PowerPoint for the web. PowerPoint for iPad is not supported.

Are my photos uploaded to the internet?

No. Processing happens on your device, in the browser or in the pane.

How do I change the language?

From the menu at the top right. Your choice also applies to the other The Ultraspeaker Labs.

SUPPORT

Write to info@theultraspeaker.com, telling us whether you use the web version or PowerPoint (Mac, Windows or web), and attach a screenshot if you can.



Knowledge is not enough.
From expert to Ultraspeaker.

ASK FOR ADVICE

THEULTRASPEAKER.COM · INFO@THEULTRASPEAKER.COM