

Install Card

Создание локальных учетных записей

Создать ТЕХНИЧЕСКИЕ учетные записи (ТУЗ) без права логина на сервер ([стандарт])(<https://wiki.corp.dev.vtb/pages/viewpage.action?pageId=63317572>))

- tyk
- fluentbit
- auditor

Выдать разрешение сервисной УЗ tyk пользоваться crontab

```
```shell
sudo echo tyk >> /etc/cron.allow
sudo usermod -aG crontab tyk
```
```

Создать домашний каталог для пользователя tyk

```
```shell
sudo mkhomedir_helper tyk
```
```

Создать каталоги и назначить права локальным учетным записям

```
```shell
sudo mkdir /app
sudo mkdir /app/tyk-gateway
sudo mkdir /app/logs
sudo mkdir /app/mdcb-proxy
sudo mkdir /app/xmlv
sudo mkdir /app/var_itcs
sudo mkdir /app/etc_itcs
sudo chown -R tyk:tyk /app && sudo chmod -R 775 /app
```
```

Установить fluentbit

Установку fluentbit произвести по стандарту УСИ-UNIX. ([стандарт])(<https://wiki.corp.dev.vtb/pages/viewpage.action?pageId=1690578729>))

Пакет можно взять из публичного репозитория - <https://inst0.nexus-ci.corp.dev.vtb/#browse/browse:tyk-maven-pub>

* Установка VipNet

FYI При работе с ViPNet OSSSL в виртуальной среде ESXi параметры виртуальной машины могут изменяться при перемещении с одного сервера на другой. Отличия между компьютерами фиксируются системой лицензирования и при значительном изменении параметров лицензия может деактивироваться. Для предотвращения деактивации лицензии запретите перемещение виртуальной машины между серверами виртуальной инфраструктуры или задайте маску идентификатора центрального процессора в настройках виртуальной машины.

Создать симлинк из /var/opt/itcs в /app/var_itcs
Создать симлинк из /etc/opt/itcs в /app/etc_itcs
и предоставить права для сервисной учетной записи tyk

```
```shell
sudo mkdir -p /app/var_itcs
sudo mkdir -p /app/etc_itcs
```

```
sudo ln -s /app/var_itcs /var/opt/itcs
sudo ln -s /app/etc_itcs /etc/opt/itcs
sudo chown -R tyk:tyk /app/var_itcs /app/etc_itcs
sudo chmod -R 755 /app/var_itcs /app/etc_itcs
...
```

### ### В случае ручной установки с наличием прав супепользователя.

Архив vipnet\_5.4.tar.gz размещается по пути /tmp/vipnet/vipnet\_5.4.tar.gz

Произвести распаковку архива

```
```shell
tar -xvzf /tmp/vipnet/vipnet_5.4.tar.gz -C /tmp/vipnet
...
```

Запустить скрипт установки, с правами суперпользователя

```
```shell
cd /tmp/vipnet/vipnet_5.4/SOFT/scripts
sudo sh vipnet_ossinstall.sh install --dir ../Default_Astra_x86/DEB/ --all-pltf-dir ../AllPlatforms/DEB/
...
```

### ### При отсутствии прав супепользователя

Установка ПО VipNet OSSL производится UNIX-администраторами. Архив ПО берется из репозитория [URL:MIRROR\\_NAME/packages/deb/all/vipnet/vipnet\\_5.4.tar.gz](http://mirror.region.vtb.ru/packages/deb/all/vipnet/vipnet_5.4.tar.gz) (пример <http://mirror.region.vtb.ru/packages/deb/all/vipnet/>)

Настройка SoftToken без привязки к каталогу пользователя  
(проверить у рута, и удалить)

```
```shell
sudo rm -rf ~/.itcs/soft_token
...
```

Предоставление прав на возможность изменения файла конфигурации

```
```shell
sudo cp /opt/itcs/ssl/itp11gost.cnf /opt/itcs/ssl/openssl.cnf
sudo chmod 666 /opt/itcs/ssl/openssl.cnf
...
```

### ### Создать systemd юниты для сервисов

Создать unit `mdcb-proxy.service`

```
```shell
[Unit]
Description=MDCB proxy unit
Wants=network-online.target
After=network-online.target
```

```
[Service]
LimitNOFILE=300000
Type=simple
User=tyk
Group=tyk
```

```
EnvironmentFile=-/app/mdcb-proxy/mdcb-proxy.env
EnvironmentFile=-/app/mdcb-proxy/mdcb-proxy.local.env
ExecStart=/bin/sh -c '/app/mdcb-proxy/mdcb_proxy --conf /app/mdcb-proxy/mdcb_proxy.config >>
/app/logs/mdcb-proxy.log 2>&1'
Restart=always
WorkingDirectory=/app/mdcb-proxy
```

```
[Install]
WantedBy=multi-user.target
````
```

Создать unit `tyk-gateway.service`

```
````shell
[Unit]
Description=Tyk API Gateway

[Service]
LimitNOFILE=300000
Type=simple
User=tyk
Group=tyk
EnvironmentFile=-/app/tyk-gateway/tyk-gateway.env
EnvironmentFile=-/app/tyk-gateway/tyk-gateway.local.env
ExecStart=/bin/sh -c '/app/tyk-gateway/tyk --conf /app/tyk-gateway/tyk.conf >> /app/logs/tyk-gateway.
log 2>&1'
Restart=always
WorkingDirectory=/app/tyk-gateway
RuntimeDirectory=tyk
RuntimeDirectoryMode=0770

[Install]
WantedBy=multi-user.target
````
```

**# Для прикладных админов необходимо добавить строку в env на который ссылается сервис tyk-gateway**

**# LD\_LIBRARY\_PATH=\$LD\_LIBRARY\_PATH:/opt/itcs/lib (в /app/tyk-gateway/tyk-gateway.env)**

Создать unit `xmlv.service`

```
````shell
[Unit]
Description=XML Validation Service

[Service]
Type=simple
User=tyk
Group=tyk
ExecStart=/bin/sh -c '/app/xmlv/java/bin/java $JAVA_OPTS >> /app/logs/xmlv.log 2>&1'
EnvironmentFile=/app/xmlv/xmlv.env
WorkingDirectory=/app/xmlv
RuntimeDirectory=xmlv
```

RuntimeDirectoryMode=0770

Restart=always

[Install]

WantedBy=multi-user.target

...

Зарегистрировать новые сервисы

```shell

sudo systemctl daemon-reload

```

Предоставить доступ по ssh и sudo права для доменной группы IF-TYKI-ADMIN

ALL=(tyk) NOPASSWD: ALL

ALL=(ALL) NOPASSWD: /bin/systemctl start tyk-gateway

ALL=(ALL) NOPASSWD: /bin/systemctl stop tyk-gateway

ALL=(ALL) NOPASSWD: /bin/systemctl status tyk-gateway

ALL=(ALL) NOPASSWD: /bin/systemctl restart tyk-gateway

ALL=(ALL) NOPASSWD: /bin/systemctl reload tyk-gateway

ALL=(ALL) NOPASSWD: /bin/systemctl enable tyk-gateway

ALL=(ALL) NOPASSWD: /bin/systemctl disable tyk-gateway

ALL=(ALL) NOPASSWD: /bin/journalctl -u tyk-gateway

ALL=(ALL) NOPASSWD: /bin/systemctl start mdcb-proxy

ALL=(ALL) NOPASSWD: /bin/systemctl stop mdcb-proxy

ALL=(ALL) NOPASSWD: /bin/systemctl status mdcb-proxy

ALL=(ALL) NOPASSWD: /bin/systemctl restart mdcb-proxy

ALL=(ALL) NOPASSWD: /bin/systemctl enable mdcb-proxy

ALL=(ALL) NOPASSWD: /bin/systemctl disable mdcb-proxy

ALL=(ALL) NOPASSWD: /bin/journalctl -u mdcb-proxy

ALL=(ALL) NOPASSWD: /bin/systemctl start xmlv

ALL=(ALL) NOPASSWD: /bin/systemctl stop xmlv

ALL=(ALL) NOPASSWD: /bin/systemctl status xmlv

ALL=(ALL) NOPASSWD: /bin/systemctl restart xmlv

ALL=(ALL) NOPASSWD: /bin/systemctl enable xmlv

ALL=(ALL) NOPASSWD: /bin/systemctl disable xmlv

ALL=(ALL) NOPASSWD: /bin/journalctl -u xmlv

ALL=(fluentbit) NOPASSWD: ALL

ALL=(ALL) NOPASSWD: /bin/systemctl start fluentbit

ALL=(ALL) NOPASSWD: /bin/systemctl stop fluentbit

ALL=(ALL) NOPASSWD: /bin/systemctl restart fluentbit

ALL=(ALL) NOPASSWD: /bin/systemctl reload fluentbit

ALL=(ALL) NOPASSWD: /bin/systemctl status fluentbit

ALL=(ALL) NOPASSWD: /bin/systemctl enable fluentbit

ALL=(ALL) NOPASSWD: /bin/systemctl disable fluentbit

ALL=(ALL) NOPASSWD: /bin/journalctl -u fluentbit

выдается при использовании роли tyk-pump

ALL=(ALL) NOPASSWD: /bin/systemctl start tyk-pump

ALL=(ALL) NOPASSWD: /bin/systemctl stop tyk-pump

ALL=(ALL) NOPASSWD: /bin/systemctl status tyk-pump

ALL=(ALL) NOPASSWD: /bin/systemctl restart tyk-pump

```

ALL=(ALL) NOPASSWD: /bin/systemctl reload tyk-pump
ALL=(ALL) NOPASSWD: /bin/systemctl enable tyk-pump
ALL=(ALL) NOPASSWD: /bin/systemctl disable tyk-pump
ALL=(ALL) NOPASSWD: /bin/journalctl -u tyk-pump
ALL=(ALL) NOPASSWD: /bin/systemctl start mdcb-proxy
ALL=(ALL) NOPASSWD: /bin/systemctl stop mdcb-proxy
ALL=(ALL) NOPASSWD: /bin/systemctl status mdcb-proxy
ALL=(ALL) NOPASSWD: /bin/systemctl restart mdcb-proxy
ALL=(ALL) NOPASSWD: /bin/systemctl enable mdcb-proxy
ALL=(ALL) NOPASSWD: /bin/systemctl disable mdcb-proxy
ALL=(ALL) NOPASSWD: /bin/journalctl -u mdcb-proxy
ALL=(fluentbit) NOPASSWD: ALL
ALL=(ALL) NOPASSWD: /bin/systemctl start fluentbit
ALL=(ALL) NOPASSWD: /bin/systemctl stop fluentbit
ALL=(ALL) NOPASSWD: /bin/systemctl restart fluentbit
ALL=(ALL) NOPASSWD: /bin/systemctl reload fluentbit
ALL=(ALL) NOPASSWD: /bin/systemctl status fluentbit
ALL=(ALL) NOPASSWD: /bin/systemctl enable fluentbit
ALL=(ALL) NOPASSWD: /bin/systemctl disable fluentbit
ALL=(ALL) NOPASSWD: /bin/journalctl -u fluentbit

```

VIPNET OSSL

```

ALL=(ALL) NOPASSWD: /opt/itcs/bin/check_prg
ALL=(ALL) NOPASSWD: /opt/itcs/bin/itp11manager-1.1
ALL=(ALL) NOPASSWD: /opt/itcs/bin/ixs-tool
ALL=(ALL) NOPASSWD: /opt/itcs/bin/make_ext_crg
ALL=(ALL) NOPASSWD: /opt/itcs/bin/openssl-1.1
ALL=(ALL) NOPASSWD: /opt/itcs/bin/openssl_license-1.1
ALL=(ALL) NOPASSWD: /opt/itcs/bin/openssl_manager-1.1
ALL=(ALL) NOPASSWD: /opt/itcs/bin/token_manager
ALL=(ALL) NOPASSWD: /opt/itcs/bin/uprngctl # Fixed error (added l to the end of line)
ALL=(ALL) NOPASSWD: /opt/itcs/bin/uprngd
ALL=(ALL) NOPASSWD: /opt/itcs/bin/openssl_admin
ALL=(ALL) NOPASSWD: /opt/itcs/bin/openssl_manager

```

```

# Предоставить доступ по ssh и sudo права для доменной группы tyk-k3-admin@test.vtb.ru
%tyk-k3-admin@test.vtb.ru ALL=(tyk) NOPASSWD: ALL

```

```

# Предоставить доступ по ssh для доменной группы Аудиторов TEST\IF-TYKI-AUDIT
%IF-TYKI-AUDIT@test.vtb.ru ALL=(auditor) NOPASSWD: ALL

```

```

# Предоставить доступ по ssh для доменной группы Аудиторов ИБ TEST\IF-TYKI-AUDIT-IB
%IF-TYKI-AUDIT-IB@test.vtb.ru ALL=(auditor) NOPASSWD: ALL
```

```

#### ### Изменить параметры ядра Linux

```

```shell
net.core.netdev_max_backlog=261144
net.core.default_qdisc = fq
net.core.rmem_max=67108864
net.core.somaxconn=65535

```

```
net.ipv4.tcp_wmem=8192 131072 67108864
net.ipv4.ip_local_port_range=1024 65535
net.ipv4.tcp_slow_start_after_idle=0
net.ipv4.tcp_max_syn_backlog=8192
net.ipv4.tcp_keepalive_time=1800
net.ipv4.tcp_keepalive_intvl=15
net.ipv4.tcp_keepalive_probes=5
net.ipv4.tcp_no_metrics_save=1
net.ipv4.tcp_synack_retries=2
net.ipv4.tcp_tw_reuse=1
fs.file-max=2345257
net.ipv4.tcp_low_latency=1
net.core.rmem_default=212992
net.core.wmem_default=212992
net.core.wmem_max=67108864
net.ipv4.udp_rmem_min=16384
net.ipv4.udp_wmem_min=16384
net.ipv4.tcp_rmem=8192 174760 67108864
net.ipv4.tcp_mem=1048576 4194304 67108864
net.ipv4.udp_mem=2097152 8388608 67108864
kernel.pid_max=4194303
kernel.sched_autogroup_enabled=0
vm.dirty_background_ratio=2
vm.dirty_ratio=10
vm.swappiness=0
``
```