# PoCSD In-memory file system Code overview

#### Overview

- The in-memory file system is used as a basis for various assignments used in class
- The code implements, in memory, a file system inspired by the design in Chapter 2 of the textbook
- You will progressively add complexity to this design to capture, in practice, concepts that we discuss in class

#### Code overview

- The code is written in Python, and maintains data structures that store information and expose methods to perform various functions across the layers of file system
- The data structures are abstracted as classes with methods that implement the majority of the "heavy lifting code" necessary to manipulate them
- This presentation overviews the major data structures and methods, in a "bottom-up" fashion – from the "raw" block layer up

#### Overall code structure and Python files

- fsconfig.py various file system configurations (you won't change)
- fsmain.py command-line argument parsing and initialization
- shell.py interactive command shell for file system operations
- fileoperations.py file operations: create, write, read, ...
- absolutepath.py absolute path layer; from path to inode number
- filename.py Lookup() and helper functions (you won't change)
- inodenumber.py inode number layer (you won't change)
- inode.py inode layer (you won't change)
- block.py raw block layer

## Layering on textbook's discussion

	Layer	Purpose		
HW3	Symbolic link	Integrate multiple file systems	User-oriented names	
absolutepathname.py	Absolute path name layer	Provide a root for naming hierarchies		
	Path name layer	Organize files into naming hierarchies		
filename.py	File name layer	Human-oriented names	User/machine Interface	
inodenumber.py ——	Inode number layer	Machine-oriented names	Machine- oriented names	
inode.py ——	File layer	Organize blocks into files		
block.py ——	Block layer	Identify disk blocks		

#### General approach

shell.py
(called by fsmain.py)

% ls % cat file.txt block.py

DiskBlocks()

•••

Layers above: fileoperations.py

filename.py inode.py

absolutepath.py

inodenumber.py



DiskBlocks class implements in-memory storage of "raw" block layer

LoadFromDump()

DumpToDisk()



interactive
UNIX-like
file system
commands
for data stored
in block.py



This allows save/restore of DiskBlocks raw block layer to files in your computer (persist across program runs)

Your computer's file system dump1\_bs\_256\_nb\_.....dump dump2\_bs\_512\_nb\_.....dump


#### DiskBlocks()

- This class stores the raw block array
- The blocks are used to store file system data and metadata
  - Boot block normally this would store boot code; it's unused in our class
  - Superblock() stores file system constants
  - Bitmap for free blocks: stores an array of bytes, one byte per block, which determines if the block is free (0) or used (1)
  - Inode table: stores a table of inodes
  - File blocks: store file system object data (file contents, directory entries)

0	1	•••				n-1	
Boot block	Super block	Bitmap for free blocks	Inode table	File block	•••	File block	


#### DiskBlocks()

- File system constants are declared at the beginning of memoryfs.py
  - BLOCK\_SIZE (Bytes), TOTAL\_NUM\_BLOCKS, MAX\_NUM\_INODES, and INODE\_SIZE (the size of each inode, in Bytes)
  - Additional constants used in the code are derived from them, such as:




#### DiskBlocks() – encoding inodes

- Note: to simplify programming and readability, the following constants used for the inode data structure cannot be changed:
  - 4 Bytes are used to store size (hence maximum file size cannot exceed 4GB)
  - 2 Bytes are used to store type (plenty; we only have a handful of types)
  - 2 Bytes for refcnt (hence a file has at most 65535 references)
  - 4 Bytes for each index in block\_numbers (hence at most 2^32 blocks)




#### DiskBlocks() – encoding directory entries

- Each data block storing directory entries is structured as follows:
  - MAX\_FILENAME determines the max size (characters) of an object's name
  - INODE\_NUMBER\_DIRENTRY\_SIZE determines the size of an inode number
  - By default, MAX\_FILENAME=12 and INODE\_NUMBER\_DIRENTRY\_SIZE=4
    - Hence, each (name, inode) mapping uses 16 Bytes
    - With default block size 128 Bytes, there are up to 8 directory entries per datablock



#### DiskBlocks() – encoding directory entries

- The file name can have any characters, except "/"
  - The code doesn't enforce for encoding
- Unused file name bytes are filled with zeroes ('\x00' in hex)
  - A file name that is all zeroes means that the entry is free
- Inode numbers are encoded as big-endian
- In the example below, we see "myfile" maps to inode number 5 linede number



#### DiskBlocks()

- The key methods exposed by DiskBlocks() are:
  - Put(block\_number, block\_data)
    - Writes raw data block indexed by block number
    - Data block must be a byte array of up to BLOCK\_SIZE length
      - If it is smaller than BLOCK\_SIZE, Put() pads it with zeroes up to BLOCK\_SIZE
    - Number must be between 0..TOTAL\_NUM\_BLOCKS-1

bBlock\_data = Get(block\_number)

- Reads from raw block storage indexed by block number
- block\_data is a bytearray; block\_number an integer
- DiskBlocks() is an in-memory class; two methods are exposed to "dump" the entire raw block storage to disk, and to read from disk
  - This is useful to save/restore the file system state between invocations of memory.py
  - DumpToDisk() and LoadFromDump() use Python's "pickle" to serialize the object

#### DiskBlocks()

- DiskBlocks() constructor:
  - This method initializes the raw block storage in memory with zeroes
- LoadFromDump(self, filename):
  - This method initializes the raw block storage in memory <u>from a file</u>
    - You will be given examples of "dump files" in HW#1
    - You can create your own "dump files" to checkpoint block storage to disk see below
- DumpToDisk(self, filename):
  - This method <u>creates a dump file</u> from the raw block contents in memory

#### Visualizing data in DiskBlocks()


- The file system shell has debugging commands to help you visualize raw block data (and inode info), and get yourself acquainted with how data is stored in blocks:
  - load dumpfile, save dumpfile : load or save dumpfile in disk
  - showfsconfig: displays FS configuration, number of blocks, block size, number of inodes, inode size
  - showblock blockno: displays the contents of raw block number "blockno"
  - showblockslice blockno start end: displays a slice of the contents of raw block number "blockno", in hexadecimal format, from byte "start" to byte "end", including byte "end"
  - showinode inodeno: displays the inode data structure for inode number "inodeno"

## Inode()

- This class represents an inode in memory
  - Its type, size, reference count, and array of block\_numbers[]
  - The types supported in the version you start from are:
    - INODE TYPE INVALID
    - INODE TYPE FILE
    - INODE\_TYPE\_DIR
- Inodes are initialized as INVALID, size 0, refcnt 0, block\_numbers[] as an array of zeroes

## Inode()


- Helper functions extract/insert inode class from raw block storage
  - InodeFromByteArray(b)
    - This method loads an inode's type, size, refcnt, block\_numbers[] from a byte array with INODE\_SIZE bytes
  - InodeToBytearray()
    - This method returns a byte array encoding the inode's information
- Print() prints out inode info to log file refert
   size type block\_numbers[0]




#### InodeNumber()

- This class exposes methods that use numbers to identify an inode
  - It holds an Inode() object, the inode's number
  - You need to initialize it with a number, and the object holding disk blocks
- InodeNumberToInode()
  - Load inode structure from raw block storage, given its number
- StoreInode()
  - Store inode structure in raw block storage, given its number
- InodeNumberToBlock(offset)
  - Returns a block of data from raw storage, given its offset; equivalent to textbook's INODE\_NUMBER\_TO\_BLOCK


- This class exposes methods at the file layer
  - You need to initialize it with the object holding disk blocks
- HelperGetFilenameString(block, index)
  - Extract MAX\_FILENAME-size string from bytearray block, using index
  - E.g. with block below, index 0 returns "myfileA", index 1 returns "myfileB"
    - Padded to the right with "\x00"



- HelperGetFilenameInodeNumber(block, index)
  - Extract INODE\_NUMBER\_DIRENTRY\_SIZE int from block, using index
  - E.g. with block below, index 0 returns 5, index 1 returns 6




- InsertFilenameInodeNumber(insert\_to, filename, inodenumber)
  - Inserts a (filename,inodenumber) entry to a directory's data block
  - insert\_to is an InodeNumber() object the inode number of the directory that we're inserting this entry
  - This adds an entry to the end of the table (starting from inode.size)
    - Allocates a new block and add to block\_numbers[] if needed
    - E.g. the state below would be after Insert(i,"myfileA",5) followed by Insert(i,"myfileB",6) filename inode number



- FindAvailableInode()
  - Scans inode table to find a free inode
  - Used when allocating a new inode as part of Create()
  - An inode is free if its type is INODE\_TYPE\_INVALID
- FindAvailableFileEntry(dir)
  - Finds next available block in a directory's block\_numbers[] array
    - If inode reached maximum size, returns error
  - Used when allocating a new data block for a directory as part of Create()
- AllocateDataBlock()
  - Allocates a new data block from free list; if there is a free block available, update free bitmap, and returns block number
- InsertFilenameInodeNumber():
  - Insert (name, inode) binding to directory table

- Lookup(filename, dir)
  - Looks up a file object in a directory as in the book's LOOKUP
  - dir is an inode number, filename is a string
  - Example, Lookup("myfileA",0) would return 5 for the example below, assuming this is one of the data blocks indexed in the root directory (inode number 0)



- InitRootInode()
  - Initializes root inode (inode number 0), and writes to block storage
  - Also inserts "." directory entry
- Create(dir, name, type)
  - Create a file system object of given type, in given directory, with given name
    - Allocates a new inode for the object
    - Adds (name,inode\_number) to dir's entry, allocating new block if needed
    - If type is INODE\_TYPE\_DIR
      - Allocate data block for new directory, and insert "." and ".." entries
    - If type is INODE\_TYPE\_FILE
      - Create empty file, with size 0 no data blocks are allocated yet
  - Returns the new object's inode number

#### FileOperations()

- Create(dir, name, type)
  - Create a file system object of given type, in given directory, with given name
    - Allocates a new inode for the object
    - Adds (name,inode\_number) to dir's entry, allocating new block if needed
    - If type is INODE\_TYPE\_DIR
      - Allocate data block for new directory, and insert "." and ".." entries
    - If type is INODE\_TYPE\_FILE
      - Create empty file, with size 0 no data blocks are allocated yet
  - Returns the new object's inode number

#### FileOperations()

- Write(file\_inode\_number, offset, data)
  - Writes bytearray "data" into file given its inode number, starting at offset
  - file\_inode\_number must index an inode of type INODE\_TYPE\_FILE
  - offset can point to anywhere within the file, and data can be smaller or larger than BLOCK\_SIZE, but:
    - offset cannot be larger than file's size
    - offset + len(data) cannot exceed MAX\_FILE\_SIZE
  - This method allocates data blocks as needed to accommodate data
  - Partial writes (smaller than a block) only change the bytes to be written
    - The block is first read from raw storage
  - Returns the number of bytes written