Bansilal Ramnath Agarwal Charitable Trust's

Vishwakarma Institute of Technology, Pune-37

(An autonomous Institute of Savitribai Phule Pune University)



Department Of Computer Engineering Lab Manual

Course Code	Course Name	Teaching Scheme (Hrs. / Week)	Credits
CS30303	Operating System Lab	2	1

Course Outcomes:

- 1. Identify the mechanisms and strategies of an Operating System in order to solve real world problems.
- 2. Develop solutions based on Operating system concepts in various contexts.
- 3. Automate the administrative tasks by means of modern tools in Operating System.
- 4. Examine the functions of a contemporary Operating system with respect to convenience, efficiency and the ability to evolve
- 5. Engage in a team towards development of a prototype Operating System.
- 6. Construct solutions to real world problems by applying the standard techniques used by Operating Systems for similar issues.

Class: - TY Branch: - Computer Engineering

Year: -2016-17 Prepared By: - Mrs. Aparna R. Sawant

Required H/W and S/W : C, C++, JAVA Linux /Win XP

with P-IV 128 MB RAM

INDEX

Sr.	Title of Experiments	Page No
No.		
	Implementation of a multiprogramming	
	operating system	
	Introduction	3-12
1	Stage I:	13-15
	i. CPU/ Machine Simulation	
	ii. Supervisor Call through interrupt	
2	Stage II:	16-19
	i. Paging	
	ii. Error Handling	
	iii. Interrupt Generation and Servicing	
	iv. Process Data Structure	
3	Stage III:	20-27
	i. Multiprogramming	
	ii. Virtual Memory	
	iii. Process Scheduling and Synchronization	
	iv. Inter-Process Communication	
	v. I/O Handling, Spooling and Buffering	
	Final Version	28-38

INTORODUCTION OF PROJECT

Outcomes:

- Understand all general concept of Multiprogramming Operating System.
- Understand How to write assembly program to execute on multiprogramming operating system.

Al. INTRODUCTION

The appendix describes a tractable project involving the design and implementation of a multiprogramming operating system (MOS) for a hypothetical computer configuration that can be easily simulated (Shaw and Weiderman, 1971). The purpose is to consolidate and apply, in an almost realistic setting, some of the concepts and techniques discussed in this book. In particular, the MOS designer/implementer must deal directly with problems of input-output, interrupt handling, process synchronization, scheduling, main and auxiliary storage management, process and resource data structures, and systems organization.

We assume that the project will be coded for a large central computer facility (The "host" system) which, on the one hand, does not allow users to tamper with the operating system or the machine resources but on the other hand, does provide a complete set of services, including filing services, debugging aids, and a good higher-level language. The global strategy is to simulate the hypothetical computer on the host and writes the MOS for this simulated machine. The MOS and simulator will consist of approximately 1000 to 1200 cards of program, with most of the code representing the MOS. The project can be completed over a period of about two months by students concurrently taking a normal academic load.

The characteristics and components of the MOS computer are specified in the next section. Section A3 outlines the format of user jobs. The path of a user job through the system, and the functions and main components of the MOS are described in Section A4. The following section (A5) then lists the detailed requirements for the project. In the final Sec. A6, some limitations of the project are described.

A2. MACHINE SPECIFICATIONS

The MOS computer is described from two points of view: the "virtual" machine seen by the typical user and the "real" machine used by the MOS designer/implementer.

1. The Virtual Machine:

The virtual machine viewed by a normal user is illustrated in Fig. A-1. Storage consists of a maximum of 100 words, addressed from 00 to 99; each word is divided into four one-byte units, where a byte may contain any character acceptable by the host machine. The CPU has three registers of interest: a four-byte general register R. a one-byte Boolean" toggle C, which may contain either 'T' (true) or 'F' (false), and a two-byte instruction counter IC.




Fig A-1: Virtual user machine.

A storage word may be interpreted as an instruction or data word. The operation code of an instruction occupies the two high-order bytes of the word, and the operand address appears in the two low-order bytes. Table A-I gives the format and interpretation of each instruction. Note that the input instruction (*GD*) reads only the first 40 columns of a card and that the output instruction (*PD*) prints a new line of 40 characters. The first instruction of a program must always appeal in location 00. With this simple machine, a batch of compute-bound, IO-bound, and balanced programs can be quickly written. The usual kinds of programming errors are also almost guaranteed to be made. (Both these characteristics are desirable, since the MOS should be able to handle a variety of jobs and user errors.)

Instruction		
		Interpretation
Operator	Operand	
LR	x1,x2	R:=[α]
SR	x1,x2	α: =R
CR	x1,x2	If R: = $[\alpha]$ then C:='T'
		else C:='F'
BT	x1,x2	If C='T' then IC:= α
GD	x1,x2	Read([β+i],i=09)
PD	x1,x2	Write([β+i],i=09)
Н		halt

Table A-1 Instruction Set of Virtual Machine

2. The Real Machine

(a) Components

Figure A-2 contains a schematic of the real machine. The CPU may operate in either a *master* or a *slave* mode. In master mode, instructions from supervisor storage are directly processed by the higher-level language processor (HLP); in slave mode, the HLP interprets a 'micro program" in the read-only memory which simulates (emulates) the CPU of the virtual machine and accesses virtual machine programs in user storage via a paging mechanism. The HLP is any convenient and available higher-level language. (This organization allows the virtual machine emulator and the MOS to be coded in a higher-level language available on the host system, while maintaining some correspondence with real computers.)




Fig A-2: Real Machine

The CPU registers of interest are:

C: a one-byte "Boolean&' toggle,

R: a four-byte general register,

IC: a two-byte virtual machine location counter,

PI, SI, IOI, TI: four interrupt registers,

PTR: a four-byte page table register,

CHST[i], i = 1, 2, 3: three channel status registers, and

MODE: mode of CPU, master' or 'slave'.

User storage contains 300 four-byte words, addressed from 000 to 299. It is divided into 30 tenword blocks for paging purposes. Supervisor storage is loosely defined as that amount of storage required for the MOS.

Auxiliary storage is a high-speed drum of 100 tracks, with 10 four-byte words per track. A transfer of 10 words to or from a track takes one time unit. (Rotational delay time is ignored.) The card reader and line printer both operate at the rate of three time units for the 10 of one record. These devices have the same characteristics as the virtual machine devices; i.e., 40 bytes (10 words) of information are transferred from the first 40 card columns or to the first 40 print positions on a read or write operation, respectively.

Channels 1 and 2 are connected from peripheral devices to supervisor storage, while channel 3 is connected between auxiliary storage and both supervisor and user memory.

(b) Slave Mode Operation

User storage addressing while in slave mode is accomplished through paging hardware. The PTR register contains the length and page table base location for the user process currently running. The four bytes a0 a1 a2, a3, in the PTR have this interpretation: a1 is the page table length minus 1, and 10a2, + a3, is the number of the user storage block in which the page table resides, where a1, a2, and a3 are digits.

A two-digit instruction or operand address, x1 x2, in virtual space is mapped by the relocation hardware into the real user storage address:

$$10 [10 (10a2, +a3) + x1] + x2$$

Where (α) means "the contents of address" and it is assumed that $x1 \le a1$.

All pages of a process are required to be loaded into user storage prior to execution. It is assumed that each virtual machine instruction is emulated in one time unit. All interrupts occurring during

slave mode operation are honored at the end of instruction cycles and cause a switch to master mode. The operations GD, PD, and H result in supervisor-type interrupt that is, "supervisor calls." A program-type interrupt is triggered if the emulator receives an invalid operation code or if x1, > a1, during the relocation map (invalid virtual space address).

(c) Master Mode Operation

Master mode programs residing in supervisor storage have access to user storage and the CPU registers. The CPU is *not* interruptible in master mode however; an appropriate interrupt register is set when an interrupt-causing event (timer or IO) occurs. The interrupt registers may be interrogated and reset by the instruction Test(x), which returns a value and has the effect:

if x = 1 then begin Test := IOI; IOI := 0 end else

if x = 2 then begin Test := PI; PI = 0 end else

if x = 3 then begin Test := SI; SI := 0 end else

if x = 4 then begin Test := TI; TI := 0 end else

if (IOI + P1 + SI + TI) > 0 then Test:= 1 else Test := 0;

All users IO is performed in master mode. An IO operation is initiated by the instruction

StartIO(Ch, S. D, n);

Where Ch is the channel number, S is an array of source blocks (IO word units), D is an array of destination blocks, and n is the number of blocks to be transmitted. If a StartIO is issued on a busy channel, the CPU idles in a wait state until the channel is free, whereupon the StartIO is accepted. (Issuing a StartIO on a busy channel is generally not advisable.) The status of any channel may be determined by examining the channel status registers CHST; CHST ([i] = 1 if channel i is busy and CHST[i] = 0 when channel i is free (i=1, 2, 3).

To switch back to slave mode, the instruction

Slave(ptr, c, r, Ic)

is issued. *Slave* sets *PTR* to *ptr*, *C* to *c*, *R* to *r*, *IC* to *ic*, and then switches to slave mode, at the start of the emulator execution cycle.

Master mode instructions are normally executed in *zero* time units. However, it is occasionally necessary to force the CPU to wait for some specified time interval before continuing. This occurs implicitly when a *StartIO* on a busy channel is issued. An explicit wait is affected by the instruction

Superwait(t));

This causes the CPU to idle in a wait state for t unit of time.

(d) Channels

When a *StartIO* is accepted by the addressed channel I, *CHST[i]* is set to 1 (busy), and the IO transmission occurs completely in parallel with continued CPU activity, at the completion of the IO, *CFIST[i]* is set to 0 and an *IO Interrupt* signal is raised.

(e) Timer

The timer hardware decrements supervisor storage location TM by 1 at the end of every 10 time units of CPU operation. A timer interrupt occurs whenever TM decremented to zero; the time continues decrementing at the same rate so that TM may also have negative values. TM may be set and interrogated in master mode.

(f) Interrupts

Four types of interrupts are possible:

- (1) Program: Protection (page table length), invalid operation code
- (2) Supervisor: GD, PD, H.
- (3) IO: Completion interrupts
- (4) Timer: Decrement to zero

The events causing interrupts of types (1) and (2) can happen only in slave mode; events of type (3) and (4) can occur in both master and slave mode, and several of these events may happen simultaneously. The interrupt causing event is recorded in the interrupt registers regard less of whether the interrupt are inhibited (master mode) or enabled slave mode.

The interrupt register are set by an interrupt event to the following values:

- (1) PI= 1: Protection; P1= 2: invalid operation code
- (2) SI = 1: GD; SI = 2: PD; SI = 3: H
- (3) IOI = 1: Channel 1; IOI = 2: Channel 2; IOI = 4: Channel 3; if several IO completion interrupts are raised simultaneously, the values are summed; for example. IOI = 6 indicates that both channel 2 and channel 3 completion interrupts are raised.
- (4) TI = 1: Timer

The following code describes the *hardware* actions on an interrupt in slave mode:

Comment Save state of slave process in supervisor storage locations c, r, and ic;

$$c: =C; r: =R; ic: = IC;$$

Comment Switch to master mode;

MODE := 'master'

Comment Determine cause of interrupt and transfer control;

if IOI != 0 then go to IOIint else

if P1 != 0 then go to PROGint else

if SI != 0 then go to SUPint else

go to T1Mint;

Comment IOIint, PROGint, SUPint, and TIMint are supervisor storage locations;

Note that the order of interrupt register testing implies a hardware priority scheme; this can be easily changed by master mode software.

A3. JOB, PROGRAM AND DATA CARD FORMATS

A user job is submitted as a deck of control, program, and data cards in the order:

<JOB card>, <Program>, <DATA card>, <Data>, <ENDJOB card>.

- 1. The *<JOB cord>* contains four entries:
 - (1) \$AMJ cc. 1-4, A Multiprogramming Job
 - (2) < job Id> cc. 5—8, a unique 4-character job identifier.
 - (3) *<time estimate>* cc. 9—12, 4-digit maximum time estimate.
 - (4) *line estimate>* cc. 13—16, 4-digit maximum output estimate.
- 2. Each card of the *Program>* deck contains information in card columns 1-40. The ith card contains the initial contents of user virtual memory locations.

$$10(i-1)$$
, $10(I-1) + 1$, ..., $10(I-1) + 9$, $i = 1, 2, ..., n$,

Where n is the number of cards in the $\langle Program \rangle$ deck. Each word may contain a VM instruction or four bytes of data. The number of cards n in the program deck defines the size of the user space; i.e., n cards define 10 X n words, n 10.

- 3. The *<DATA card>* has the format: The *(Data)* deck contains information in cc. 1—40 and is the user data retrieved by the VM *GD* instructions.
- 5. The (JOB card) has the format: SEND cc. 1-4

The *<DATA card>* is omitted if there are no *<Data>* cards in a job.

A4. THE OPERATING SYSTEM

The primary purpose of the MOS is to process a batched stream of user jobs efficiently. This is accomplished by multiprogramming systems and user processes.

A job *J* will pass sequentially through the following phases:

- 1. *Input Spooling. J* enters from the card reader and is transferred to the drum.
- 2. *Main Processing*. The program part of J is loaded from the drum into user storage.

J is then ready to run and becomes a process j. Until j terminates, either normally or as a result of an error, its status will generally switch many times among:

- (a) Ready-waiting for the CPU.
- (b) Running-executing on the CPU.
- (c) Blocked-waiting for completion of an input-output request. Input-output requests are translated by the MOS into drum input-output operations.
- 3. *Output Spooling. J's* Output, including charges, systems messages, and his original program, is printed from the drum.

In general, many jobs will simultaneously be in the main processing phase, The MOS is to be documented and programmed as a set of interacting processes. A typical design might have the following major processes:

Reading Cards: Read cards into supervisor storage.

Job to Drum: Create a job descriptor and transfer a job to the drum

Loader: Load job into user storage

Get- Put-Data: Process VM input-output instructions.

Line -from- Drum: Read output lines from drum into supervisor storage.

Print - Lines: Write output lines on the printer.

The operating system is normally activated by slave mode operation. The interrupt handling routines will typically call the process scheduler (CPU allocator) after they service an interrupt.

A major task of the MOS is the management of hardware and software resources. These include user storage, drum storage, channel 3, software *buffers*, job descriptors, and the *CPU*. The MOS is also responsible for maintaining statistics on hardware utilization and job characteristics. The following statistics are computed from software measurements:

- 1. *Resource Utilization*. Fraction of total time that each channel is busy, fraction of total time that the CPU is busy (in slave mode), mean user storage utilization and mean drum utilization.
- 2. *Job Characteristics*. Mean run time (**on** VM), mean time in system, mean user storage required, mean input length, and mean output length.

These statistics are to be printed at the end of a run.

A5. PROJECT REQUIREMENTS

Three sets of program modules must be designed and implemented:

- 1. Major simulators for hardware, including the interrupt system, timer, channels, reader, printer, auxiliary storage, user storage, and the slave mode paging system. (The HLP and supervisor storage is assumed available directly from the host system.)
- 2. The "micro-program" that emulates the VM.
- 3. The MOS.

These three parts should be clearly and cleanly separated. It should not be difficult to change the size and time parameters of the hardware, specifically drum and user storage size, 10 times, instruction times, and the timer "frequency."

Students should work in small teams of two or three, each team doing the complete project. Several weeks after the project is assigned, a complete design of the MOS as a set of interacting processes is submitted. The design includes a description of the major processes *in* the system and how they interact, the methods to be used for the allocation and administration of each resource, and the identification and contents of the main data structures.

A batch stream of about 60 jobs (a "run") should be prepared for testing purposes.

A6. SOME LIMITATIONS

The MOS and machine deviate from reality in simplifying some features of real systems and omitting others. Significant features that are lacking include: a more general virtual machine that would permit multistep jobs and the use of language translators, a system to organize and handle a loader variety of data files, an operator communication facility, and master mode operation of the CPU in nonzero time. The project specifications could be expanded in some of the above directions, but there appears o be an unacceptable overhead in doing so. Instead, similar tractable case studies emphasizing other aspects of operating systems, such as file systems or timesharing, should be designed.

Experiment No: 1

Title: Implementation of a multiprogramming operating system

Problem Statement: Stage I:

i. CPU/ Machine Simulation

ii. Supervisor Call through interrupt

Description:

Assumption:

- Jobs entered without error in input file
- No physical separation between jobs
- Job outputs separated in output file by 2 blank lines
- Program loaded in memory starting at location 00
- No multiprogramming, load and run one program at a time
- SI interrupt for service request

Notation:

M: memory; IR: Instruction Register (4 bytes)

IR [1, 2]: Bytes 1, 2 of IR/Operation Code

IR [3, 4]: Bytes 3, 4 of IR/Operand Address

M[&]: Content of memory location &

IC: Instruction Counter Register (2 bytes)

R: General Purpose Register (4 bytes)

C: Toggle (1 byte)

: Loaded/stored/placed into

MOS (MASTER MODE)

SI = 3 (Initialization)

Case SI of

- 1: Read
- 2: Write
- 3: Terminate

Endcase

READ:

IR $[4] \leftarrow 0$

Read next (data) card from input file in memory locations IR [3,4] through IR [3,4] +9

If M [IR [3,4]] = \$END, abort (out-of-data)

EXECUTEUSERPROGRAM

WRITE:

IR $[4] \leftarrow 0$

Write one block (10 words of memory) from memory locations IR [3,4] through IR [3,4] + 9 to output file

EXECUTEUSERPROGRAM

TERMINATE:

Write 2 blank lines in output file

MOS/LOAD

LOAD:

 $m \leftarrow 0$

While not e-o-f

Read next (program or control) card from input file in a buffer

Control card: \$AMJ, end-while

\$DTA, MOS/STARTEXECUTION

\$END, end-while

Program Card: If m = 100, abort (memory exceeded)

Store buffer in memory locations m through m + 9

 $m \leftarrow m + 10$

End-While

STOP

MOS/STARTEXECUTION

 $IC \leftarrow 00$

EXECUTEUSERPROGRAM

EXECUTEUSERPROGRAM (SLAVE MODE)

Loop

 $IR \leftarrow M [IC]$

 $IC \leftarrow IC+1$

Examine IR[1,2]

LR: $R \leftarrow M [IR[3,4]]$

SR: $R \rightarrow M [IR[3,4]]$

CR: Compare R and M [IR[3,4]]

If equal $C \leftarrow T$ else $C \leftarrow F$

BT: If C = T then $IC \leftarrow IR$ [3,4]

GD: SI = 1

PD: SI = 2

H: SI = 3

End-Examine

End-Loop

Question Bank:

- 1. What is use of different registers?
- 2. What is significance of SI?
- 3. When SI would set to 1/2/3?
- 4. What is Interrupt?
- 5. What is system call?

Experiment No: 2

Title: Implementation of a multiprogramming operating system

Problem Statement: Stage II:

- i. Paging
- ii. Error Handling
- iii. Interrupt Generation and Servicing
- iv. Process Data Structure

Description:

Assumption:

- Jobs may have program errors
- PI interrupt for program errors introduced
- No physical separation between jobs
- Job outputs separated in output file by 2 blank lines
- Paging introduced, page table stored in real memory
- Program pages allocated one of 30 memory block using random number generator
- Load and run one program at a time
- Time limit, line limit, out-of-data errors introduced
- TI interrupt for time-out error introduced
- 2-line messages printed at termination

Notation:

M: memory

IR: Instruction Register (4 bytes)

IR [1, 2]: Bytes 1, 2 of IR/Operation CodeIR [3, 4]: Bytes 3, 4 of IR/Operand AddressM[&]: Content of memory location &

IC: Instruction Counter Register (2 bytes)R: General Purpose Register (4 bytes)

C: Toggle (1 byte)

PTR: Page Table Register (4 bytes)

PCB: Process Control Block (data structure)

VA: Virtual Address RA: Real Address

TTC: Total Time Counter
LLC: Line Limit Counter
TTL: Total Time Limit
TLL: Total Line Limit
EM: Error Message

←: Loaded/stored/placed into

Interrupt values:

SI = 1 on GD

= 2 on PD

= 3 on H

TI = 2 on Time Limit Exceeded

PI = 1 Operation Error

= 2 Operand Error

= 3 Page Fault

Error Message Coding

EM	Error
0	No Error
1	Out of Data
2	Line Limit Exceeded
3	Time Limit Exceeded
4	Operation Code Error
5	Operand Error
6	Invalid Page Fault

BEGIN

INITIALIZATION

SI = 3, TI = 0

MOS (MASTER MODE)

Case TI and SI of

TI	SI	Action
0	1	READ
0	2	WRITE
0	3	TERMINATE (0)
2	1	TERMINATE (3)
2	2	WRITE, THEN TERMINATE (3)
2	3	TERMINATE (0)

Case TI and PI of

TI	PI	Action
0	1	TERMINATE (4)
0	2	TERMINATE (5)
0	3	If Page Fault Valid, ALLOCATE, update page Table, Adjust IC if necessary, EXECUTE USER PROGRAM Otherwise TERMINATE (6)
2	1	TERMINATE (3,4)
2	2	TERMINATE (3,5)
2	3	TERMINATE (3)

```
READ:
```

If next data card is \$END, TERMINATE (1)

Read next (data) card from input file in memory locations RA through RA + 9

EXECUTEUSERPROGRAM

WRITE:

 $LLC \leftarrow LLC + 1$

If LLC > TLL, TERMINATE (2)

Write one block of memory from locations RA through RA + 9 to output file

EXECUTEUSERPROGRAM

TERMINATE (EM):

Write 2 blank lines in output file

Write 2 lines of appropriate Terminating Message as indicated by EM

LOAD

LOAD:

While not e-o-f

Read next (program or control) card from input file in a buffer

Control card: \$AMJ, create and initialize PCB

ALLOCATE (Get Frame for Page Table)

Initialize Page Table and PTR

Endwhile

\$DTA, STARTEXECUTION

\$END, end-while

Program Card: ALLOCATE (Get Frame for Program Page)

Update Page Table

Load Program Page in Allocated Frame

End-While

End-While

STOP

STARTEXECUTION:

 $IC \leftarrow 00$

EXECUTEUSERPROGRAM

END (MOS)

EXECUTEUSERPROGRAM (SLAVE MODE):

ADDRESS MAP (VA, RA)

Accepts VA, either computes & returns RA or sets PI \leftarrow 2 (Operand Error) or PI \leftarrow 3 (Page Fault)

```
LOOP
```

ADDRESSMAP (IC, RA)
If PI \neq 0, End-LOOP (F)
IR \leftarrow M[RA]
IC \leftarrow IC+1
ADDRESSMAP (IR[3,4], RA)
If PI \neq 0, End-LOOP (E)
Examine IR[1,2]

LR: $R \leftarrow M [RA]$ SR: $R \rightarrow M [RA]$

CR: Compare R and M [RA]

If equal $C \leftarrow T$ else $C \leftarrow F$

BT: If C = T then $IC \leftarrow IR$ [3,4]

GD: SI = 1 (Input Request)
PD: SI = 2 (Output Request)
H: SI = 3 (Terminate Request)

Otherwise PI \leftarrow 1 (Operation Error)

End-Examine

End-LOOP (X) X = F (Fetch) or E (Execute)

SIMULATION:

Increment TTC
If TTC = TTL then TI \leftarrow 2

If SI or PI or $TI \neq 0$ then Master Mode, Else Slave Mode

Question Bank:

- 1. What is significance of PI?
- 2. What is use of PTR?
- 3. What PCB contains?
- 4. What different errors may occur in a job?
- 5. When TI would set to 1/2?
- 6. What is a difference between relative ,absolute and logical address?

Experiment No: 3

Title: Implementation of a multiprogramming operating system

Problem Statement: Stage III:

- i. Multiprogramming
- ii. Virtual Memory
- iii. Process Scheduling and Synchronization
- iv. Inter-Process Communication
- v. I/O Handling, Spooling and Buffering

Description:

Assumption:

- Multiprogramming and virtual memory added
- TI "time slice out" interrupt introduced
- Paging retained without even-odd restrictions
- I/O Processing through 3 channels introduced
- Spooling and buffering for I/O through channels introduced
- Drum (secondary storage) introduced
- I/O interrupt introduced

Notations (Added):

- TS: Time Slice
- TSC: Time Slice Counter
- CHi: Channel i i = 1, 2, 3
- RD: Read
- WT: Write
- IS: Input Spool
- OS: Ouput Spool
- LD: Load
- SWP: Swap
- eb(q): Empty buffer (queue)
- ifb(q): Inputful buffer (queue)
- ofb(q): Outputful buffer (queue)
- LQ: Load queue
- RQ: Ready queue
- SQ: Swap queue
- IOQ: Input-Output (read/write) queue
- TQ: Terminate (output spool) queue
- IRi: Interrupt Routine for channel i i = 1, 2, or 3

SPOOLING AND BUFFERING INFO:

- Buffer Pool: 3 Types: Empty, Inputful, Outputful
- Channels: 3

Channel 1: Cardreader to Supervisor Memory

Channel 3: Supervisor Memory and Drum (either way)

Channel 2: Supervisor Memory to Printer

- Spooling: Input and Output
 - (a) Input (Before Execution): Program and data cards transferred from Card Reader to Drum

Performed by Channels 1 and 3

Channel 1:

Started with an Empty buffer

Fills it with the next card from card reader

Returns Inputful buffer

Channel 3:

Started with the next Inputful buffer, and an available drum track

Writes the buffer to the drum track

Returns an Empty buffer

OUTPUT (After the program has terminated)

Output lines stored on drum tracks during execution sent to printer Performed by channels 3 and 2

Channel 3:

Started with an Empty buffer, and the next output drum track

Fills the buffer with the next output line from the drum truck

Returns an Outputful buffer

Channel 2:

Started with the next Outputful buffer

Sends it to the printer

Returns an Empty buffer

Note that a channel cannot be started if appropriate type of buffer is not available.

INTERRUPT VALUES (Added):

TI = 1 on Time Slice Out

IOI: 1 channel 1 done

2 channel 2 done

4 channel 3 done

Error Message Coding: (No Change)

BEGIN

INITIALIZATION

IOI = 1

MOS (MASTER MODE)

Case TI and SI of

TI SI Action

0 or 1 1 Move PCB, $RQ \rightarrow IOQ$ (Read)

```
0 or 1
                 2
                          Move PCB, RQ \rightarrow IOQ (Write)
                          Move PCB, RQ \rightarrow TQ (Terminate [0])
     0 or 1
                 3
     2
                 1
                          Move PCB, RQ \rightarrow TQ (Terminate [3])
     2
                 2
                          Move PCB, RQ \rightarrow IOQ (Write) then TQ (Terminate [3])
     2
                 3
                          Move PCB, RQ \rightarrow TQ (Terminate [0])
Case TI and PI of
     ΤI
                 PΙ
                          Action
     0 or 1
                 1
                          Move PCB, RQ \rightarrow TQ (Terminate [4])
                          Move PCB, RQ \rightarrow TQ (Terminate [5])
     0 or 1
                 2
     0 or 1
                 3
                           Page Fault
                           If Valid
                                  If Frame Available
                                       Allocate
                                       Update Page Table
                                       Adjust IC, if necessary
                                  Else
                                       Move PCB, RQ \rightarrow SQ
                               Else
                                    Move PCB, RQ \rightarrow TQ (Terminate [6])
     2
                 1
                           Move PCB, RQ \rightarrow TQ (TERMINATE [3,4])
     2
                 2
                           Move PCB, RQ \rightarrow TQ (Terminate [3,5])
                           Move PCB, RQ \rightarrow TQ (Terminate [3])
     2
                 3
Case IOI of
     0
                 No Action
     1
                 IR1
     2
                 IR2
      3
                 IR2, IR1
     4
                 IR3
     5
                 IR1, IR3
     6
                 IR3, IR2
     7
                 IR2, IR1, IR3
IR1
         Read next card in given eb, change status to ifb, place on if b (q)
         If not e-o-f and eb(q) not empty
                                          Get next eb
                                          Start Channel 1
         Examine ifb
               $AMJ:
                          Create and initialize PCB
                          Allocate frame for Page Table
                          Initialize Page Table and PTR
                          Set F \leftarrow P (Program cards to follow)
                          Change Status from ifb to eb
                          Return buffer to eb(q)
```

\$DTA: Set $F \leftarrow D$ (data cards to follow)

Change status from ifb to eb

Return buffer to eb(q)

\$END: Place PCB on LQ, change status from ifb to eb, return buffer to eb(q)

Otherwise place ifb on ifb(q), save F information (program or data card for channel 3)

IR2

Print given ofb, change status from ofb to eb

Return buffer to eb(q)

If ofb(q) not empty,

Get next ofb

Start Channel 2

IR3 (First, complete the assigned task and the follow up action for channel 3 for each possible task, and then assign new task to it in priority order.)

Case Task of

IS: Write given ifb on given track

Place track number in P or D part of PCB

Change status from ifb to eb

Return buffer to eb(q)

OS: Read information (Output line) from given track into given eb

Change status from eb to ofb

Return buffer to ofb(q)

Release track

Decrement line count in PCB

If last line, fill two other ebs (if available) with blanks, change status from eb to ofb and place the buffers on ofb(q)

Release PCB, all remaining drum tracks and all memory blocks.

Prepare 2 lines of messages from next PCB (if available) on TQ, move them into ebs (if available), change status from eb to ofb, and place these buffers also on ofb(q)

LD: Load program card from given track into indicated memory block

Decrement count in PCB

If zero, place PCB on RQ after all the <u>initializations</u>

RD: Read data card from given track into indicated memory block

Decrement count in PCB

Move PCB to RQ after setting TSC $\leftarrow 0$

WT: Write information from the indicated memory block to the given track

Increment line count (TLC) in PCB

If TI = 2 or 3, move PCB to TQ

```
Else move PCB to RQ after setting TSC \leftarrow 0
```

```
SQ(W): Write the information from the victim frame to the given track.
                Locate drum track with faulted page
                Task \leftarrow SQ(R)
                Start Channel 3
       SQ(R): Read drum track with faulted page in newly allocated frame
               Move PCB, SQ \rightarrow RQ after setting TSC \leftarrow 0
       End-Case
(Now Assign New Task in Priority Order)
         If a PCB on TQ (output spool first)
               If eb(q) not empty
               Get next buffer from eb(q)
                       Find track number of next output line
                       Task \leftarrow OS
                       Start Channel 3
         Else (input spool next)
           If ifb(q) not empty and a drum track available
                       Get next buffer from ifb(q)
                       Get a drum track
                       Task \leftarrow IS
                       Start Channel 3
         Else (load next)
             If a PCB on LQ (load next) and a memory frame available
                       Find track number of next program card
                       Allocate a frame
                       Update Page Table
                       Task \leftarrow LD
                       Start Channel 3
           Else (now i/o)
             If a PCB on IOQ
             If Read (GD)
                       If no more data card
                              Move PCB, IOQ \rightarrow TQ (Terminate [3])
                       Else
```

```
Find track number of next data card
                              Get memory RA
                             Task \leftarrow GD
                             Start Channel 3
              Else If Write (PD)
                      If TLC > TLL, Move PCB IOQ \rightarrow TQ (Terminate [2])
                      Else
                              Get a drum track, if available
                              Update PCB
                             Find memory RA
                             Task \leftarrow PD
                             Start Channel 3
         Else (allocate memory)
             If a PCB on SQ
              If a memory frame now available
                              Allocate
                              Update page Table
                              Adjust IC, if necessary
                              Move PCB SQ \rightarrow RQ with TSC \leftarrow 0
              Else
                      Run page replacement algorithm
                      Find a victim frame
                      Allocate and Deallocate this frame by updating both page tables
                      If victim frame not written into, locate drum track for faulted page
                              Task \leftarrow SQ(R)
                              Start Channel 3
              Else
                              Task \leftarrow SQ(W)
                              Start Channel 3
         (END OF IR3)
START CHi
         Adjust IOI (Subtract 1, 2, or 4)
         Reset Ch timer to zero
         Set Ch flag to busy.
STARTEXECUTION
         IC \leftarrow 00
         EXECUTEUSERPROGRAM
END (MOS)
```

```
EXECUTEUSERPROGRAM (SLAVE MODE)
ADDRESS MAP (VA, RA)
         Accepts VA, either computes & returns RA or sets PI \leftarrow 2 (Operand Error) or PI \leftarrow 3
(Page Fault)
LOOP
         ADDRESSMAP (IC, RA)
         If PI \neq 0, End-LOOP (F)
         IR \leftarrow M[RA]
         IC \leftarrow IC+1
         ADDRESSMAP (IR[3,4], RA)
         If PI \neq 0, End-LOOP (E)
         Examine IR[1,2]
               LR:
                      R \leftarrow M [RA]
               SR:
                      R \rightarrow M [RA]
               CR:
                      Compare R and M [RA]
                      If equal C \leftarrow T else C \leftarrow F
                      If C = T then IC \leftarrow IR [3,4]
               BT:
               GD:
                      SI = 1 (Input Request)
               PD:
                      SI = 2 (Output Request)
               H:
                      SI = 3 (Terminate Request)
               Otherwise PI \leftarrow 1 (Operation Error)
         End-Examine
End-LOOP (X)
                      X = F (Fetch) or E (Execute)
SIMULATION
       Increment TTC
       If TTC = TTL then TI \leftarrow 2
                                         Increment TSC
       If TSC = TS, then TI \leftarrow 1
       For all CHi, i = 1,2,3
                  If CHi flag busy,
                  Increment Chi timer
                  If CHi timer = CHi total time
                                Increment IOI accordingly
                               (Set channel completion interrupts)
       End - For
If SI or PI or TI or IOI \neq 0 then Master Mode, Else Slave Mode
```

Question Bank:

- 1. What is use of IOI? What are different values of IOI?
- 2. When TI would set to 3?
- 3. What is buffering?
- 4. What is significance of EB,IFB,OFB?
- 5. What is role of channels?
- 6. What different operations are done by Channel 3?
- 7. Explain Input spooling, Output spooling?
- 8. How many cycles channel 1, channel 2 and channel 3 needs to complete assigned task?

OPERATING SYSTEM PROJECT FINAL VERSION

Outcomes:

- Understand how to load multiple programs into main memory.
- Understand how to achieve multiprogramming on single processor system.
- i) There are 4 processors: the CPU, and the 3 channels. CPU is master, channels are slaves. Channels are started with fix task by CPU. CPU then becomes free, and thus CPU and all the channels could be or n at t e same time When channels complete the assigned task, they inform the CPU (the master) o task completion, and thus of readiness to accept the next task, by sending interrupt signals called Input-Output Interrupt (101). Recall that Channel 1 and 2 takes five time units each, and Channel 3 takes two time units to complete an assigned task.

In order to distinguish which channel is sending interrupt, different interrupt values are sent by channels:

Ch 1 sets IOI to 1

Ch 2 sets IOI to 2

Ch 3 sets 101 to 4

Of course, different channels may send (raise) interrupt signals at the same time, thus IOI can take a value between 0 (no interrupt) and 7.

In previous implementations, it was implicitly assumed that only one of the 4 processors could be active at a time.

We will now explicitly simulate concurrent operation by the CPU, and the 3 channels by keeping timers for each channel: Ch1T, Ch2T, Ch3T

We will also keep flag for each channel to indicate whether channel is busy or free. The CPU should interrogate this flag to ensure that it assigns a task to only a free channel: Ch1F, Ch2F, Ch3F

- ii) In earlier versions, we had only one user program in memory. We will now implement multiprogramming several user programs in memory at the same time
- iii) The only program in memory had complete control of the CPU, when the CPU was assigned to it by the operating system. Now that there programs in memory at the same time, operating system will allocate the CPU to each process by turn for a fixed amount of time called TIME

QUANTUM or TIME INTERVAL or TIME SLICE. This is simulated by keeping a timer for each process:

TS (for Time Slice)

and when TS reaches time quantum, a timer interrupt (TI) is raised. Another timer

TT (for Total Time)

is also kept for each process, and when this timer reaches the time estimate indicated on the job card, then also a timer interrupt (TI) is raised. In order to distinguish between these two types of interrupts, TS expiry sets TI to I, and IT expiry sets TI to 2. Since both interrupts may occur at the same time, value of TI will vary between 0 (no interrupt) and 3.

iv) In earlier version, when Operating Systems Services were needed, service calls for operating systems were directly made by user programs through routines such as MOS/READ. Now user program will communicate with Operating System only through interrupts.

Two types of interrupts are provided for this purpose.

For service calls, Supervisor Interrupt (SI) is raised, 1 for GD (Read Data), 2 for PD (Write Data) and 3 for Halt. Note that only one such interrupt can occur at a time, thus SI takes value between 0 (no interrupt) to 3.

For any abnormality in the program, Program Interrupt (P1) is raised. P1 is set to:

- 1 for operation code error (not one of seven)
- 2 for operand error (not numeric)
- 3 for page fault

Note that the value of P1 will vary between 0 (no interrupt) to 3

Interrupts

PI and SI are set in slave mode when user program runs on CPU.

IOI and TI are external interrupts, which will be simulated outside of slave mode.

MOS will be interrupt-driven, i.e., which functions in MOS will execute will be completely determined by the interrupts which have occurred. Since the project simulates interrupt, and interrupt may occur any time, MOS should check and service interrupt after the execution of every user instruction. Thus the control of CPU will switch to MOS after CPU executes one user instruction in slave mode. When MOS has serviced all the interrupts raised during the execution of this instruction, control of CPU is given back to user program for execution of the next instruction.

Concurrent Operation

The CPU and the channels work concurrently. Thus the operations of

Input spooling (Ch 1 and Ch3) Loading (Ch3)

Execution (CPU)

Input-Output, i.e., GD & PD (Ch3)

and Output Spooling (Ch3 and Ch2)

could, and perhaps most of the time will, be taking place simultaneously except for the fact that Ch3 can do only one thing at a time.

Channel 3

Channel 3 performs four different tasks:

Input Spooling

Loading

Input-Output (GD & PD)

Output Spooling

It is possible that any of these four tasks could be waiting to be assigned to Channel 3. The operating system will lay down a priority (most likely static rather than dynamic) system to decide as to which task should be assigned to Channel 3.

An Outline of Project Design

Begin

Definitions and Initializations

While there is still any job in the system

Slave Mode (user program, P1 & SI set here)

Simulate IOI and TI

Master Mode (MOS, service interrupts)

End-while

Wrap-up

End

Slave Mode

Same as before except:

- i. Assume error may occur, check for it, and set PI to 1 or 2
- ii. when page fault occurs, don't call MOS/ALLOCATE MEM, only set PI to 3

iii. Replace service calls by interrupts as shown below

SPOOLING AND BUFFERING INFO

- Buffer Pool: 3 Types: Empty, Inputful, Outputful
- Channels: 3
 - Channel 1: Cardreader to Supervisor Memory
 - Channel 3: Supervisor Memory and Drum (either way)
 - Channel 2: Supervisor Memory to Printer
- Spooling: Input and Output

(a)Input (Before Execution): Program and data cards transferred from Card Reader to Drum

Performed by Channels 1 and 3

Channel 1:

Started with an Empty buffer

Fills it with the next card from card reader

Returns inputful buffer

Channel 3:

Started with the next inpuful buffer, and an available drum track

Writes the buffer to the drum track

Returns an Empty buffer

OUTPUT (After the program has terminated)

Output lines stored on drum tracks during execution sent to printer

Performed by channels 3 and 2

Channel 3:

Started with an Empty buffer, and the next output drum track

Fills the buffer with the next output line from the drum truck

Returns an Outputful buffer

Channel 2:

Started with the next Outputful buffer

Sends it to the printer

Returns an Empty buffer

Note that a channel cannot be started f appropriate type of buffer is not available.

```
Service Calls Interrupts
MOS/READ (RA) SI ---1
MOS/WRITE (RA) SI ---2
MOS/TERMINATE SI ---3
Simulate IOI and TI
       Simulate IOI
              For all Chi (i = 1, 2, or 3)
                      If Chi F = I (Chi is busy)
                             Then ChiT --- ChiT + 1
                      If ChiT=(5 \text{ for } i=1 \text{ and } 2, 2 \text{ for } i=3)
                             Then increment 101 (by 1 for i = 1, 2 for i = 2, and 4 for i = 3)
                      End—For
Simulate TI
       For the process which is running
              TS --- TS + 1
              If TS = 10 (assuming 10 units for time quantum)
              Then TI --- TI + 1;
              TT --- TT + i
              If TT = time estimate in $AMJ card
              Then TI --- TI + 2;
Master Mode
Operating system maintains several queues:
Buffer Pool
       Queue for empty buffers (EBQ)
       Queue for inputful buffers (IFBQ)
       Queue for outputful buffers (OFBQ)
PCB
       Load queue (LQ): Input spool completed, PCB waiting for loading or being loaded by
       Channel 3
       Ready queue (RQ): Loading completed, PCB ready for execution by CPU
       Memory queue (MQ): PCB was executing, now waiting to get memory
```

Input-Output Queue (IOQ): PCB was executing, now waiting for IJO (GD/PD) to be completed by Channel 3

Terminate queue (TQ): Execution completed, PCB waiting for output spooling or being output-spooled by Channel 3 —Channel 2 combine

MOS

Service all interrupts if set:

Case PI of:

- 0 return
- 1 op-code error message

move PCB: RQ --- TQ

2 operand error message

move PCB: RQ --- TQ

3 check page fault

Invalid: move PCB: RQ --- TQ

Valid: memory available?

Yes: allocate

No: (Graduate Group) Execute Page Replacement Algorithm (Undergraduate

Group) Move PCB: RQ --- MQ

End-case

Case TI of

- 0 return
- 1 move PCB :RQ---RQ
- 2, 3 time-out error message

move PCB: RQ --- TQ

Case SI of

- 0 return
- 1 (GD) if no more data card

out-of-data error message

move PCB: RQ --- TQ

else move PCB: RQ --- IOQ

2 (PD) if print line-limit to exceed,

print —line—limit exceeded error message

move PCB: RQ---TQ

else move PCB: RQ --- IOQ

3 (H) normal termination message

move PCB: RQ --- TQ

IOI Interrupt

Coding of IOI interrupt is central to MOS Design, and will probably account for more than half of MOS code.

There should be three separate interrupt Routines (IR) coded for each channel:

Ch1IR, Ch2IR, Ch3IR

An interrupt is raised by a channel when it completes a task, and hence it is now free to accept a new task. Thus, 1-0 interrupt routines are written to perform two tasks in the order shown.

- Housecleaning after last task
- Assigning new task, if possible.

In the project, since channels are being simulated, an additional task of simulating channel operation (moving information appropriately from source to destination) must be done before anything else is done. Thus interrupt routines will be written to perform three tasks in the order shown.

- Move information for the last task
- Housecleaning after the last task
- Assigning new task, if possible

Following notations will be used:

EB Empty Buffer

EBQ Empty Buffer Queue

IFB Inputful Buffer

IFBQ Inputful Buffer Queue

OFB Outputful Buffer

OFBQ Outputful Buffer Queue

Coding will follow the following pattern:

```
Case IOI of
0
       return
1
       CH1IR
2
      Ch2IR
3
      Ch2IR, Ch1IR
4
      Ch3IR
5
      Ch3IR, Ch1IR
6
      Ch3IR, Ch2IR
7
      Ch3IR, Ch2IR, ChlIR
Ch1IR
      Move next card into the assigned EB
       Place buffer on IFBQ
       Start Ch 1
Start Ch1
If Ch1F = 0, and a card on card reader, and a buffer on EBQ
Then
      Take an EB
      Ch1F --- 1
       ChlT ---0
Ch2IR
       Move the assigned OFB to printer
      Place buffer on EBQ
       StartCh2
StartCh2
      If Ch2F = 0, and a buffer on OFBQ,
      Then
      Take an OFB
       Ch2F--- 1
       Ch2T---0
Ch3IR
(Note: A defined variable TASK indicates the current Ch3 function:
```

IS (Input Spool)

LD (Load)

IO (GD/PD)

OS (Output Spool)

First perform simulation of last (one of four mentioned above) assigned task and related housecleaning functions, and then StartCh3:

Case TASK of:

IS: Move assigned IFB to assigned drum truck

Place buffer on EBQ

LD: Move next program card from drum truck (location in PCB on LQ) to assigned memory block.

Check if this was last program card. If so, move PCB: LQ --- RQ

[undergrad project only]

GD: Move next data card from drum truck (location in PCB on IOQ) to assigned memory block.

Move PCB: IOQ --- RQ

PD: Move a line image from assigned memory block to assigned drum track.

Move PCB: IOQ --- RQ

OS: Move next output line from drum track (location in PCB on TQ) to assigned ED.

Place buffer on OFBQ.

If this was the last output line, kill PCB.

End-case

StartCh3

(NOTE: There are 4 tasks, prioritize them, and assign in that order. Assume OS, IS, GD/PD,

LD priority to be the priority order.)

If TQ and EBQ not empty

If starting a new PCB, take buffer(s) from EBQ.

Move message(s) from PCB to buffer(s)

Take a buffer from EBQ

Pick up pointer to next output line stored on the drum track from PCB

```
TASK---OS
       Ch3F---1
       Ch3T---0
Else if IFBQ not empty,
      Take a buffer from IFBQ
       If $AMJ
             then create and update PCB, F --- P
             Place buffer on EBQ
Else if $DTA
             Then F---D
             Place buffer on EBQ
Else if $END
Then place PCB on LQ (undergrad project), RQ (graduate project)
Place buffer in EBQ
Else
Allocate drum track
TASK---IS
Ch3F--- 1
Ch3T---0
Else if IOQ not empty
If PCB indicates GD
       Find drum track with next data card and locate memory RA, both from PCB
      TASK---GD
       Ch3F--- 1
       Ch3T---0
Else
      Locate memory RA of the next output line from PCB
       Allocate drum track, update PCB
      TASK---PD
       Ch3F--- 1
       Ch3T---0
```

