TIPS FOR EFFECTIVE DIMENSIONALITY REDUCTION (DR) Tip 1 -> Choose an appropriate method!

In general, linear method such as PCA are good at preserving global structure. " Non linear method such as Kernel PCA, +- 3NE better at preserving local streture. of observations in data have assigned class labels and goal is to represent that best separates them into known categories, we consider using superived DR techniques like LDA superiosed DR techniques like LDA. Tip 2 -> Preprocess continuous dota and count input data!

• Before applying any DR technique, data standardization/scoling is required o scaling step ensures equal contribution from each variable, which is especially important for datasets containing heterogenous features with high variance or distinct units. of the dataset contains large set of categorical variable, multiple factor analysis is used. PCA cannot be applied to categorical variables, because its objective is to maximize the variance accounted for, a concept that exist only for numerical measure. For categorical variables like "nominal" (unordered) or "ordinal" (ordered) categorical variable, variance can be replaced by chi-square distance on category frequencies. · Converting categorical variables to dummy binary features, another approach is to use Optimal Scaling PCA. (CATPCA). Optimal scaling quantification such that the variance in new variable is maximized.

Advantage of ophmal scaling is that it does not assume linear relationship between variables Tip 4 -> Use embedding methods for reducing similarity & dissimilarity input · When features (column name) are not available, relationship between

data points measured as similarhes/dissimilarhes.

- If the original data are binary, Euclidean distance is not appropriate and Mohhatten distance is better. If the feature are sparsed, then Jaccard distance is preferred.

- Dissimilarities can be also used as an input to t-SNE.

- A collection of neural network based approaches, colled Wood2Vec use similarity score (the co-occurence data) to generate vector embedding of objects in a continuous Euclidean space.

Tip 5 > Consciously decide on the number of dimensions to retain.

- Choose number of PCs which explain maximum variance from data

- For nonspectral, optimization based methods, number of components is usually prespecified before DR computation: when using these approach, number of component can be choosen by repeating DR process using an increasing number of dimensions and lower value of loss function that the method minimize eq KL divergence transition probability defined for input & output data in the case of t-SNE.

Tip 6 -> Understanding the meaning of the new dimensions.

- Feature map or correlation circles can be used to determine which original variables are associated with each other on with newly generated output dimensions.

Tip7 -> Check the robustness of result & quantity uncertainities,

- when subsequence eigen vectors have close to equal values then PCA is unstable. Then we should check against different polameter setting.

- For t-SNE, use KL divergence to choose optimal pemplexity.

- On other hand, if a dataset contains aberrant, robost kernel PeA should be use