

intouch
COMMUNICATIONS

HTTP INTERFACE TO INTOUCH BULK SMS GATEWAY

Sending Messages through the HTTP API.

Messages can be sent using HTTP **"POST"** issued by your gateway or server. The URL to use to send messages is below:

https://www.intouchsms.co.rw/api/sendsms/.json

1. SEND SMS REQUEST

A send SMS request to the gateway to be sent should be encoded as a json string. Below are the necessary parameters to be passed with the URL.

Parameter Name	Data Format	Description
username	string	Username assigned to your account by Intouch
password	string	Password provided by Intouch for your account associated with your username.
Recipients	string	Phone numbers of the recipient(s) if more than one they should be separated by commas
sender	string	Sender (Can be alpha-numeric)
message	string	Contents of the message e.g. test sms
dlrurl	String	Your server URL to which the delivery report will be sent

An example of a request is below:

I. In Python

```
data = {
        'recipients':'0785971082,0782300441',
         'message' :'Hello World',
        'sender':'Intouch',
        'dlrurl':'http://www.dlrurl.rw /deliversms/'
        }
r = requests.post(
```

```
                'https://www.intouchsms.co.rw/api/sendsms/.json',
                data,
                auth=(username, password)
                )
print  (r.json(), r.status_code)
```

II. In PHP

```
$data = array(
                "sender"=>'Intouch',
                "recipients"=>"0722404528",
                "message"=>"hello world",
               "dlrurl"=>"http://www.dlrurl.rw /deliversms/"
        );
        $url = "https://www.intouchsms.co.rw/api/sendsms/.json";
        $data = http_build_query ($data);
        $username="username";
        $password="password";
        $ch = curl_init();
        curl_setopt($ch,CURLOPT_URL, $url);
        curl_setopt($ch, CURLOPT_USERPWD, $username . ":" . $password);
        curl_setopt($ch,CURLOPT_POST,true);
        curl_setopt($ch, CURLOPT_RETURNTRANSFER,1);
        curl_setopt($ch, CURLOPT_SSL_VERIFYPEER, 0);
        curl_setopt($ch,CURLOPT_POSTFIELDS, $data);
        $result = curl_exec($ch);
        $httpcode = curl_getinfo($ch, CURLINFO_HTTP_CODE);
        curl_close($ch);
        echo $result;
        echo $httpcode;
```

2. SEND SMS RESPONSE

The IntouchSMS gateway will respond with json response.

Below is the format of the response:


```
{
'details': [{
        'status': 'P',
        'message': 'Hello',
        'cost': 18.0,
        'receipient':
        '+250785971082',
        'messageid': 238254
        }],
'success': True,
'summary': {
        'message': 'Hello',
        'balance': -1617.0,
        'cost': 18.0,
        'totalmessages': 1,
        'time': u'2015-08-27T16:19:58.398'
        }
}
```


A response will have a status code to indicate wether the send message request was successfull or not. The response will also include a description to indicate the reason why the message failed to be sent in case it's a failure.

Below is a list of the status codes.

Status Code	Description
200	OK. No error encountered.
400	Bad Request, error encountered.

3. RECEIVING THE DELIVERY REPORT

When requesed through the dlrurl field when sending an SMS, a delivery receipt (DLR) will be sent back to the application url (set in dlrurl) through an http GET.

The receiving end point must reply back with a «200 OK» status header

The intouchsms platform will send the final status of the sms as an http get with the messageid and status

Below is a sample URL with parameters

http://www.dlrurl.rw/deliversms?messageid=55311547&status=U

Meaning of Statuses sent to the Delivery report URL

Status	Description
P	Message being Processed
D	Message Delivered
Q	Message Queued
E	Message Errored
S	Message Sent
U	Message Undelivered