

Measures

1 Why

We want to generalize the notion of length, area, volume beyond the Lebesgue measure on the product spaces of real numbers.

2 Definition

An extended-real-valued non-negative function on an algebra is *finitely additive* if the result of the function applied to the union of a disjoint finite family of distinguished sets is the sum of the results of the function applied to each of the sets individually.

An extended-real-valued non-negative function on a sigma algebra is *countably additive* if the result of the function applied to the union of a disjoint countable family of distinguished sets is the limit of the partial sums of the results of the function applied to each of the sets individually.

A finitely additive measure is an extended-real-valued non-negative finitely additive function which associates the empty set with the real number 0. A countably additive measure is an extended-real-valued non-negative countably additive function which associates the empty set with the real number 0. We call countably additive measures measures, for short.

Every countably additive measure is finitely additive. On the other hand, there exist finitely additive measures which are not countable additive.

In the context of measure, we call a countably unitable subset algebra a measurable space. We call the distinguished sets measurable sets. A measure

space is triple. As a pair, the first two objects are a measurable space. The third object is a measure defined on the sigma algebra of teh measurable space.

3 Notation

Let A a set. Let \mathcal{A} a sigma algebra on A. The pair (A, \mathcal{A}) is a measurable space.

Let $\mu : \mathcal{A} \to [0, \infty]$ a measure; thus: (a) $\mu(\emptyset) = 0$ and (b) for disjoint $\{A_n\} \subset \mathcal{A}, \ \mu(\bigcup_{n=1}^{\infty} A_n) = \sum_{n=1}^{\infty} \mu(A_n)$ The triple (A, \mathcal{A}, μ) is a measure space.

We use μ since it is a mnemonic for "measure". We often also us ν to denote measures, since it is after μ in the Greek alphabet, and λ , since it is before μ in the Greek alphabet.

4 Examples

Example 1. Let (A, A) a measurable space. Let $\mu : A \to [0, +\infty]$ such that $\mu(A)$ is |A| if A is finite and $\mu(A)$ is $+\infty$ otherwise. Then μ is a measure. We call μ the counting measure.

Example 2. Let (A, A) measurable. Fix $a \in A$. Let $\mu : A \to [0, +\infty]$ such that $\mu(A)$ is 1 if $a \in A$ and $\mu(A)$ is 0 otherwise. Then μ is a measure. We call μ the point mass concentrated at a.

Example 3. Let R denote the real numbers. The Lebesgue measure on the measurable space $(R, \mathcal{B}(R))$ is a measure.

Example 4. Let N be the natural numbers. Let A the finite co-finite algebra on N. Let $\mu : A \to [0, +\infty]$ be such that $\mu(A)$ is 1 if A is infinite or 0 otherwise. Then μ is a finitely additive measure. However it is impossible to extend μ to be a countably additive measure. Observe that if $A_n = \{n\}$ the $\mu(\cup_n A_n) = 1$ but $\sum_n \mu(A_n) = 0$.

Example 5. Let (A, A) a measurable space. Let $\mu : A \to [0, +\infty]$ be 0 if $A = \emptyset$ and $\mu(A)$ is $+\infty$ otherwise. Then μ is a measure.

Example 6. Let A be set with at least two elements $(|A| \ge 2)$. Let $A = A^*$. Let $\mu : A \to [0, +\infty]$ such that $\mu(A)$ is 0 if $A = \emptyset$ and $\mu(A) = 1$ otherwise. Then μ is not a measure, nor is μ finitely additive.

Proof. Let $B, C \in \mathcal{A}$, $B \cap C = \emptyset$ then using finite additivity we obtain a contradiction $1 = \mu(B \cup C) = \mu(B) + \mu(C) = 2$.