



User Manual

Copy your camera cards to several drives at once, and know that every file arrived intact.

ingesto.

KIOSK

SOURCES

Drop your card here + Browse

LOADED CARDS

▼ SRC1

A001

004_A001_ALEX_FX6_261001_1416

OPERATOR ALEX CAMERA FX6

PICTURE PROFILE SLOG3

NOTES Shooting notes, lens info, location...

▼ SRC2

A002

005_A002_ALEX_FX6_261001_1416

OPERATOR ALEX CAMERA FX6

PICTURE PROFILE SLOG3

NOTES Shooting notes, lens info, location...

COUNTER

004

last: 003

7% INGEST QUEUE (2)

1 card left · 49.2 GB total · ~5m58s left

COPYING XDR00T/Clip/...

FILES REMAINING 97 (168)

DATA REMAINING 14.2 GB (24.6 GB)

SPEED 392.9 MB/s

ETA 38s

14% A001 168 files · 24.6 GB · 2 destinations

COPYING

XDR00T/Clip/A001C014.MXF 392.9 MB/s

RAID_SHOOT COPYING 42%

NAS_BACKUP NETWORK COPYING 42%

0% A002 24.6 GB · 2 destinations

QUEUED

waiting

RAID_SHOOT QUEUED 0%

NAS_BACKUP NETWORK QUEUED 0%

COPY MODE

FAST Copy only, no checks

SIZE CHECK Detects incomplete copies, not corruption

SECURE Detects any data corruption (xxHash)

PRO Secure + checksum lists

DESTINATIONS

Drop your destinations here + Browse

RAID_SHOOT /Volumes/RAID_SHOOT

DST1 004_A001_ALEX_FX6_261001_1416 005_A002_ALEX_FX6_261001_1416

NAS_BACKUP /Volumes/NAS_BACKUP

DST2 004_A001_ALEX_FX6_261001_1416 005_A002_ALEX_FX6_261001_1416

FOLDER STRUCTURE

Insert /

{counter} * {cardname} *

{operator} * {camera} *

{YY} * {MM} * {DD} * {HH} *

{MIN} *

TEMPLATES

Template 1 empty

Template 2 empty

Template 3 empty

Template 4 empty

PAUSE

CANCEL

Version 2.7.2 · October 2026

Just Edit · github.com/noar-justedit/ingesto

Contents

1	Welcome	What ingestor does, and its three promises
2	Install and first launch	macOS, Windows, Linux
3	Your first ingest in seven steps	The short version
4	The window at a glance	Three columns, three buttons
5	Loading cards	Sources, card details, several cards
6	Choosing destinations	Drives, RAIDs, network shares
7	Naming the folders	Folder structure, subfolders, templates
8	The counter	Numbering your cards
9	Choosing a copy mode	FAST, SIZE CHECK, SECURE, PRO
10	Starting and following an ingest	Safety checks, the ingest queue
11	When the ingest ends	Summary, errors, re-copy, eject
12	History and reports	What was ingested, and where
13	Verifying a folder later	Re-check without copying again
14	Settings	Every option, one by one
15	Kiosk mode	A locked station for a whole crew
16	Managing volumes	Filters, hide, eject, refresh
17	Good practice on set	A checklist
18	Troubleshooting	Common questions

1 Welcome

ingesto copies the footage from your camera cards to as many drives as you need, then reads every copy back to make sure it is identical to the card. It is free and open source, and runs on macOS, Windows and Linux.

What it does for you

- **One card, several drives, in one pass.** The card is read once and written to every destination at the same time. The copies are then checked at the same time too.
- **Several cards in a row.** Load a batch of cards; they are ingested one after the other, each to every destination.
- **Folders named for you.** Each card lands in a folder built from a template: counter, card name, operator, camera, date...
- **It recognises the camera** from the structure of the card, and fills the camera field for you.
- **It writes what it did:** an ingest report on each drive, checksum lists and MHL manifests if you want them, and a notification on your phone if you set one up.

Three promises

1 · YOUR CARD IS NEVER TOUCHED

ingesto never deletes, renames or overwrites anything on a card it copies. While a card is being ingested, any write to it is refused. The only exception is **Card Tracking**, an option that is off by default and writes nothing but its own small journal file (see chapter 14).

2 · "VERIFIED" MEANS VERIFIED

The word *verified* only appears when every file was read back from every destination and compared with the card (SECURE and PRO modes). A FAST copy says *not verified*, a SIZE CHECK copy says *sizes checked*, everywhere: on screen, in the report, on your phone. A run with errors is never shown as a success.

3 · IT REFUSES TO START WHEN SOMETHING IS WRONG

A drive that has been unplugged, two cards that would land in the same folder, a card with nothing to copy: ingest stops before writing anything, names the problem, and tells you nothing has been copied.

2 Install and first launch

Download

Get the latest version from the Releases page: github.com/noar-justedit/ingesto/releases/latest. Choose the file for your system.

macOS

1. Open the `.dmg` file.
2. Drag **ingesto** into your **Applications** folder.
3. Launch it with a normal double-click. The app is signed and notarised by Apple: no security warning.


Windows

1. Run the installer.
2. The installer is not signed, so Windows SmartScreen shows a warning the first time. Click **More info**, then **Run anyway**. This is expected.

Linux

Two packages are offered: the `.AppImage` runs on most distributions without installing; the `.deb` installs on Debian and Ubuntu.

The first launch



ingesto at first launch: no card, no destination yet.

There is no setup wizard. The window opens straight away with your mounted cards and drives in the middle. The mode is **SECURE**, the recommended setting. You can start working immediately; chapter 3 shows how.

UPDATES

When a new version is published, ingesto shows **New version available** at launch. **Get it** opens the download page, **Later** closes the notice.


YOUR COMPUTER STAYS AWAKE

During an ingest, ingesto prevents the computer from going to sleep. The screen may still turn off; the copy carries on.

3 Your first ingest in seven steps

The essentials on one page. Each step is detailed in the chapters that follow.

- 1 **Connect** your card reader and your destination drives. They appear under **MOUNTED VOLUMES**.
- 2 **Drag the card** onto the **SOURCES** zone on the left (or right-click it → **Set as SOURCE**).
- 3 **Drag one or more drives** onto the **DESTINATIONS** zone on the right (or right-click → **Set as DESTINATION**).
- 4 **Fill in** the operator, camera, picture profile and notes for the card, if you need them in the folder name or the report.
- 5 **Check the folder name** shown in green under each destination. Change the **FOLDER STRUCTURE** if needed.
- 6 **Choose the copy mode**. Keep **SECURE** unless you have a reason not to.
- 7 **Click START INGEST**. Wait for the green summary **ALL FILES COPIED & VERIFIED** before you do anything with the card.




Ready to go: card A001 loaded, two destinations, the folder name previewed on each drive.

BEFORE YOU FORMAT A CARD

Only format a card after a **verified** ingest (SECURE or PRO) to at least two drives, with a green summary. ingesto will never format a card for you.

4 The window at a glance

Three columns, read from left to right: what you copy, what is happening, where it goes.



AREA	WHAT YOU FIND THERE
Left: SOURCES	The cards to copy, with their details (operator, camera, picture profile, notes) and the counter at the bottom.
Centre	MOUNTED VOLUMES: every card, drive and network share connected to the computer. INGEST HISTORY: the cards already ingested on the loaded destinations. COPY MODE at the bottom. During an ingest, this column shows the ingest queue instead.
Right: DESTINATIONS	The drives that will receive the copies, the FOLDER STRUCTURE , the TEMPLATES and the START INGEST button.

The three buttons at the top right


BUTTON	USE
KIOSK	Switches to kiosk mode, a simplified, locked screen for a shared station (chapter 15).
Book icon	Verifies a folder that was ingested earlier, without copying again (chapter 13).
Gear icon	Opens the Settings (chapter 14).

Hover over any button or icon for a short explanation. The small ⓘ buttons next to some titles open a detailed explanation.


5 Loading cards

Three ways to load a card

- **Drag** the card from **MOUNTED VOLUMES** onto the **SOURCES** zone. You can also drag it from the Finder or the Explorer.
- **Right-click** the card → **Set as SOURCE**.
- **+ Browse** in the Sources zone, to pick a card or a folder.



Right-click on a volume.



A card has just been inserted.

When you insert a new card, ingesto offers to use it: **Use as source** loads it, **Ignore** leaves it alone.

A loaded card shows a red **SRC1** badge, both in the Sources column and on its tile. The folder it will create appears in green under its name.

The card details

Each card has four fields:

- **OPERATOR:** who shot it.
- **CAMERA:** the camera model.
- **PICTURE PROFILE:** SLOG3, CLOG, VLOG, HLG... pick one from the list or type your own.
- **NOTES:** free text, recorded in the report and the notification.

These values can be used in the folder name and appear in the report.

- **Carried over:** operator, camera and picture profile are kept from one card to the next. Notes describe one card and are cleared after each ingest.
- **(A) or (M):** a small green **(A)** next to **CAMERA** means ingesto read the model off the card. A grey **(M)** means it was typed by hand.
- **The broom** next to **LOADED CARDS** clears the four fields in one click.
- Operator and camera accept letters and digits only, so the folder names stay clean. The picture profile is written in capitals and without spaces: `s-log 3` becomes `SL0G3`.

Several cards

Load as many cards as you like. Each gets its own block, which you can fold with the arrow. They are ingested one after the other, each to every destination, each in its own numbered folder. Remove a card with its **x**.


WRITE-PROTECTED CARD

If the card's lock switch is on, ingesto warns you before starting. You can continue (nothing is ever written to the card anyway) or remove the card.

6 Choosing destinations

A destination is a drive, a RAID, a network share or a folder that will receive a full copy of each card.

Load them the same way as cards: drag onto the **DESTINATIONS** zone, right-click → **Set as DESTINATION**, or **+ Browse** to choose a precise folder. Each one gets a green badge **DST1**, **DST2** ...



Under each destination: its path, and in green the folder each card will create.

- Under each destination, ingesto lists **the folders it will create**, one per loaded card. Check them before starting.
- Your destinations are remembered from one session to the next.
- Network shares (NAS) work. In SECURE and PRO modes, ingesto really reads the copy back over the network, not from the computer's memory, so the check is genuine. It is slower; that is the price of a real check.
- A destination cannot be the card itself, nor a folder inside it: ingesto refuses.
- Before starting, ingesto checks that each drive has enough free space. If not, it tells you and lets you decide.


HOW MANY DESTINATIONS?

Two is the usual minimum on a shoot: for example a working drive and a backup drive. ingesto writes to all of them in one pass, so a third copy costs little extra time.

7 Naming the folders

Each card is copied into its own folder. Its name is built from the **FOLDER STRUCTURE**: a row of pieces you assemble.

The Insert menu



Click **Insert** to add a piece at the end of the structure. Pieces are grouped by kind:

- **THE CARD**: counter, card name, camera, picture profile, operator.
- **THE DATE**: year, month, day, hour, minute.
- **TYPED BY YOU**: **Custom text...** adds a fixed text such as `DAY1` or a client name.
- **SEPARATORS**: underscore `_` or hyphen `-`.

Drag the pieces to reorder them. The **x** on a piece removes it.

Double-click the row to type the whole structure by hand.


What each piece becomes

PIECE	BECOMES	EXAMPLE
<code>{counter}</code>	The card number (chapter 8)	<code>004</code>
<code>{cardname}</code>	The name of the card	<code>A001</code>
<code>{operator}</code>	The operator field	<code>ALEX</code>
<code>{camera}</code>	The camera field	<code>FX6</code>
<code>{pp}</code>	The picture profile field	<code>SLOG3</code>
<code>{YY}</code> / <code>{YYYY}</code>	Year, 2 or 4 digits	<code>26</code> / <code>2026</code>
<code>{MM}</code> <code>{DD}</code>	Month, day	<code>10</code> <code>01</code>
<code>{HH}</code> <code>{MIN}</code>	Hour, minute of the ingest	<code>14</code> <code>35</code>

The default structure gives, for example: `004_A001_ALEX_FX6_261001_1435` .

An empty field creates nothing, not even a stray separator. You never get `004__FX6` .

Subfolders



The `/` button starts a subfolder. One ingest can thus build the whole tree of your project, identically on every destination.

Example:


DAY1 / {camera} / {counter}_{cardname}... gives
DAY1/FX6/004_A001_ALEX_261001 .

Subfolder pieces are shown in blue, the card's own folder in green. A piece in *italics* is text you typed.

A few rules, all checked before anything is written:

- The `{counter}` must be in the card's own folder, after the last `/`.
- Four levels at most.
- A subfolder level that ends up empty (a card with no camera, for example) is simply skipped. The card's own folder can never be empty: ingestor refuses instead.
- A `/` typed in a field (operator, camera...) never creates a folder. Only the structure decides.

Templates



The **TEMPLATES** area keeps four structures, each with a name. The one in use carries a tick.

- **Click a filled template** to load it.
- **Click an empty one** to save the current structure there; you can give it a name.
- **Right-click** a template to load, save over or delete it.
- The icons in the header **save**, **export** and **import** templates, to share them with another station.

8 The counter

The counter numbers your cards: 001, 002, 003... It stays at the bottom of the left column.

Counter

How the ingest number for each card is chosen.

Auto (default). INGESTO scans your destinations and picks the next free number, so cards get consecutive numbers even across sessions. It rescans automatically whenever a destination is added or a copy finishes.

Manual override. Typing a number, or using +/-, locks the counter to that value. It stays locked until you click **Auto** again, which rescans the destinations and returns to automatic mode.

How it is written. Pick the number of digits. It is a **minimum**, not a maximum: after 99 comes 100, never 00. Changing it does not disturb folders already on your drives, and it does not restart the counter.

Got it

Auto (the normal case)

ingesto looks at what is already on your destinations and picks the next free number. Cards get consecutive numbers across sessions and days. **last: 003** under the counter tells you what it found.

Manual

Type a number or use **- / +** to force a value. It stays locked until you click **Auto**, which goes back to automatic numbering.

Number of digits

The ⓘ next to **COUNTER** lets you choose 2, 3 or 4 digits (07, 007, 0007). It is a minimum: after 99 comes 100.

WHY IT MATTERS


The counter is global to the destination, even with subfolders per day or per camera. A gap in the numbering therefore means a card is missing.

A NUMBER ALREADY USED

If the number you chose already exists on a destination, ingestio refuses to start and offers to change the counter or show you the existing folder. An existing card folder is never written into.

9 Choosing a copy mode

The mode decides how thoroughly each copy is checked. It is chosen at the bottom of the centre column.



The four modes. Here PRO is selected, which shows its own options below.

MODE	WHAT IT CHECKS	WHEN TO USE IT
FAST	Nothing. Copy only. Shown as <i>not verified</i> .	Throwaway material, or an extra copy you will check elsewhere.
SIZE CHECK	That each copied file has the same size as the original. Catches an interrupted copy or a full disk, not a corrupted file. Shown as <i>sizes checked</i> .	When time is very short and you accept the risk.
SECURE	Every file is read back from every destination and its fingerprint (xxHash) compared with the card. Detects any corruption, down to a single bit.	Recommended for all rushes. The default.
PRO	Everything SECURE does, plus checksum lists and manifests, a choice of algorithm, and the optional double source read.	When a post house, an archive or a workflow asks for checksum files.

The ⓘ next to **COPY MODE** explains each mode in the app.

PRO options

- **Algorithm:** xxHash64, xxHash128 or MD5. Choose the one your post-production or archive asks for. MD5 is noticeably slower.
- **Double source read:** after verifying the copies, ingestor reads the card a second time and checks it gives the same data. A card that answers differently is failing; those files are flagged. It makes the verification roughly twice as long.

PRO mode, advanced use

Not recommended for most users.

PRO does everything **SECURE** does, and also writes a **checksum list** in each destination folder for later re-verification. It's meant for specific archival / hand-off workflows where you carry those lists into another tool.

For normal ingest, **SECURE already guarantees your copies bit-for-bit**, so you do not need PRO. PRO is slower (especially in MD5), adds extra files to your folders, and assumes you know why you want checksum lists.

☐ Don't show this again

Back to SECURE

Use PRO

The warning shown the first time you pick PRO.

PRO IS NOT "MORE SECURE"

SECURE already guarantees your copies bit for bit. PRO adds files for other tools. If nobody asked you for checksum lists, SECURE is the right choice.

The checksum and manifest files PRO writes are chosen in the **Settings**, section **WRITE CHECKSUM** (chapter 14).

WHY SECURE TAKES LONGER


Checking means reading every file again from each drive. ingestor deliberately bypasses the computer's memory cache so that what it reads really comes from the disk. On a slow drive or a network share, verification can take as long as the copy.

10 Starting and following an ingest

The START INGEST button

Its label tells you what is missing: **Load a card**, then **Choose a destination**, then **START INGEST** when everything is ready.

Safety checks before anything is written




When you click Start, ingesto checks everything first. If something is wrong, a window explains what, why, and what to do. The line **Nothing has been written** confirms your drives and card are untouched.

Typical cases:

- a drive or card that is no longer connected;
- two cards that would land in the same folder (here, two cards both called A001 with no counter in the structure);
- a counter number already used on a destination;
- not enough free space;
- a card with nothing to copy.


The ingest queue

During the ingest, the centre column shows the queue, and only it.



Card A001 being copied to two drives; A002 is waiting.

- **The ring at the top left** follows the whole queue, all cards and all phases included, with the cards left, total size and time left.
- **The tiles** below give the current file, files and data remaining, speed and estimated time. An **Errors** tile appears if anything goes wrong.
- **One block per card**, with one line per destination, each with its own percentage and speed. A drive lagging behind is visible at a glance.
- **The colour says the phase:** green while copying, blue while verifying, violet during the double source read, red on error.



Verification: each destination is read back at its own speed (here the network share is slower).

Pause and cancel

PAUSE finishes the current file then waits; **Resume** continues. **CANCEL** stops the ingest. Everything else (cards, destinations, structure, counter, mode) is locked during the run: what you change after clicking Start cannot affect a copy already under way.


QUITTING DURING AN INGEST

If you try to quit while copying, ingesto asks for confirmation. Your card is untouched either way.

11 When the ingest ends

A summary window opens, with a sound. Its colour and title tell you at once whether you can trust the copies.

Everything went well



The title depends on the mode:

- **ALL FILES COPIED & VERIFIED:** SECURE or PRO. The copies are proven identical.
- **ALL FILES COPIED & SIZE-CHECKED:** SIZE CHECK.
- **ALL FILES COPIED:** FAST. Nothing was checked.

Below: mode, number of files, size, time of each phase and average speed. Then, for each card, its folder on each drive.

- **REVEAL** opens the folder in the Finder or the Explorer.
- **EJECT** ejects the card (**EJECT ALL** for a batch).

Something went wrong



The window turns red and says plainly what happened, for example **2 FILES DID NOT SURVIVE THE COPY TO NAS_BACKUP**. Under the title: **Do not format this card**.

The list below groups the failed files by cause. A bad copy is set aside under a name ending in `.ingesto-failed`, so no damaged file ever carries a valid name in your delivery folder.

Re-copy 2 failed files copies and verifies those files again, and only them. The queue shows the progress as usual.

THE RULE

As long as the summary is not green and verified, keep the card. If a re-copy fails again on the same drive, suspect the drive or its cable. If ingestio says the card does not give the same data twice, the card itself is failing: keep it aside.

Two notes you may see on a green summary

- **Blue, You can double-check this later.** The check ran right after the copy, and part of it may have been answered by the computer's memory rather than the drive. The ingest is verified; for extra peace of mind, another day, re-plug the drive and verify the folder (chapter 13).
- **Orange, The extra card check did not really run** (PRO with double source read). Your footage is fine and verified, but the second read of the card came from the computer's memory, so it did not test the card's health. Where it is possible, a button offers to run that card check again for real.

12 History and reports

Ingest history

INGEST HISTORY 3 cards · 56.2 GB

✓ 003	A002	003_A002_ALEX_FX6_260924_1502			2 drives	VERIFIED	
DATE: 24.09.2026 15:02 FILES: 121 SIZE: 18.4 GB DURATION: 8m28s COPY SPEED: 59.4 MB/s MODE: Secure PHASES: copy 5m18s · verify 3m10s DESTINATIONS: RAID_SHOOT, NAS_BACKUP OPERATOR · CAMERA · PROFILE: ALEX · FX6 · SLOG3							
> ✓ 002	B001	002_B001_MARC_FX3_260924_1131			2 drives	VERIFIED	

Read back from the reports written on the destinations, so it survives a restart. [Open the report](#)

The history, with one line opened.

As soon as a destination is loaded, the centre column lists every card already ingested on it: number, card name, folder, number of drives, and a status badge **VERIFIED** or **FAILED**.

- **Click a line** to see the details: date, number of files, size, duration, speed, mode, the time of each phase, every destination, operator, camera, profile and notes.
- The **folder icon** at the end of a line shows that folder on the drive.
- The history is read from the reports written on the drives. It survives a restart, and a drive brought from another computer arrives with its own history.
- The **eraser** in the header clears the list in ingesto only. The reports on the drives are never touched, and **Show it again** brings the lines back.

The ingest report

After each ingest, ingesto updates a report at the root of each destination. **Open the report**, under the history, opens it in your browser.


ingesto.										
INGEST REPORT										
/Volumes/RAID_SHOOT										
Created 24.09.2026 09:12 · last update 24.09.2026 17:14										
3 CARDS			381 FILES			56.2 GB TOTAL SIZE			3 CLEAN	
#	DATE	CARD	OPERATOR	CAM	MODE	FILES	SIZE	RESULT	COPY / V1 / V2	NOTE
- 001	24.09.2026 09:12	A001	ALEX	FX6 SLOG3	Secure	168	24.6 GB	OK	6m52s / 4m11s / -	Interviews
6 files ingested										
XDR00T/Clip/A001C001.MXF										4.1 GB
XDR00T/Clip/A001C002.MXF										4.1 GB
XDR00T/Clip/A001C003.MXF										4.1 GB
XDR00T/Clip/A001C004.MXF										4.1 GB
XDR00T/Clip/A001C005.MXF										4.1 GB
XDR00T/Clip/A001C006.MXF										4.1 GB
- 002	24.09.2026 11:31	B001	MARC	FX3 SLOG3	PRO · xxHash64	92	13.1 GB	OK	3m41s / 2m19s / 2m00s	B-roll
- 003	24.09.2026 15:02	A002	ALEX	FX6 SLOG3	Secure	121	18.4 GB	OK	5m18s / 3m10s / -	
COPY copy pass V1 read back on the destination V2 second read on the source Click - on a line to list the files.										

Written by ingestio. This file lives in the destination and is updated after each ingest. Only Secure and PRO read the copies back: a line in Fast or Size check says what was copied, not that it was verified.

The HTML report: one line per card. Click ▶ on a line to list its files.

- One line per card: number, date, card, operator, camera, mode, files, size, result, the time of each phase, notes.
- The **Export PDF** button turns it into a PDF to send to production or post.
- CSV (spreadsheet) and JSON (for scripts) versions can be added in the Settings.

13 Verifying a folder later



The **book icon** at the top right re-checks a folder that was already ingested, without copying anything.

1. Click the book icon.
2. Choose the card folder on the drive.
3. ingesto reads its checksum list or MHL manifest, re-reads every file and compares.


The result shows how many files were checked, matched, corrupted or missing. **ALL FILES VERIFIED** means the folder is still identical to what was ingested.

WHEN TO USE IT


Before handing a drive to post-production, after a long journey, or months later before archiving. The folder must contain a checksum list or a manifest: keep **Write Checksum** on in the Settings (it is on by default).

14 Settings


The gear icon at the top right opens the Settings. Each section has its own switch. **Done** closes the window; everything is saved straight away.



Card Tracking (off by default)



Writes a small file, `.ingesto.json`, on the card. When the same card comes back, ingesto knows whether it was formatted since its last ingest. This is the only option that ever writes on a card, which is why it asks for confirmation when you turn it on.




If a card comes back unformatted, ingesto tells you how many files were already ingested and how many are new:

- **COPY NEW FILES:** only what was shot since. A file is skipped only if every destination already holds a verified copy of it.
- **COPY FULL CARD:** everything again.
- **CANCEL:** nothing.

Useful when a card goes back into the camera between two ingests.

Write Checksum (on by default)




Writes, next to the footage, files that let anyone re-check the copy later (SECURE and PRO only):

- **Checksum list:** a `.xxh` / `.md5` list, readable by ingesto and TeraCopy.
- **MHL manifest:** the classic format of Silverstack, YoYotta, OffShoot (PRO with MD5 or xxHash64).
- **ASC MHL:** the newer industry standard, in an `ascmhl` folder.


Turn on what your post-production asks for. If nobody asks, the checksum list alone is enough.

Ingest Report (on by default)



Formats: **HTML** to read and print, **CSV** for spreadsheets, **JSON** for scripts. **Full report** lists every file of each card; off, each card is a single line. **VIEW** opens the current report.

File Filter (off at every launch)



Copies only the file types you choose: video, audio, pictures, and other files (sidecars such as XML, THM...), each type one by one.

Copy empty folders keeps the card's empty folders.

Reorganize files on destination sorts the copied files into `/VIDEO` , `/AUDIO` , `/PICTURES` . Other files are then never copied.

USE WITH CARE

A filtered ingest is not a full copy of the card. That is why the filter switches itself off at every launch: you have to turn it on on purpose each time. Your choice of formats is kept.

Many cameras need their sidecar files (XML, metadata folders) to be read correctly in editing software. When in doubt, leave the filter off.

Phone Notifications (ntfy) (off by default)

PHONE NOTIFICATIONS (NTFY)
Send a notification to your phone after ingest.

Server `https://ntfy.sh`

Topic `ingesto-studio-7x2k`

Scan to install the ntfy app
Point your phone camera at the code: it opens ntfy.sh, where the free app is available for iPhone and Android.

Then open the app and subscribe to the topic above. Pick a long, hard-to-guess topic name: on the public server it is the only thing protecting your notifications.

Send test notification

Receive a notification on your phone after each card: card, operator, camera, number of files, size, mode, result per drive, time of each phase, notes. A failed card is sent as high priority.

1. Install the free **ntfy** app (iPhone, Android): scan the QR code.
2. In ingestio, enter a **Topic**: a long, hard-to-guess name.
3. In the app, subscribe to that same topic.
4. Click **Send test notification** and check your phone.

Leave the **Server** on `https://ntfy.sh` unless you run your own.

PRIVACY

On the public server, the topic name is the only thing protecting your notifications. Anyone who knows it can read them. Choose something like `ingesto-studio-7x2k`, not `ingesto`.

Post-Ingest Command and Card Handoff (off by default)

Two options for technical users who automate their workflow with scripts. **Post-Ingest Command** runs a command after each ingest. **Card Handoff** passes each card to a script of yours with a document describing what was copied and verified; **Dry run** tests it. Both run exactly what you type. If you do not know what to put there, leave them off.

Settings File

SETTINGS FILE
Share ingestio settings with another machine / user.

Included in export / applied on import:

- ☒ Current naming template
- ☒ Saved templates
- ☒ Copy mode
- ☒ Card tracking
- ☒ Write checksum (incl. settings)
- ☒ Ingest report (incl. settings)
- ☒ File filter (incl. settings)

Export settings... **Import settings...**

To set up several stations the same way. **Export settings...** saves a file; **Import settings...** applies it on another computer. The switches choose what is included: current structure, templates, copy mode, Card Tracking, checksums, report, file filter.

WHAT IS NOT A SETTING


There is no language choice: the interface is in English. Sounds and keeping the computer awake are automatic. The counter's number of digits is set from its own ⓘ (chapter 8), the kiosk PIN from the KIOSK button (chapter 15).

15 Kiosk mode


A simplified, locked, full-screen view for a station shared by a whole crew: the camera operator comes, inserts the card, types their name, starts. Nobody can change the settings.

Prepare the station

- 1 In the normal window, load the **destinations**, choose the **copy mode** and the **folder structure**. Kiosk mode uses them as they are.
- 2 Click **KIOSK** at the top right.
- 3 Choose a 4-digit PIN, then type it again to confirm.



Setting the PIN.




The kiosk screen, card loaded.

For the person ingesting

- 1 Insert the card, or click **Browse a card....**
- 2 Type your name in **Operator** (required). Camera, profile and notes are optional; the camera is often filled in automatically.
- 3 Click **START INGEST** and follow the large progress ring.

- 4 Read the result, then click **Next card**.



The result screen speaks plainly:

- **Verified:** "You can remove your card." The card is ejected automatically.
- After FAST or SIZE CHECK: "Remove your card. Do not erase it."
- On a problem: "Do not erase it. Call the person in charge."

If no destination was chosen, the screen says **Not set up yet** and asks for the person who set up the station.

Leaving kiosk mode

Click **STANDARD** at the top right and enter the PIN. After five wrong attempts, the pad locks for 30 seconds.

FORGOTTEN PIN

Quit and reopen ingestor: it always starts in the normal window. The PIN is never saved; it only lasts for the session.

16 Managing volumes

The **MOUNTED VOLUMES** area shows every card, drive and share connected, with an icon by type (card, disk, network, system disk) and the free space.

CONTROL	USE
HIDE SYSTEM	Hides the computer's internal disk.
HIDE NETWORK	Hides network shares.
Right-click → Hide Volume	Hides one particular volume. The eye icon in the header shows hidden volumes again.
Right-click → Eject	Ejects a card or drive without leaving ingestio. Not offered for the system disk or network shares, and refused during an ingest. If the volume was loaded, it is unloaded once the eject has succeeded.
Circular arrow	Refreshes the list.

On Windows, a card's drive letter is shown in the list, for example **LUMIX (D:)** , so two identical cards in two readers can be told apart. The folder name and the report use the bare name, **LUMIX** .

17 Good practice on set

ingesto does the checking. These habits make the rest of the chain just as safe.

Before the shoot

- ☐ Install ingestio and do a test ingest with a real card.
- ☐ Prepare the folder structure and save it as a template.
- ☐ Set up ntfy and send a test notification.
- ☐ Prepare at least two destination drives, formatted and with enough space for the day.

For every card

- ☐ Mode **SECURE** (or PRO if asked).
- ☐ Check the folder name in green under each destination.
- ☐ Fill in the operator, camera and notes.
- ☐ Wait for the green summary: **ALL FILES COPIED & VERIFIED.**
- ☐ Only then hand the card back to camera for formatting.

At the end of the day

- ☐ Check the history: no red line, no gap in the numbers.
- ☐ Export the report as PDF for production if needed.
- ☐ Keep the two copies in two different places.

18 Troubleshooting

macOS says ingesto cannot be opened, or the developer cannot be verified

Versions from 2.5.5 onwards are signed and should not show this. If you see it, you have an older version or a copy you built yourself: right-click the app in Applications → **Open** → **Open** again. Once is enough.

My card or drive does not appear

Click the refresh arrow. Check that it appears in the Finder or the Explorer. Check that **HIDE SYSTEM / HIDE NETWORK** are not hiding it, and click the eye icon to show hidden volumes.

The ingest refuses to start

Read the window: it names the problem and says what to do. Nothing has been copied. The most common causes are a drive that has been disconnected, two cards with the same name and no counter in the structure, or a counter number already used.

SECURE or PRO is slow

That is expected: every file is read again from every drive, from the disk itself. On a network share, verification can take as long as the copy. It is the price of a real check.

Some files failed

Do not format the card. Click **Re-copy**. If it fails again on the same drive, change the cable or the drive. If ingesto says the card gives different data on each read, the card is failing: keep it aside.

The counter does not give the number I expected

In Auto mode, it follows what it finds on the destinations. Look at **last:** under the counter. To force a number, type it; click **Auto** to go back.

I hid the history by mistake

Click **Show it again** in the history area. The reports on the drives were never touched.

The notification does not arrive

Check that the topic is exactly the same in ingesto and in the ntfy app, and use **Send test notification**. The computer needs an Internet connection.

Help and contact

To report a problem or suggest an improvement, open an *issue* on github.com/noar-justedit/ingesto/issues. Mention your version of ingesto (bottom left of the window) and your system.

ingesto is free software, under the GNU GPL v3 licence. © Just Edit 2026.