

Scoop neck tank mini dress

EU38 sewing guide . 6 pieces . 1.5 m fabric at 140 cm

text-first guide, no illustrations in this edition. Every step is the engine's own instruction.

Cut list

Bodice Front - cut 1 on fold

Bodice Back - cut 2

Front Neck Facing - cut 1 on fold, interface

Back Neck Facing - cut 2, interface

Skirt Front - cut 1 on fold

Skirt Back - cut 2 (center back seam)

Steps

1. Print and check the 3 cm calibration square before cutting.
2. This block uses standard assumptions for shoulder slope, underbust sew a quick muslin (test version) from cheap fabric first and adjust before cutting your real fabric.
3. Knit fabric: sew with a narrow zigzag or stretch stitch and a ballpoint/stretch needle so the seams stretch with the fabric.
4. Cut every piece as labelled: pieces marked 'on fold' on the fabric fold, 'cut 2' twice.
5. Fuse interfacing to the neck facings.
6. Staystitch the neckline just inside the seam line so it doesn't stretch while you work.
7. Sew all darts first, pressing toward the center.
8. Sew the bodice shoulder seams and press them open.
9. Sew the front and back neck facings together at the shoulders; finish the facing's outer edge (zigzag, overlock or turn 5 mm and stitch).
10. Attach the facing to the neckline right sides together, leaving the last 2 cm free at each center back edge (the zipper goes there later). Trim to 6 mm, clip into the curve every 2 cm.
11. Understitch: press the seam allowance toward the facing and stitch it to the facing 2 mm from the seam this keeps the facing rolled inside. Turn, press, tack at the shoulder seams.
12. Sew the bodice side seams.
13. Finish armholes with bias binding (sleeveless).
14. Sew the skirt seams (leave the center back seam open where the zipper will go), then join bodice to skirt at the waist seam, matching side seams.

15. Insert an invisible zipper in the center back through bodice and skirt: install the zipper BEFORE closing the seam below it, then close the rest of the seam. (Very stretchy knit? Baste the back seam closed first and test pulling the dress on you may be able to skip the zipper and just sew the seam.)
16. Fold the free facing ends back over the zipper tape and hand-tack them down so the edge sits clean against the zipper.
17. Try it on, then hem with a 2 cm double fold.