


Lab - Configuring Basic RIPv2 and RIPng (Instructor Version)

Instructor Note: Red font color or Gray highlights indicate text that appears in the instructor copy only.

Topology



Addressing Table

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	G0/1	172.30.10.1	255.255.255.0	N/A
	S0/0/0 (DCE)	10.1.1.1	255.255.255.252	N/A
R2	G0/0	209.165.201.1	255.255.255.0	N/A
	S0/0/0	10.1.1.2	255.255.255.252	N/A
	S0/0/1 (DCE)	10.2.2.2	255.255.255.252	N/A
R3	G0/1	172.30.30.1	255.255.255.0	N/A
	S0/0/1	10.2.2.1	255.255.255.252	N/A
S1	N/A	VLAN 1	N/A	N/A
S3	N/A	VLAN 1	N/A	N/A
PC-A	NIC	172.30.10.3	255.255.255.0	172.30.10.1
РС-В	NIC	209.165.201.2	255.255.255.0	209.165.201.1
PC-C	NIC	172.30.30.3	255.255.255.0	172.30.30.1

Objectives

Part 1: Build the Network and Configure Basic Device Settings

Part 2: Configure and Verify RIPv2 Routing

- Configure and verify RIPv2 is running on routers.
- Configure a passive interface.
- Examine routing tables.
- Disable automatic summarization.
- Configure a default route.
- Verify end-to-end connectivity.

Part 3: Configure IPv6 on Devices

Part 4: Configure and Verify RIPng Routing

- Configure and verify RIPng is running on routers.
- Examine routing tables.
- Configure a default route.
- Verify end-to-end connectivity.

Background / Scenario

RIP version 2 (RIPv2) is used for routing of IPv4 addresses in small networks. RIPv2 is a classless, distance-vector routing protocol, as defined by RFC 1723. Because RIPv2 is a classless routing protocol, subnet masks are included in the routing updates. By default, RIPv2 automatically summarizes networks at major network boundaries. When automatic summarization has been disabled, RIPv2 no longer summarizes networks to their classful address at boundary routers.

RIPng (RIP Next Generation) is a distance-vector routing protocol for routing IPv6 addresses, as defined by RFC 2080. RIPng is based on RIPv2 and has the same administrative distance and 15-hop limitation.

In this lab, you will configure the network topology with RIPv2 routing, disable automatic summarization, propagate a default route, and use CLI commands to display and verify RIP routing information. You will then configure the network topology with IPv6 addresses, configure RIPng, propagate a default route, and use CLI commands to display and verify RIPng routing information.

Note: The routers used with CCNA hands-on labs are Cisco 1941 Integrated Services Routers (ISRs) with Cisco IOS Release 15.2(4)M3 (universalk9 image). The switches used are Cisco Catalyst 2960s with Cisco IOS Release 15.0(2) (lanbasek9 image). Other routers, switches, and Cisco IOS versions can be used. Depending on the model and Cisco IOS version, the commands available and output produced might vary from what is shown in the labs. Refer to the Router Interface Summary Table at the end of the lab for the correct interface identifiers.

Note: Make sure that the routers and switches have been erased and have no startup configurations. If you are unsure, contact your instructor.

Instructor Note: Refer to the Instructor Lab Manual for the procedures to initialize and reload devices.

Required Resources

- 3 Routers (Cisco 1941 with Cisco IOS Release 15.2(4)M3 universal image or comparable)
- 2 Switches (Cisco 2960 with Cisco IOS Release 15.0(2) lanbasek9 image or comparable)
- 3 PCs (Windows 7, Vista, or XP with terminal emulation program, such as Tera Term)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet and Serial cables as shown in the topology

Part 1: Build the Network and Configure Basic Device Settings

In Part 1, you will set up the network topology and configure basic settings.

- Step 1: Cable the network as shown in the topology.
- Step 2: Initialize and reload the router and switch.
- Step 3: Configure basic settings for each router and switch.
 - a. Disable DNS lookup.
 - b. Configure device names as shown in the topology.
 - c. Configure password encryption.
 - d. Assign class as the privileged EXEC password.
 - e. Assign **cisco** as the console and vty passwords.
 - Configure a MOTD banner to warn users that unauthorized access is prohibited.
 - g. Configure logging synchronous for the console line.
 - h. Configure the IP address listed in the Addressing Table for all interfaces.
 - i. Configure a description to each interface with an IP address.
 - j. Configure the clock rate if applicable to the DCE serial interface.
 - k. Copy the running-configuration to the startup-configuration.

Step 4: Configure PC hosts.

Refer to the Addressing Table for PC host address information.

Step 5: Test connectivity.

At this point, the PCs are unable to ping each other.

- a. Each workstation should be able to ping the attached router. Verify and troubleshoot if necessary.
- b. The routers should be able to ping one another. Verify and troubleshoot if necessary.

Part 2: Configure and Verify RIPv2 Routing

In Part 2, you will configure RIPv2 routing on all routers in the network and then verify that routing tables are updated correctly. After RIPv2 has been verified, you will disable automatic summarization, configure a default route, and verify end-to-end connectivity.

Step 1: Configure RIPv2 routing.

a. On R1, configure RIPv2 as the routing protocol and advertise the appropriate networks.

```
R1# config t
R1(config)# router rip
R1(config-router)# version 2
R1(config-router)# passive-interface g0/1
R1(config-router)# network 172.30.0.0
R1(config-router)# network 10.0.0.0
```

The **passive-interface** command stops routing updates out the specified interface. This process prevents unnecessary routing traffic on the LAN. However, the network that the specified interface belongs to is still advertised in routing updates that are sent out across other interfaces.

- b. Configure RIPv2 on R3 and use the **network** statement to add appropriate networks and prevent routing updates on the LAN interface.
- c. Configure RIPv2 on R2. Do not advertise the 209.165.201.0 network.

Note: It is not necessary to make the G0/0 interface passive on R2 because the network associated with this interface is not being advertised.

Step 2: Examine current state of network.

a. The status of the two serial links can quickly be verified using the **show ip interface brief** command on R2.

R2# show ip interface brief

Interface	IP-Address	OK?	Method	Status	Protocol
Embedded-Service-Engine0/0	unassigned	YES	unset	administratively down	down
GigabitEthernet0/0	209.165.201.1	YES	manual	up	up
GigabitEthernet0/1	unassigned	YES	unset	administratively down	down
Serial0/0/0	10.1.1.2	YES	manual	up	up
Serial0/0/1	10.2.2.2	YES	manual	up	up

b. Check connectivity between PCs.

From PC-A, is it possible to ping PC-B? _____ Why?

No, R2 is not advertising the route to PC-B.

From PC-A, is it possible to ping PC-C? Why? No, R1 and R3 do not have routes to the specific subnets on the remote router. From PC-C, is it possible to ping PC-B? No, R2 is not advertising the route to PC-B. From PC-C, is it possible to ping PC-A? No, R1 and R3 do not have routes to the specific subnets on the remote router.

c. Verify that RIPv2 is running on the routers.

You can use the debug ip rip, show ip protocols, and show run commands to confirm that RIPv2 is running. The **show ip protocols** command output for R1 is shown below.

```
R1# show ip protocols
```

```
Routing Protocol is "rip"
Outgoing update filter list for all interfaces is not set
Incoming update filter list for all interfaces is not set
Sending updates every 30 seconds, next due in 7 seconds
Invalid after 180 seconds, hold down 180, flushed after 240
Redistributing: rip
Default version control: send version 2, receive 2
 Interface
                      Send Recv Triggered RIP Key-chain
  Serial0/0/0
Automatic network summarization is in effect
Maximum path: 4
Routing for Networks:
 10.0.0.0
 172.30.0.0
Passive Interface(s):
   GigabitEthernet0/1
Routing Information Sources:
 Gateway Distance Last Update
 10.1.1.2
                      120
Distance: (default is 120)
```

When issuing the debug ip rip command on R2, what information is provided that confirms RIPv2 is running?

RIP: sending v2 updates to 224.0.0.9 via Serial 0/0/0 (10.1.1.2).

When you are finished observing the debugging outputs, issue the undebug all command at the privileged EXEC prompt.

When issuing the show run command on R3, what information is provided that confirms RIPv2 is running?

router rip version 2

d. Examine the automatic summarization of routes.

The LANs connected to R1 and R3 are composed of discontiguous networks. R2 displays two equal-cost paths to the 172.30.0.0/16 network in the routing table. R2 displays only the major classful network address of 172.30.0.0 and does not display any of the subnets for this network.

R2# show ip route

```
<Output omitted>
     10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks
         10.1.1.0/30 is directly connected, Serial0/0/0
L
        10.1.1.2/32 is directly connected, Serial0/0/0
         10.2.2.0/30 is directly connected, Serial0/0/1
С
        10.2.2.2/32 is directly connected, Serial0/0/1
L
     172.30.0.0/16 [120/1] via 10.2.2.1, 00:00:23, Serial0/0/1
R
                    [120/1] via 10.1.1.1, 00:00:09, Serial0/0/0
      209.165.201.0/24 is variably subnetted, 2 subnets, 2 masks
С
         209.165.201.0/24 is directly connected, GigabitEthernet0/0
         209.165.201.1/32 is directly connected, GigabitEthernet0/0
Τ.
```

R1 displays only its own subnets for the 172.30.0.0 network. R1 does not have any routes for the 172.30.0.0 subnets on R3.

R1# show ip route

R3 only displays its own subnets for the 172.30.0.0 network. R3 does not have any routes for the 172.30.0.0 subnets on R1.

R3# show ip route

Use the **debug ip rip** command on R2 to determine the routes received in the RIP updates from R3 and list them here.

172.30.0.0/16

R3 is not sending any of the 172.30.0.0 subnets, only the summarized route of 172.30.0.0/16, including the subnet mask. Therefore, the routing tables on R1 and R2 do not display the 172.30.0.0 subnets on R3.

Step 3: Disable automatic summarization.

a. The **no auto-summary** command is used to turn off automatic summarization in RIPv2. Disable auto summarization on all routers. The routers will no longer summarize routes at major classful network boundaries. R1 is shown here as an example.

```
R1(config) # router rip
R1(config-router) # no auto-summary
```

b. Issue the **clear ip route** * command to clear the routing table.

```
R1 (config-router) # end
R1# clear ip route *
```

c. Examine the routing tables. Remember will it take some time to converge the routing tables after clearing them.

The LAN subnets connected to R1 and R3 should now be included in all three routing tables.

```
R2# show ip route
<Output omitted>
Gateway of last resort is not set
      10.0.0.0/8 is variably subnetted, 4 subnets, 2 masks
         10.1.1.0/30 is directly connected, Serial0/0/0
        10.1.1.2/32 is directly connected, Serial0/0/0
L
С
         10.2.2.0/30 is directly connected, Serial0/0/1
         10.2.2.2/32 is directly connected, Serial0/0/1
      172.30.0.0/16 is variably subnetted, 3 subnets, 2 masks
       172.30.0.0/16 [120/1] via 10.2.2.1, 00:01:01, Serial0/0/1
                      [120/1] via 10.1.1.1, 00:01:15, Serial0/0/0
        172.30.10.0/24 [120/1] via 10.1.1.1, 00:00:21, Serial0/0/0
        172.30.30.0/24 [120/1] via 10.2.2.1, 00:00:04, Serial0/0/1
      209.165.201.0/24 is variably subnetted, 2 subnets, 2 masks
С
         209.165.201.0/24 is directly connected, GigabitEthernet0/0
         209.165.201.1/32 is directly connected, GigabitEthernet0/0
R1# show ip route
<Output omitted>
Gateway of last resort is not set
      10.0.0.0/8 is variably subnetted, 3 subnets, 2 masks
С
        10.1.1.0/30 is directly connected, Serial0/0/0
L
        10.1.1.1/32 is directly connected, Serial0/0/0
R
        10.2.2.0/30 [120/1] via 10.1.1.2, 00:00:12, Serial0/0/0
      172.30.0.0/16 is variably subnetted, 3 subnets, 2 masks
      172.30.10.0/24 is directly connected, GigabitEthernet0/1
        172.30.10.1/32 is directly connected, GigabitEthernet0/1
R 172.30.30.0/24 [120/2] via 10.1.1.2, 00:00:12, Serial0/0/0
R3# show ip route
<Output omitted>
      10.0.0.0/8 is variably subnetted, 3 subnets, 2 masks
C.
        10.2.2.0/30 is directly connected, Serial0/0/1
        10.2.2.1/32 is directly connected, Serial0/0/1
L
```

d. Use the **debug ip rip** command on R2 to exam the RIP updates.

```
R2# debug ip rip
```

After 60 seconds, issue the **no debug ip rip** command.

What routes are in the RIP updates that are received from R3?

172.30.30.0/24

Are the subnet masks now included in the routing updates? _____ yes

Step 4: Configure and redistribute a default route for Internet access.

a. From R2, create a static route to network 0.0.0.0 0.0.0.0, using the **ip route** command. This forwards any unknown destination address traffic to the R2 G0/0 toward PC-B, simulating the Internet by setting a Gateway of Last Resort on the R2 router.

```
R2(config) # ip route 0.0.0.0 0.0.0.0 209.165.201.2
```

b. R2 will advertise a route to the other routers if the **default-information originate** command is added to its RIP configuration.

```
R2(config) # router rip
R2(config-router) # default-information originate
```

Step 5: Verify the routing configuration.

a. View the routing table on R1.

```
R1# show ip route
```

<Output omitted>

Gateway of last resort is 10.1.1.2 to network 0.0.0.0

How can you tell from the routing table that the subnetted network shared by R1 and R3 has a pathway for Internet traffic?

There is a Gateway of Last Resort, and the default route shows up in the table as being learned via RIP.