Nick Tipton - ITS Undergrad

ITS 4750: Internet Engineering – Final Project Friday December 2nd

Executive Brief

ADDITIONAL POINTS (60): VLANS (15), VPNS (25), OSPF IPv4 INTERNALLY ROUTED (20)

1. Full IP documentation (not just an IP Grid)

IPV4 Private Network Address	IPV6 Network Address	IPV4 Public Network Address	IPV4 WAN Network Address	IPV6 WAN Network Address
172.18.128.0/17	2610:a8:483f:5100::/64	100.70.81.0/24	132.235.160.192/26	2610:a8:4831:312::51/64

Location	Network Address IPv4	Useable IPv4 Range	Network Address IPv6			
Internet				ethernet	IPv4 Address	IPv6 Address
Cloud	132.235.160.192/26	132.235.160.193 - 132.235.160.254	2610:a8:4831:312::51/64	br192-PublicNet	132.235.160.254	2610:a8:4831:312::1
PFE				e0	132.235.160.223	2610:a8:4831:312::51

	100.70.81.0/24	100.70.81.1 - 100.70.81.254	2610:a8:483f:5110::/64
	eth1 - PFE	100.70.81.254	2610:a8:483f:5110::1
DMZ	WebServer	100.70.81.1	2610:a8:483f:5110::3
	DNS	100.70.81.2	2610:a8:483f:5110::4
	Bastion	100.70.81.5	2610:a8:483f:5110::5
	eth0 - PFI	100.70.81.253	2610:a8:483f:5110::2

Location	Network Address IPv4	Useable IPv4 Range	Network Address IPv6			
US1	172.18.240.0/20	172.18.240.1 - 172.18.255.254	2610:a8:483f:5105::/64	ethernet : VPN	IPv4 Address	IPv6 Address
US1 to US2	172.18.160.0/20:192.168.0.224/27	172.18.160.1 - 172.18.175.254	2610:a8:483f:5100::/64	eth1:192.168.0.254	172.18.175.254	2610:a8:483f:5100::1
US1 to China	172.18.128.0/21:192.168.0.160/27	172.18.128.1 - 172.18.135.254	2610:a8:483f:5104::/64	eth2:192.168.0.190	172.18.135.254	2610:a8:483f:5104::1
US1 Subdivisions	Network Address IPv4	Useable IPv4 Range	Network Address IPv6	ethernet	IPv4 Gateway	IPv6 Gateway
VLAN 100 - Sales	172.18.241.0/24	172.18.241.1 - 172.18.241.254		eth3	172.18.241.254	
VLAN 200 - Technical	172.18.244.0/23	172.18.244.1 - 172.18.245.254	2610:a8:483f:5105::/64	eth3	172.18.245.254	
VLAN 300 - Support	172.18.242.0/23	172.18.242.1 - 172.18.243.254		eth3	172.18.243.254	2610:a8:483f:5105::1
VLAN 400 - Local Management	172.18.246.0/23	172.18.246.1 - 172.18.247.254		eth3	172.18.247.254	
VLAN 500 - Wireless	172.18.248.0/21	172.18.248.1 - 172.18.255.254		eth3	172.18.255.254	
US1	172.18.240.0/25	172.18.240.1 - 172.18.240.126	2610:a8:483f:5112::/64	eth0	172.18.240.125	2610:a8:483f:5112::2
PFI				eth1	172.18.240.126	2610:a8:483f:5112::1
PFI	172.18.240.128/25	172.18.240.129 - 172.18.240.254	2610:a8:483f:5111::/64	eth2	172.18.240.254	2610:a8:483f:5111::1
IT ADMIN				eth0	172.18.240.129	2610:a8:483f:5111::2

Location	Network Address IPv4	Useable IPv4 Range	Network Address IPv6			
US2	172.18.224.0/20	172.18.224.1 - 172.18.239.254	2610:a8:483f:5106::/64	ethernet : VPN	IPv4 Address	IPv6 Address
US2 to US1	172.18.160.0/20:192.168.0.224/27	172.18.160.1 - 172.18.175.254	2610:a8:483f:5100::/64	eth0: 192.168.0.225	172.18.160.1	2610:a8:483f:5100::2
US2 to European	172.18.152.0/21:192.168.0.192/27	172.18.152.1 - 172.18.159.254	2610:a8:483f:5101::/64	eth1:192.168.0.222	172.18.159.254	2610:a8:483f:5101::1
US2 Subdivisions	Network Address IPv4	Useable IPv4 Range	Network Address IPv6	ethernet	IPv4 Gateway	IPv6 Gateway
VLAN 100 - Sales	172.18.224.0/23	172.18.224.1 - 172.18.225.254		eth3	172.18.225.254	
VLAN 200 - Technical	172.18.226.0/23	172.18.226.1 - 172.18.227.254		eth3	172.18.227.254	
VLAN 300 - Support	172.18.228.0/23	172.18.228.1 - 172.18.229.254	2610:a8:483f:5106::/64	eth3	172.18.229.254	2610:a8:483f:5106::1
VLAN 400 - Global Management	172.18.230.0/23	172.18.230.1 - 172.18.231.254		eth3	172.18.231.254	
R&D Wifi Mesh	172.18.232.0/21	172.18.232.1 - 172.18.239.254		eth6	172.18.239.254	


Location	Network Address IPv4	Useable IPv4 Range	Network Address IPv6			
European	172.18.208.0/20	172.18.208.1 - 172.18.223.254	2610:a8:483f:5107::/64	ethernet : VPN	IPv4 Address	IPv6 Address
European to US2	172.18.152.0/21:192.168.0.192/27	172.18.152.1 - 172.18.159.254	2610:a8:483f:5101::/64	eth0:192.168.0.193	172.18.152.1	2610:a8:483f:5101::2
European to Ireland	172.18.144.0/21:192.168.0.0/25	172.18.144.1 - 172.18.151.254	2610:a8:483f:5102::/64	eth2:192.168.0.126	172.18.151.254	2610:a8:483f:5102::1
European to China	172.18.136.0/21:192.168.0.128/27	172.18.136.1 - 172.18.143.254	2610:a8:483f:5103::/64	eth1:192.168.0.158	172.18.143.254	2610:a8:483f:5103::1
European Subdivisions	Network Address IPv4	Useable IPv4 Range	Network Address IPv6	ethernet	IPv4 Gateway	IPv6 Gateway
VLAN 100 - Manufacturing	172.18.208.0/23	172.18.208.1 - 172.18.209.254		eth3	172.18.209.254	
VLAN 200 - Sales	172.18.210.0/23	172.18.210.1 - 172.18.211.254		eth3	172.18.211.254	
VLAN 300 - Technical	172.18.220.0/22	172.18.220.1 - 172.18.223.254		eth3	172.18.223.254	
VLAN 400 - Support	172.18.212.0/23	172.18.212.1 - 172.18.213.254	2610:a8:483f:5107::/64	eth3	172.18.213.254	2610:a8:483f:5107::1
VLAN 500 - Legal	172.18.214.0/23	172.18.214.1 - 172.18.215.254		eth3	172.18.215.254	
VLAN 600 - R&D	172.18.216.0/23	172.18.216.1 - 172.18.217.254		eth3	172.18.217.254	
VLAN 700 - Management	172.18.218.0/23	172.18.218.1 - 172.18.219.254		eth3	172.18.219.254	

Location	Network Address IPv4	Useable IPv4 Range	Network Address IPv6			
China	172.18.192.0/20	172.18.192.1 - 172.18.207.254	2610:a8:483f:5108::/64	ethernet : VPN	IPv4 Address	IPv6 Address
China to European	172.18.136.0/21:192.168.0.128/27	172.18.136.1 - 172.18.143.254	2610:a8:483f:5103::/64	eth0:192.168.0.129	172.18.136.1	2610:a8:483f:5103::2
China to US1	172.18.128.0/21:192.168.0.160/27	172.18.128.1 - 172.18.135.254	2610:a8:483f:5104::/64	eth1:192.168.0.161	172.18.128.1	2610:a8:483f:5104::2
China Subdivisions	Network Address IPv4	Useable IPv4 Range	Network Address IPv6	ethernet	IPv4 Gateway	IPv6 Gateway
VLAN 100 - Manufacturing	172.18.204.0/22	172.18.204.1 - 172.18.207.254		eth3	172.18.207.254	
VLAN 200 - Sales	172.18.192.0/23	172.18.192.1 - 172.18.193.254		eth3	172.18.193.254	
VLAN 300 - Technical	172.18.200.0/22	172.18.200.1 - 172.18.203.254	2610:a8:483f:5108::/64	eth3	172.18.203.254	2610:a8:483f:5108::1
VLAN 400 - Support	172.18.194.0/23	172.18.194.1 - 172.18.195.254	2010.uo.103j.3100.704	eth3	172.18.195.254	2010.110.11031.31001
VLAN 500 - Legal	172.18.196.0/23	172.18.196.1 - 172.18.197.254		eth3	172.18.197.254	
R&D	172.18.198.0/23	172.18.198.1 - 172.18.199.254		eth2	172.18.199.254	

Location	Network Address IPv4	Useable IPv4 Range	Network Address IPv6			
Ireland	172.18.176.0/20	172.18.176.1 - 172.18.191.254	2610:a8:483f:5109::/64	ethernet : VPN	IPv4 Address	IPv6 Address
Ireland to European	172.18.144.0/21:192.168.0.0/25	172.18.144.1 - 172.18.151.254	2610:a8:483f:5102::/64	eth0:192.168.0.1	172.18.144.1	2610:a8:483f:5102::2
Ireland Subdivisions	Network Address IPv4	Useable IPv4 Range	Network Address IPv6	ethernet	IPv4 Gateway	IPv6 Gateway
VLAN 100 - NAS	172.18.176.0/20	172.18.176.1 - 172.18.191.254	2610:a8:483f:5109::/64	eth0	172.18.191.254	2610:a8:483f:5109::1

	PFI access:	
ITAdminLaptop	http://172.18.240.254/	admin/class115#
	PFE access:	
Bastion	http://100.70.81.254/	admin/class115#
All routers	US1:US2:EU:IR:CH	itsclass/class115#

2. Network Diagram from Draw.io




3. US1 configuration

GUI Configs - ITAdmin

sudo nmcli general hostname ITAdmin

DHCP in Pfsense 2 - PFI

US1 Config set system host-name US-1 set interfaces ethernet eth0 address 172.18.240.125/25 set interfaces ethernet eth0 address 2610:a8:483f:5112::2/64 set interfaces ethernet eth0 description PFI set interfaces ethernet eth1 address 172.18.175.254/20 set interfaces ethernet eth1 address 2610:a8:483f:5100::1/64 set interfaces ethernet eth1 description E-Line3 set interfaces ethernet eth2 address 172.18.135.254/21 set interfaces ethernet eth2 address 2610:a8:483f:5104::1/64 set interfaces ethernet eth2 description E-Line4 set interfaces ethernet eth3 vif 100 address 172.18.241.254/24 set interfaces ethernet eth3 vif 200 address 172.18.245.254/23 set interfaces ethernet eth3 vif 300 address 172.18.243.254/23 set interfaces ethernet eth3 vif 400 address 172.18.247.254/23 set interfaces ethernet eth3 vif 500 address 172.18.255.254/21 set protocols static route6 2610:a8:483f:5106::/64 next-hop 2610:a8:483f:5100::2 set protocols static route6 2610:a8:483f:5101::/64 next-hop 2610:a8:483f:5100::2 set protocols static route6 2610:a8:483f:5107::/64 next-hop 2610:a8:483f:5100::2 set protocols static route6 2610:a8:483f:5108::/64 next-hop 2610:a8:483f:5100::2 set protocols static route6 2610:a8:483f:5103::/64 next-hop 2610:a8:483f:5100::2 set protocols static route6 2610:a8:483f:5109::/64 next-hop 2610:a8:483f:5100::2 set protocols static route6 2610:a8:483f:5102::/64 next-hop 2610:a8:483f:5100::2



set protocols static route 0.0.0.0/0 next-hop 172.18.240.126
set protocols static route6 ::/0 next-hop 2610:a8:483f:5112::1
set system name-server 100.70.81.2
set system name-server 2610:a8:483f:5110::4

VLAN 100

set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.241.0/24 range 0 start 172.18.241.1 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.241.0/24 range 0 stop 172.18.241.253 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.241.0/24 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.241.0/24 default-router 172.18.241.254 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.241.0/24 lease 120

VLAN 200

set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.244.0/23 range 0 start 172.18.244.1 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.244.0/23 range 0 stop 172.18.245.253 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.244.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.244.0/23 default-router 172.18.245.254 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.244.0/23 lease 120

VLAN 300

set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.242.0/23 range 0 start 172.18.242.1 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.242.0/23 range 0 stop 172.18.243.253 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.242.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.242.0/23 default-router 172.18.243.254 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.242.0/23 lease 120

VLAN 400

set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.246.0/23 range 0 start 172.18.246.1
set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.246.0/23 range 0 stop 172.18.247.253

set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.246.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.246.0/23 default-router 172.18.247.254 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.246.0/23 lease 120

VLAN 500

set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.248.0/21 range 0 start 172.18.248.1 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.248.0/21 range 0 stop 172.18.255.253 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.248.0/21 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.248.0/21 default-router 172.18.255.254 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.248.0/21 lease 120

VPN - US1 to US2

set interfaces openvpn vtun2 local-address 192.168.0.254 subnet-mask 255.255.255.224
set interfaces openvpn vtun2 local-host 172.18.175.254
set interfaces openvpn vtun2 local-port 1195
set interfaces openvpn vtun2 mode site-to-site
set interfaces openvpn vtun2 remote-address 192.168.0.225
set interfaces openvpn vtun2 remote-host 172.18.160.1
set interfaces openvpn vtun2 remote-port 1195
set interfaces openvpn vtun2 shared-secret-key-file /config/auth/openvpn-2.key
set interfaces openvpn vtun2 protocol udp
set interfaces openvpn vtun2 persistent-tunnel

VPN - US1 to China

set interfaces openvpn vtun1 local-address 192.168.0.190 subnet-mask 255.255.255.224
set interfaces openvpn vtun1 local-host 172.18.135.254
set interfaces openvpn vtun1 local-port 1195
set interfaces openvpn vtun1 mode site-to-site
set interfaces openvpn vtun1 remote-address 192.168.0.161
set interfaces openvpn vtun1 remote-host 172.18.128.1

set interfaces openvpn vtun1 remote-port 1195

set interfaces openvpn vtun1 shared-secret-key-file /config/auth/openvpn-1.key

set interfaces openvpn vtun1 protocol udp

set interfaces openvpn vtun1 persistent-tunnel

ospf default to PFI

set protocols ospf default-information originate always

set protocols ospf default-information originate metric 10

set protocols ospf default-information originate metric-type 2

OSPF CONFIG

set protocols ospf area 0 network 172.18.128.0/17

set protocols ospf log-adjacency-changes

set protocols ospf redistribute connected metric-type 2

set protocols ospf redistribute connected route-map CONNECT

set policy route-map CONNECT rule 10 action permit

set policy route-map CONNECT rule 10 match interface lo

4. US2 configuration

US2 Config

set system host-name US-2

set interfaces ethernet eth0 address 172.18.160.1/20

set interfaces ethernet eth0 address 2610:a8:483f:5100::2/64

set interfaces ethernet eth0 description E-Line3

set interfaces ethernet eth1 address 172.18.159.254/21

set interfaces ethernet eth1 address 2610:a8:483f:5101::1/64

set interfaces ethernet eth1 description E-Line2

set interfaces ethernet eth3 vif 100 address 172.18.225.254/23

set interfaces ethernet eth3 vif 200 address 172.18.227.254/23

set interfaces ethernet eth3 vif 300 address 172.18.292.254/23
set interfaces ethernet eth3 vif 400 address 172.18.231.254/23
set interfaces ethernet eth6 address 172.18.239.254/21
set interfaces ethernet eth6 address 2610:a8:483f:5106::1/64
set interfaces ethernet eth6 description R&DWifiMesh
set protocols static route6 ::/0 next-hop 2610:a8:483f:5100::1
set system name-server 100.70.81.2
set system name-server 2610:a8:483f:5110::4
set service router-advert interface eth6 prefix 2610:a8:483f:5106::/64
set service router-advert interface eth6 name-server 2610:a8:483f:5110::4
set protocols static route6 2610:a8:483f:5107::/64 next-hop 2610:a8:483f:5101::2
set protocols static route6 2610:a8:483f:5103::/64 next-hop 2610:a8:483f:5101::2
set protocols static route6 2610:a8:483f:5103::/64 next-hop 2610:a8:483f:5101::2
set protocols static route6 2610:a8:483f:5109::/64 next-hop 2610:a8:483f:5101::2
set protocols static route6 2610:a8:483f:5109::/64 next-hop 2610:a8:483f:5101::2
set protocols static route6 2610:a8:483f:5102::/64 next-hop 2610:a8:483f:5101::2

VLAN 100

set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.224.0/23 range 0 start 172.18.224.1 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.224.0/23 range 0 stop 172.18.225.253 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.224.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.224.0/23 default-router 172.18.225.254 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.224.0/23 lease 120

VLAN 200

set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.226.0/23 range 0 start 172.18.226.1 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.226.0/23 range 0 stop 172.18.227.253 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.226.0/23 name-server 100.70.81.2

set service dhop-server shared-network-name LAN-POOL2 subnet 172.18.226.0/23 default-router 172.18.227.254 set service dhop-server shared-network-name LAN-POOL2 subnet 172.18.226.0/23 lease 120

VLAN 300

set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.228.0/23 range 0 start 172.18.228.1 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.228.0/23 range 0 stop 172.18.229.253 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.228.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.228.0/23 default-router 172.18.229.254 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.228.0/23 lease 120

VLAN 400

set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.230.0/23 range 0 start 172.18.230.1 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.230.0/23 range 0 stop 172.18.231.253 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.230.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.230.0/23 default-router 172.18.231.254 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.230.0/23 lease 120

set dhcpv4 - R&D Wifi Mesh US2

set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.232.0/21 range 0 start 172.18.232.1 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.232.0/21 range 0 stop - 172.18.239.253 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.232.0/21 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.232.0/21 default-router 172.18.239.254 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.232.0/21 lease 120

VPN - US2 to Europe

set interfaces openvpn vtun3 local-address 192.168.0.222 subnet-mask 255.255.255.224
set interfaces openvpn vtun3 local-host 172.18.159.254
set interfaces openvpn vtun3 local-port 1195
set interfaces openvpn vtun3 mode site-to-site
set interfaces openvpn vtun3 remote-address 192.168.0.193

set interfaces openvpn vtun3 remote-host 172.18.152.1

set interfaces openvpn vtun3 remote-port 1195

set interfaces openvpn vtun3 shared-secret-key-file /config/auth/openvpn-3.key

set interfaces openvpn vtun3 protocol udp

set interfaces openvpn vtun3 persistent-tunnel

VPN - US2 to US1

set interfaces openvpn vtun2 local-address 192.168.0.225 subnet-mask 255.255.255.224

set interfaces openvpn vtun2 local-host 172.18.160.1

set interfaces openvpn vtun2 local-port 1195

set interfaces openvpn vtun2 mode site-to-site

set interfaces openvpn vtun2 remote-address 192.168.0.254

set interfaces openvpn vtun2 remote-host 172.18.175.254

set interfaces openvpn vtun2 remote-port 1195

set interfaces openvpn vtun2 shared-secret-key-file /config/auth/openvpn-2.key

set interfaces openvpn vtun2 protocol udp

set interfaces openvpn vtun2 persistent-tunnel

ALL ROUTER OSPF CONFIG

set protocols ospf area 0 network 172.18.128.0/17

set protocols ospf log-adjacency-changes

set protocols ospf redistribute connected metric-type 2

set protocols ospf redistribute connected route-map CONNECT

set policy route-map CONNECT rule 10 action permit

set policy route-map CONNECT rule 10 match interface lo

5. European configuration

European Config

set system host-name European

set interfaces ethernet eth0 address 172.18.152.1/21

set interfaces ethernet eth0 address 2610:a8:483f:5101::2/64 set interfaces ethernet eth0 description E-Line2 set interfaces ethernet eth1 address 172.18.143.254/21 set interfaces ethernet eth1 address 2610:a8:483f:5103::1/64 set interfaces ethernet eth1 description E-Line1 set interfaces ethernet eth2 address 172.18.151.254/21 set interfaces ethernet eth2 address 2610:a8:483f:5102::1/64 set interfaces ethernet eth2 description E-Line5 set protocols static route 0.0.0.0/0 next-hop 172.18.159.254 set protocols static route6 ::/0 next-hop 2610:a8:483f:5101::1 set system name-server 100.70.81.2 set system name-server 2610:a8:483f:5110::4 set interfaces ethernet eth3 vif 100 address 172.18.209.254/23 set interfaces ethernet eth3 vif 200 address 172.18.211.254/23 set interfaces ethernet eth3 vif 300 address 172.18.223.254/22 set interfaces ethernet eth3 vif 400 address 172.18.213.254/23 set interfaces ethernet eth3 vif 500 address 172.18.215.254/23 set interfaces ethernet eth3 vif 600 address 172.18.217.254/23 set interfaces ethernet eth3 vif 700 address 172.18.219.254/23 set protocols static route6 2610:a8:483f:5109::/64 next-hop 2610:a8:483f:5103::2 set protocols static route6 2610:a8:483f:5108::/64 next-hop 2610:a8:483f:5103::2

VLAN 100

set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.208.0/23 range 0 start 172.18.208.1 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.208.0/23 range 0 stop 172.18.209.253 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.208.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.208.0/23 default-router 172.18.209.254

set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.208.0/23 lease 120

VLAN 200

set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.210.0/23 range 0 start 172.18.210.1 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.210.0/23 range 0 stop 172.18.211.253 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.210.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.210.0/23 default-router 172.18.211.254 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.210.0/23 lease 120

VLAN 300

set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.220.0/22 range 0 start 172.18.220.1 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.220.0/22 range 0 stop 172.18.223.253 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.220.0/22 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.220.0/22 default-router 172.18.223.254 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.220.0/22 lease 120

VLAN 400

set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.212.0/23 range 0 start 172.18.212.1 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.212.0/23 range 0 stop 172.18.213.253 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.212.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.212.0/23 default-router 172.18.213.254 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.212.0/23 lease 120

VLAN 500

set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.214.0/23 range 0 start 172.18.214.1 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.214.0/23 range 0 stop 172.18.215.253 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.214.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.214.0/23 default-router 172.18.215.254 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.214.0/23 lease 120

VLAN 600

set service dhcp-server shared-network-name LAN-POOL6 subnet 172.18.216.0/23 range 0 start 172.18.216.1 set service dhcp-server shared-network-name LAN-POOL6 subnet 172.18.216.0/23 range 0 stop 172.18.217.253 set service dhcp-server shared-network-name LAN-POOL6 subnet 172.18.216.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL6 subnet 172.18.216.0/23 default-router 172.18.217.254 set service dhcp-server shared-network-name LAN-POOL6 subnet 172.18.216.0/23 lease 120

VLAN 700

set service dhcp-server shared-network-name LAN-POOL7 subnet 172.18.218.0/23 range 0 start 172.18.218.1 set service dhcp-server shared-network-name LAN-POOL7 subnet 172.18.218.0/23 range 0 stop 172.18.219.253 set service dhcp-server shared-network-name LAN-POOL7 subnet 172.18.218.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL7 subnet 172.18.218.0/23 default-router 172.18.219.254 set service dhcp-server shared-network-name LAN-POOL7 subnet 172.18.218.0/23 lease 120

VPN - Europe to Ireland

set interfaces openvpn vtun1 local-address 192.168.0.126 subnet-mask 255.255.255.128
set interfaces openvpn vtun1 local-host 172.18.151.254
set interfaces openvpn vtun1 local-port 1195
set interfaces openvpn vtun1 mode site-to-site
set interfaces openvpn vtun1 remote-address 192.168.0.1
set interfaces openvpn vtun1 remote-host 172.18.144.1
set interfaces openvpn vtun1 remote-port 1195
set interfaces openvpn vtun1 shared-secret-key-file /config/auth/openvpn-1.key
set interfaces openvpn vtun1 protocol udp
set interfaces openvpn vtun1 persistent-tunnel

VPN - Europe to China

set interfaces openvpn vtun2 local-address 192.168.0.158 subnet-mask 255.255.255.224
set interfaces openvpn vtun2 local-host 172.18.143.254
set interfaces openvpn vtun2 local-port 1195
set interfaces openvpn vtun2 mode site-to-site

set interfaces openvpn vtun2 remote-address 192.168.0.129

set interfaces openvpn vtun2 remote-host 172.18.136.1

set interfaces openvpn vtun2 remote-port 1195

set interfaces openvpn vtun2 shared-secret-key-file /config/auth/openvpn-2.key

set interfaces openvpn vtun2 protocol udp

set interfaces openvpn vtun2 persistent-tunnel

VPN - Europe to US2

set interfaces openvpn vtun3 local-address 192.168.0.193 subnet-mask 255.255.255.224

set interfaces openvpn vtun3 local-host 172.18.152.1

set interfaces openvpn vtun3 local-port 1195

set interfaces openvpn vtun3 mode site-to-site

set interfaces openvpn vtun3 remote-address 192.168.0.222

set interfaces openvpn vtun3 remote-host 172.18.159.254

set interfaces openvpn vtun3 remote-port 1195

set interfaces openvpn vtun3 shared-secret-key-file /config/auth/openvpn-3.key

set interfaces openvpn vtun3 protocol udp

set interfaces openvpn vtun3 persistent-tunnel

ALL ROUTER OSPF CONFIG

set protocols ospf area 0 network 172.18.128.0/17

set protocols ospf log-adjacency-changes

set protocols ospf redistribute connected metric-type 2

set protocols ospf redistribute connected route-map CONNECT

set policy route-map CONNECT rule 10 action permit

set policy route-map CONNECT rule 10 match interface lo

6. China configuration

China Config

set system host-name China

set interfaces ethernet eth0 address 172.18.136.1/21 set interfaces ethernet eth0 address 2610:a8:483f:5103::2/64 set interfaces ethernet eth0 description E-Line1 set interfaces ethernet eth1 address 172.18.128.1/21 set interfaces ethernet eth1 address 2610:a8:483f:5104::2/64 set interfaces ethernet eth1 description E-Line4 set interfaces ethernet eth3 vif 100 address 172.18.207.254/22 set interfaces ethernet eth3 vif 200 address 172.18.193.254/23 set interfaces ethernet eth3 vif 300 address 172.18.203.254/22 set interfaces ethernet eth3 vif 400 address 172.18.195.254/23 set interfaces ethernet eth3 vif 500 address 172.18.197.254/23 set interfaces ethernet eth2 address 172.18.199.254/23 set interfaces ethernet eth2 description R&D set interfaces ethernet eth2 address 2610:a8:483f:5108::1/64 set protocols static route6 ::/0 next-hop 2610:a8:483f:5103::1 set system name-server 100.70.81.2 set system name-server 2610:a8:483f:5110::4 set service router-advert interface eth2 prefix 2610:a8:483f:5108::/64 set service router-advert interface eth2 name-server 2610:a8:483f:5110::4

VLAN 100

set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.204.0/22 range 0 start 172.18.204.1 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.204.0/22 range 0 stop 172.18.207.253 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.204.0/22 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.204.0/22 default-router 172.18.207.254 set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.204.0/22 lease 120

VLAN 200

set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.192.0/23 range 0 start 172.18.192.1 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.192.0/23 range 0 stop 172.18.193.253 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.192.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.192.0/23 default-router 172.18.193.254 set service dhcp-server shared-network-name LAN-POOL2 subnet 172.18.192.0/23 lease 120

VLAN 300

set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.200.0/22 range 0 start 172.18.200.1 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.200.0/22 range 0 stop 172.18.203.253 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.200.0/22 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.200.0/22 default-router 172.18.203.254 set service dhcp-server shared-network-name LAN-POOL3 subnet 172.18.200.0/22 lease 120

VLAN 400

set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.194.0/23 range 0 start 172.18.194.1 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.194.0/23 range 0 stop 172.18.195.253 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.194.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.194.0/23 default-router 172.18.195.254 set service dhcp-server shared-network-name LAN-POOL4 subnet 172.18.194.0/23 lease 120

VLAN 500

set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.196.0/23 range 0 start 172.18.196.1 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.196.0/23 range 0 stop 172.18.197.253 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.196.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.196.0/23 default-router 172.18.197.254 set service dhcp-server shared-network-name LAN-POOL5 subnet 172.18.196.0/23 lease 120

set dhcpv4 - R&D China

set service dhcp-server shared-network-name LAN-POOL6 subnet 172.18.198.0/23 range 0 start 172.18.198.1

set service dhcp-server shared-network-name LAN-POOL6 subnet 172.18.198.0/23 range 0 stop 172.18.199.253 set service dhcp-server shared-network-name LAN-POOL6 subnet 172.18.198.0/23 name-server 100.70.81.2 set service dhcp-server shared-network-name LAN-POOL6 subnet 172.18.198.0/23 default-router 172.18.199.254 set service dhcp-server shared-network-name LAN-POOL6 subnet 172.18.198.0/23 lease 120

VPN - China to Europe

set interfaces openvpn vtun2 local-address 192.168.0.129 subnet-mask 255.255.255.224

set interfaces openvpn vtun2 local-host 172.18.136.1

set interfaces openvpn vtun2 local-port 1195

set interfaces openvpn vtun2 mode site-to-site

set interfaces openvpn vtun2 remote-address 192.168.0.158

set interfaces openvpn vtun2 remote-host 172.18.143.254

set interfaces openvpn vtun2 remote-port 1195

set interfaces openvpn vtun2 shared-secret-key-file /config/auth/openvpn-2.key

set interfaces openvpn vtun2 protocol udp

set interfaces openvpn vtun2 persistent-tunnel

VPN - China to US1

set interfaces openvpn vtun1 local-address 192.168.0.161 subnet-mask 255.255.255.224

set interfaces openvpn vtun1 local-host 172.18.128.1

set interfaces openvpn vtun1 local-port 1195

set interfaces openvpn vtun1 mode site-to-site

set interfaces openvpn vtun1 remote-address 192.168.0.190

set interfaces openvpn vtun1 remote-host 172.18.135.254

set interfaces openvpn vtun1 remote-port 1195

set interfaces openvpn vtun1 shared-secret-key-file /config/auth/openvpn-1.key

set interfaces openvpn vtun1 protocol udp

set interfaces openvpn vtun1 persistent-tunnel

ALL ROUTER OSPF CONFIG

set protocols ospf area 0 network 172.18.128.0/17

set protocols ospf log-adjacency-changes

set protocols ospf redistribute connected metric-type 2

set protocols ospf redistribute connected route-map CONNECT

set policy route-map CONNECT rule 10 action permit

set policy route-map CONNECT rule 10 match interface lo

7. Ireland configuration

Ireland Config

set system host-name Ireland

set interfaces ethernet eth0 address 172.18.144.1/21

set interfaces ethernet eth0 address 2610:a8:483f:5102::2/64

set interfaces ethernet eth0 description E-Line5

set interfaces ethernet eth3 vif 100 address 172.18.191.254/20

set interfaces ethernet eth3 vif 100 address 2610:a8:483f:5109::1/64

set protocols static route6 ::/0 next-hop 2610:a8:483f:5102::1

set system name-server 100.70.81.2

set system name-server 2610:a8:483f:5110::4

VLAN 100

set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.176.0/20 range 0 start 172.18.176.1

set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.176.0/20 range 0 stop 172.18.191.253

set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.176.0/20 name-server 100.70.81.2

set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.176.0/20 default-router 172.18.191.254

set service dhcp-server shared-network-name LAN-POOL1 subnet 172.18.176.0/20 lease 120

VPN - Ireland

set interfaces openvpn vtun1 local-address 192.168.0.1 subnet-mask 255.255.255.128

set interfaces openvpn vtun1 local-host 172.18.144.1

set interfaces openvpn vtun1 local-port 1195

set interfaces openvpn vtun1 mode site-to-site

set interfaces openvpn vtun1 remote-address 192.168.0.126

set interfaces openvpn vtun1 remote-host 172.18.151.254

set interfaces openvpn vtun1 remote-port 1195

set interfaces openvpn vtun1 shared-secret-key-file /config/auth/openvpn-1.key

set interfaces openvpn vtun1 protocol udp

set interfaces openvpn vtun1 persistent-tunnel

ALL ROUTER OSPF CONFIG

set protocols ospf area 0 network 172.18.128.0/17

set protocols ospf log-adjacency-changes

set protocols ospf redistribute connected metric-type 2

set protocols ospf redistribute connected route-map CONNECT

set policy route-map CONNECT rule 10 action permit

set policy route-map CONNECT rule 10 match interface lo

GUI Configs - NAS

sudo nmcli general hostname NAS

VLAN 100 in Ireland - DHCP

8. DMZ host configuration

CLI Configs - HTTP

sudo nmcli general hostname HTTP

sudo nmcli con mod "Wired connection 1" ipv4.addresses 100.70.81.1/24

sudo nmcli con mod "Wired connection 1" ipv4.gateway 100.70.81.254

sudo nmcli con mod "Wired connection 1" ipv4.dns 100.70.81.2

sudo nmcli con mod "Wired connection 1" ipv4.method manual

sudo nmcli con mod "Wired connection 1" ipv6.addresses 2610:a8:483f:5110::3

sudo nmcli con mod "Wired connection 1" ipv6.gateway 2610:a8:483f:5110::1

sudo nmcli connection modify "Wired connection 1" ipv6.dns 2610:a8:483f:5110::4

sudo nmcli con mod "Wired connection 1" ipv6.method manual

sudo nmcli connection down "Wired connection 1"

CLI Configs - DNS

sudo nmcli general hostname DNS

sudo nmcli connection up "Wired connection 1"

sudo nmcli con mod "Wired connection 1" ipv4.addresses 100.70.81.2/24

sudo nmcli con mod "Wired connection 1" ipv4.gateway 100.70.81.254

sudo nmcli con mod "Wired connection 1" ipv4.dns 132.235.160.10, 132.235.160.11

sudo nmcli con mod "Wired connection 1" ipv4.method manual

sudo nmcli con mod "Wired connection 1" ipv6.addresses 2610:a8:483f:5110::4

sudo nmcli con mod "Wired connection 1" ipv6.gateway 2610:a8:483f:5110::1

sudo nmcli connection modify "Wired connection 1" ipv6.dns 2610:a8:4831:311::10, 2610:a8:4831:311::11

sudo nmcli con mod "Wired connection 1" ipv6.method manual

sudo nmcli connection down "Wired connection 1"

sudo nmcli connection up "Wired connection 1"

GUI Configs - Bastion

sudo nmcli general hostname DNS

IPv4 address: 100.70.81.5/24

IPv4 gateway: 100.70.81.254

IPv4 DNS server: 100.70.81.2

IPv6 address: 2610:a8:483f:5110::5

9. PFE Routes

Stati	ic Routes				
	Network	Gateway	Interface	Description	Actions
9	172.18.128.0/17	pfiUS1 - 100.70.81.253	LAN	aggregate	₽□○ ■
9	2610:a8:483f:51::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	aggregatevõ	₽ □ ○1
9	2610:a8:483f:5112::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	PFI-US1	/ □○ i
9	2610:a8:483f:5111::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	admin	₽ □○ 1
9	2610:a8:483f:5105::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	US1	₽□○ ■
9	2610:a8:483f:5100::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	US1-US2	₽□○ ■
9	2610:a8:483f:5106::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	US2	/ □○ i
9	2610:a8:483f:5101::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	US1-European	₽□○ ■
9	2610:a8:483f:5107::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	EU	/ □○ i
9	2610:a8:483f:5103::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	EU-China	₽□○ ■
9	2610:a8:483f:5108::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	China	/ □○ i
9	2610:a8:483f:5104::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	US1-China	₽□○ ■
9	2610:a8:483f:5102::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	EU-Ireland	/ □○ i
9	2610:a8:483f:5109::/64	Aggregate - 2610:00a8:483f:5110::2	LAN	Ireland	/ □○ i

10.PFI Routes

Gateways Static Routes Gateway Groups

Sta	Static Routes							
	Network	Gateway	Interface	Description	Actions			
\odot	172.18.128.0/17	v4 - 172.18.240.125	OPT1	v4 aggregate				
\odot	2610:a8:483f:51::/64	v6 - 2610:a8:483f:5112::2	OPT1	v6 aggregate				
\odot	2610:a8:483f:5105::/64	v6 - 2610:a8:483f:5112::2	OPT1	US1				
\odot	2610:a8:483f:5100::/64	v6 - 2610:a8:483f:5112::2	OPT1	US1-US2				
\odot	2610:a8:483f:5106::/64	v6 - 2610:a8:483f:5112::2	OPT1	US2				
\odot	2610:a8:483f:5101::/64	v6 - 2610:a8:483f:5112::2	OPT1	US2-EU				
Ø	2610:a8:483f:5107::/64	v6 - 2610:a8:483f:5112::2	OPT1	EU				
\odot	2610:a8:483f:5103::/64	v6 - 2610:a8:483f:5112::2	OPT1	EU-China				
②	2610:a8:483f:5108::/64	v6 - 2610:a8:483f:5112::2	OPT1	China				
⊘	2610:a8:483f:5102::/64	v6 - 2610:a8:483f:5112::2	OPT1	EU-Ireland				
⊘	2610:a8:483f:5109::/64	v6 - 2610:a8:483f:5112::2	OPT1	Ireland				