# Samba

Network-based File Sharing

❑ FTP (File Transfer Protocol)

❑ NFS (UNIX-based)

- mountd is responsible for mount request
- nfsd and nfsiod
- Based on RPC

❑ CIFS (Microsoft)

- Common Internet File System
- 網路芳鄰
- SMB (Server Message Block)
- Share access to files, printers, …
- Based on NetBIOS

Applikation		
SMB		
NetBIOS		
NetBEUI	TCP/IP	IPX/SPX
NDIS (2,3,3.1,4,5)-Interface		
Karten-Treiber (MAC)		
Netzwerk-Karte		

Service of SMB and NetBIOS

❑ NetBIOS (Network Basic Input/Output System)

- API related to the session layer allowing applications to communicate over a local area network
- Name Service for name registration and resolution
- Session service for connection-oriented communication
- Datagram distribution service for connectionless communication

❑ SMB

- File and printer sharing service
- Authentication

# NetBIOS – Network Basic Input/Output System

❑ NetBIOS (API)

- 1983 – developed as an API for software communication over IBM's PC-Network LAN
  - ➢ NetBIOS relied on proprietary Sytek networking protocols
- In 1985, IBM went forward with the token ring network scheme
  - ➢ NetBEUI – NetBIOS Extended User Interface
  - ➢ using the NetBIOS Frames (NBF) routing protocol
- 1985 – Microsoft created a NetBIOS implementation for its MS-Net network topology
  - ➢ By NBF protocol
- Difference between local filesystem and network filesystem when accessing
- Used to share or access network-based filesystem just as BIOS does in local filesystem

❑ NetBIOS over TCP/IP

- In 1987
- NBT

NetBIOS Naming Service

❑ Peer to peer (Workgroup model)

**Name Registration without a NetBIOS Name Server**

I wish to register hydra...
(broadcast)

No, I've already registered it.

Name Resolution without a NetBIOS Name Server

Who is registered as phoenix?
(broadcast)

I am. My address is 192.168.220.102.

NetBIOS Naming Service

❑ **WINS**

Name Registration with a NetBIOS Name Server

I wish to register hydra...

NetBIOS
Name
Server

No, someone has already registered it.

Name Resolution with a NetBIOS Name Server

Who is registered as phoenix?

NetBIOS
Name
Server

That name currently belongs to 192.168.220.102.

網際網路通訊協定第 4 版 (TCP/IPv4) - 內容

一般 其他設定

如果您的網路支援這項功能，您可以取得自動指派的 IP 設定。否則，您必須詢問網路系統管理員正確的 IP 設定。

◉ 自動取得 IP 位址(O)
◯ 使用下列的 IP 位址(S):

IP 位址(I):
子網路遮罩(U):
預設閘道(D):

◉ 自動取得 DNS 伺服器位址(B)
◯ 使用下列的 DNS 伺服器位址(E):

慣用 DNS 伺服器(P):
其他 DNS 伺服器(A):

☐ 結束時確認設定(L)   進階(V)...

確定   取消

進階 TCP/IP 設定

IP 設定 DNS WINS

IP 位址(R)

IP 位址	子網路遮罩
DHCP 已啟用	

新增(A)... 編輯(E)... 移除(V)

預設閘道(F):

閘道	計量

新增(D)... 編輯(T)... 移除(M)

☑ 自動計量(U)
介面計量(N):

確定   取消

SMB – Server Message Block

❑ SMB

- Original designed by IBM with the aim of turning DOS interrupt local file access into a network filesystem
  - ➢ Run on top of netbios
  - ➢ Microsoft has made considerable modifications to the most common used version
- 1990 – Microsoft merged the SMB protocol with LAN Manager
- 1992 – Microsoft merged and add features to SMB protocol in Windows for Workgroup
- 1996 – Microsoft renames SMB as CIFS
  - ➢ Support for symbolic link, hard link, larger file sizes, …
  - ➢ Initial attempt at supporting direct connections over TCP port 445
- 2006 – Microsoft introduced SMB2 with Windows vista
- Windows 7 – SMB 2.1
  - ➢ Performance enhancement with a new opportunistic locking
- Windows 8/Windows Server 2012 – SMB 3.0 (Previously named SMB 2.2)
  - ➢ Enables the use of multiple physical network interfaces

UNIX-Windows communication

❑ SAMBA

- 1991 – Andrew Tridgwell developed the first version of Samba
  - ➢ Using a packet sniffer on DEC Pathworks server software
- A UNIX application that speak SMB protocol
- Can not use the Original Name: Server Message Block (SMB)
  - ➢ Samba
 - ➢ grep -i '^s.*m.*b' /usr/share/dict/words
    - – Napster, Simba

❑ Why samba ?

Applikation		
SMB		
NetBIOS		
NetBEUI	TCP/IP	IPX/SPX
NDIS (2,3,3.1,4,5)-Interface		
Karten-Treiber (MAC)		
Netzwerk-Karte		

What SAMBA can do?

❑ Sharing

- Sharing files or printers just like Microsoft does
- Authenticate user identity just like Microsoft does
- Resolve NetBIOS name just like Microsoft does

Install SAMBA

❑ Using ports

- % cd /usr/ports/net/samba46
  - ➢ Samba 4.6.8
- % portmaster -BD net/samba46

❑ Using package

- % pkg install samba46

```
┌──────────────────── samba46-4.6.8 ────────────────────┐
│ ┌──────────────────────────────────────────────────┐ │
│ │+[x] ADS        Active Directory client support(implies LDAP)│ │
│ │+[x] AD_DC      Active Directory Domain Controller support   │ │
│ │+[ ] CUPS       CUPS printing system support                 │ │
│ │+[x] DEBUG      Build with debugging support                 │ │
│ │+[ ] DEVELOPER  With development support(implies NTVFS)       │ │
│ │+[x] DOCS       Build and/or install documentation           │ │
│ │+[ ] EXP_MODULES Experimental modules(WANT_EXP_MODULES)       │ │
│ │+[x] FAM        File Alteration Monitor support              │ │
│ │+[x] LDAP       LDAP client support                         │ │
│ │+[ ] MANPAGES   Build manpages from DOCBOOK templates       │ │
│ │+[ ] NTVFS      Build *DEPRECATED* NTVFS file server        │ │
│ │+[x] QUOTAS     Disk quota support                          │ │
│ │ ·(+)                                              54%      │ │
│ └──────────────────────────────────────────────────┘ │
│           < OK >              <Cancel>                 │
└────────────────────────────────────────────────────────┘
```

SAMBA components

❑ Configuration files

- /usr/local/etc/smb.conf.sample → /usr/local/etc/smb.conf
  - ➢ chmod 644 smb.conf
- /usr/local/etc/lmhosts

❑ Major execution files

- smbd (/usr/local/sbin/smbd)
  - ➢ Management of sharing directories, files and printers
- nmbd (/usr/local/sbin/nmbd)
  - ➢ Resolve NetBIOS name and manage workgroup
- winbindd (/usr/local/sbin/winbindd)
  - ➢ WINS services
- pdbedit (/usr/local/bin/pdbedit)
  - ➢ Manage the Samba user database
- smbpasswd (/usr/local/bin/smbpasswd)

SAMBA password

❑ samba4 password file
  • Now samba stores accounts and passwords in tdb
    ➢ Default database path: /var/db/samba4
❑ tdb v.s. smbpasswd

```
derek[~] -chiahung- sudo pdbedit -L -v
---------------
Unix username:          chiahung
NT username:
Account Flags:          [U             ]
User SID:               S-1-5-21-3763889141-129722405-4261865294-1000
Primary Group SID:      S-1-5-21-3763889141-129722405-4261865294-513
Full Name:              Chia-Hung Tsai
Home Directory:         \\derek\chiahung
HomeDir Drive:                                          derek[/var/db] -chiahung- sudo pdbedit -w -u chiahung
Logon Script:                                           chiahung:1000:
Profile Path:           \\derek\chiahung\profile        XXXXXXXXXXXXXXXXXXXXXXXXXXXXXXXX:
Domain:                 DEREK                           3CDEC7966A2F9837F9F628DC13CC02AE:
Account desc:                                           [U             ]:
Workstations:                                           LCT-4C39EB51:
Munged dial:
Logon time:             0
Logoff time:            never
Kickoff time:           never
Password last set:      Mon, 12 Jul 2010 00:03:29 CST
Password can change:    Mon, 12 Jul 2010 00:03:29 CST
Password must change:   never
Last bad password   :   0
Bad password count  :   0
Logon hours         :   FFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFFF
---------------
```

12

https://www.samba.org/samba/docs/man/manpages/smbpasswd.5.html

SAMBA password

❑ smbpasswd command

- -a
  - ➢ Add new user
- -d
  - ➢ Let some account in smbpasswd file can not login (to disable)
- -e
  - ➢ Let some disable account resume (to enable)

❑ pdbedit command

- pdbedit -a username
  - ➢ Add new user
- pdbedit -x username
  - ➢ delete user
- pdbedit -L -v
  - ➢ List user
- pdbedit -r -c username
  - ➢ pdbedit -r -c "[DX]" test

SAMBA configuration file

❑ smb.conf

- Sections
  - ➢ Each section in the smb.conf file represents either a share or a meta-service
  - ➢ Global section is special
    - – Global setting
  - ➢ Meta-service
    - – Printer Sharing Setting
    - – Home Sharing Setting

```
# comments
[global]
  para1 = value1
  ...

[printers]
  para2 = value2
  ...

[homes]
  para3 = value3
  ...

[share-dir]
  para4 = value4
  ...
```

SAMBA configuration file – Global Setting (1)

❑ Global Configuration
- workgroup
  - ➢ Group name to join
  - ➢ Ex: workgroup = chwong
- server string
  - ➢ Description of this host
  - ➢ Ex: server string = Samba Server of SA Course
- netbios name
  - ➢ NetBIOS name of this host
  - ➢ Ex: netbios name = sabsd
- Charset Settings
  - ➢ "display charset", "unix charset", "dos charset"
  - ➢ Ex:

    unix charset = CP850
    dos charset = CP850
- hosts allow
  - ➢ Apply to all services, regardless or individual service setting;
  - ➢ Ex: hosts allow = 140.113.235. 140.113.

SAMBA configuration file –
Global Setting (2)

- guest ok (or public = yes)
  - If this is yes, no password is required
  - Ex: guest ok = no
- guest account
  - If guest can use this samba service, any guest request will map to this guest account
  - Ex: guest account = ftp
    - Add this account into your /etc/passwd
  - Otherwise, the user nobody is used
- log file
  - Full path of log file
  - Ex: log file = /var/log/samba/log.%m
- max log size (KB)
  - Ex: max log size = 500

SAMBA configuration file – Global Setting (3)

- security = [share/user/server/domain]
  - ➢ share: no need of id and password to login
  - ➢ user: default option, login with id and password
  - ➢ domain: check id and password by domain controller
  - ➢ ads: check id and password by AD server
  - ➢ server: check id and password by another server
    - – It is highly recommended not to use this feature

  - ➢ Ex:
    - – security = user
    - – passdb backend = tdbsam

SAMBA configuration file –
Global Setting (4)

❑ Example of global setting

```
[global]
        server string = Samba Server Version %v
        unix charset = CP850
        workgroup = MYGROUP
        log file = /var/log/samba/log.%m
        max log size = 50
        usershare allow guests = Yes
        guest account = pcguest
        security = USER
        idmap config * : backend = tdb
        cups options = raw
```

Samba parameters

❑ Default parameters in samba
- %m
  - ➢ Client NetBIOS name
- %M
  - ➢ Client Hostname
- %I
  - ➢ Client IP
- %L
  - ➢ Samba server NetBIOS name
- %h
  - ➢ Samba server Hostname
- %H
  - ➢ User home directory
- %U
  - ➢ Login name
- %T
  - ➢ Current Date time

# SAMBA configuration file – Home Sharing Setting (1)

❑ Home sharing setting

- comment
    - ➢ Description of this directory
- path
    - ➢ Sharing directory path
- browseable
    - ➢ Display sharing name or not
- read only , writeable
- admin users = $username
- valid users = %S (write list)
    - ➢ Only users on this can write content if read only
- create mode / create mask
    - ➢ Default permission when file is created
- directory mode / directory mask
    - ➢ Default permission when directory is created
- guest ok (or public = yes)

SAMBA configuration file – Sharing Setting (2)

❑ Example of image sharing

```
[Image]
    comment              = Book Picture
    path                 = /home/image
    read only            = no
    public               = yes
    writable             = yes
    create mode          = 0664
    directory mode       = 0775
```

この部分は処理しない

SAMBA configuration file Additional tuning

❑ Disable printer
- load printers = no
- printing = bsd
- printcap name = /dev/null
- disable spoolss = yes

❑ Performance tuning
- max protocol = SMB2
- socket options = TCP_NODELAY
- socket options = TCP_NODELAY SO_RCVBUF=8192 SO_SNDBUF=8192
- read size
- read prediction
- …

Starting SAMBA

❑ Script

- /usr/local/etc/rc.d/samba {start|stop}

- /etc/rc.conf

  ➢ samba_enable="YES"

    – smbd_enable="YES"

    – nmbd_enable="YES"

  ➢ winbindd_enable="YES"

smbstatus

❑ Report on current Samba connections

```
hscc[~] -chiahung- smbstatus

Samba version 3.0.37
PID     Username        Group       Machine
-------------------------------------------------------------
47945   hscc            hscc        hscc-d30aedc531 (140.113.240.124)
48533   Pegasus         hscc        simba-pc    (140.113.240.135)
47944   zn               hscc       bdeca39d90d4 (140.113.240.133)


Service     pid         machine             Connected at
-------------------------------------------------------------
zn          47944       bdeca39d90d4        Mon Oct 18 17:12:02 2010
hscc        47945       hscc-d30aedc531     Mon Oct 18 17:12:02 2010
Pegasus     48533       simba-pc            Mon Oct 18 17:58:46 2010

Locked files:
Pid         Uid     DenyMode    Access      R/W     Oplock          SharePath   Name    Time
---------------------------------------------------------------------------------------------
47947       509     DENY_NONE  0x100001     RDONLY  NONE            /home/hscc  UG/Films/[USA
47946       509     DENY_NONE  0x100001     RDONLY  NONE            /home/hscc  UG/Animation
```

Tool: smbclient (1)

❑ A client program that can talk to an SMB server

❑ Usage:

- -L [hostname]
    - ➢ List sharable resource
- -U [username]
    - ➢ Login with username
- smbclient -L host_IP -U user_ID

Tool: smbclient (2)

```
hsccws5[~] -chiahung- smbclient -L hscc -U chiahung
Enter chiahung's password:
Domain=[HSCCLAB] OS=[Unix] Server=[Samba 3.0.37]

        Sharename           Type           Comment
        ---------           ----           -------
        IPC$                IPC            IPC Service (HSCC SAMBA)
        chiahung            Disk           Home Directories
Domain=[HSCCLAB] OS=[Unix] Server=[Samba 3.0.37]

        Server              Comment
        ---------           -------
        HSCC                HSCC SAMBA

        Workgroup           Master
        ---------           -------
        EC219               EC219
        HSCCLAB             HSCC
        LAB635              JJSU-LABPC
        LAB636              2AMW1GP6PMLTL77
```

Tool: smbtree

❑ A smb browser program in text mode

❑ Usage:

- -b Query network nodes by sending requests as broadcasts instead of querying the local master browser.

- -D Only print a list of all the domains known on broadcast or by the master browser

- -S Only print a list of all the domains and servers responding on broadcast or known by the master browser.

❑ smbtree -b

```
mango@mango:~ $ smbtree
WORKGORUP
          \\MANGOCOLD
SANA
          \\SATA                              sata server
                    \\SATA\IPC$               IPC Service
(sata server)

                    \\SATA\Video              ftp directory
                    \\SATA\Image              test directory
```

Tool: mount_smbfs

❑ Mount a shared resource from an SMB file server

❑ Usage:

- -I

  ➢ Do not use NetBIOS name resolver and connect directly to host, which can be either a valid DNS name or an IP address.

- -N

  ➢ Do not ask for a password.

❑ Mount_smbfs (-I IP or host name) -N '//NetBIOS name/dir' mount_point

Tool: testparm

❑ check an smb.conf configuration file for internal correctness

❑ Usage

- testparm /usr/local/etc/smb4.conf

- Load smb config files from /usr/local/etc/smb4.conf
  Processing section "[homes]"
  Processing section "[printers]"
  Processing section "[public]"
  Loaded services file OK.
  Server role: ROLE_STANDALONE

  Press enter to see a dump of your service definitions

SWAT (1)

❑ Edit /etc/inetd.conf

- Unmark

swat	stream	tcp	nowait/400	root	/usr/local/sbin/swat	swat

❑ Restart inetd

❑ Browse http://sabsd.cs.nctu.edu.tw:901/

SWAT (2)

❑ Root access