Input/output

Victor Eijkhout, Susan Lindsey

Fall 2019



Formatted output



Formatted output

- cout uses default formatting
- Possible: pad a number, use limited precision, format as hex/base2, etc
- Many of these output modifiers need

#include <iomanip>



Default unformatted output

Code:

```
for (int i=1; i<200000000; i*=10)
  cout << "Number: " << i << endl;
cout << endl;</pre>
```

Output [io] cunformat:

Number: 1
Number: 10
Number: 100
Number: 1000
Number: 10000
Number: 100000
Number: 1000000
Number: 10000000
Number: 100000000



Reserve space

You can specify the number of positions, and the output is right aligned in that space by default:

Code:

Output [io] width:

```
Width is 6:
Number: 1
Number: 100
Number: 1000
Number: 10000
Number: 100000
Number: 1000000
Number: 1000000
Number: 10000000
```

Number: 100000000

Width is 6: 123

Padding character

Normally, padding is done with spaces, but you can specify other characters:

```
Code:
                                         Output
                                         [io] formatpad:
#include <iomanip>
using std::setfill;
                                         Number: ....1
using std::setw;
                                         Number: ....10
 /* ... */
                                         Number: ...100
  for (int i=1; i<200000000; i*=10)
                                         Number: ..1000
    cout << "Number: "
                                         Number: .10000
         << setfill('.') << setw(6) <<
                                         Number: 100000
    i
                                         Number: 1000000
         << endl:
                                         Number: 10000000
                                         Number: 100000000
```

Note: single quotes denote characters, double quotes denote strings.



Left alignment

Instead of right alignment you can do left:

Code:

Output [io] formatleft:

```
Number: 1.....
Number: 10....
Number: 100...
Number: 1000..
Number: 10000.
Number: 100000
Number: 1000000
Number: 10000000
Number: 100000000
```



Number base

Finally, you can print in different number bases than 10:

Code:

```
#include <iomanip>
using std::setbase;
using std::setfill;
   /* ... */
   cout << setbase(16) << setfill(' ');
   for (int i=0; i<16; i++) {
      for (int j=0; j<16; j++)
           cout << i*16+j << " ";
      cout << endl;
   }</pre>
```

Output [io] format16:

```
0 1 2 3 4 5 6 7 8 9 a b c d e
  11 12 13 14 15 16 17 18 19
20 21 22 23 24 25 26 27 28 29
30 31 32 33 34 35 36 37 38 39
40 41 42 43 44 45 46 47 48 49
50 51 52 53 54 55 56 57 58 59
60 61 62 63 64 65 66 67 68 69
70 71 72 73 74 75 76 77 78 79
80 81 82 83 84 85 86 87 88 89
90 91 92 93 94 95 96 97 98 99
a0 a1 a2 a3 a4 a5 a6 a7 a8 a9
b0 b1 b2 b3 b4 b5 b6 b7 b8 b9
c0 c1 c2 c3 c4 c5 c6 c7 c8 c9
d0 d1 d2 d3 d4 d5 d6 d7 d8 d9
e0 e1 e2 e3 e4 e5 e6 e7 e8 e9
f0 f1 f2 f3 f4 f5 f6 f7 f8 f9
```



Exercise 1

Make the first line in the above output align better with the other lines:

```
00 01 02 03 04 05 06 07 08 09 0a 0b 0c 0d 0e 0f 10 11 12 13 14 15 16 17 18 19 1a 1b 1c 1d 1e 1f 20 21 22 23 24 25 26 27 28 29 2a 2b 2c 2d 2e 2f etc
```



Exercise 2

Use integer output to print real numbers aligned on the decimal:

1.345

23.789

456.1234

Use four spaces for both the integer and fractional part; test only with numbers that fit this format.



Hexadecimal

Hex output is useful for pointers (chapter ??):

Code:

Back to decimal:

```
cout << hex << i << dec << j;</pre>
```

Output [pointer] coutpoint:

```
address of i, decimal: 140732 address of i, hex : 0x7ffe
```



Floating point formatting



Floating point precision

Use setprecision to set the number of digits before and after decimal point:

```
Code:
                                           Output
                                           [io] formatfloat:
#include <iomanip>
using std::left;
                                           1.235
using std::setfill;
                                           12.35
using std::setw;
                                           123.5
using std::setprecision;
                                           1235
  /* ... */
                                           1.235e+04
  x = 1.234567;
                                           1.235e+05
  for (int i=0; i<10; i++) {
                                           1.235e+06
    cout << setprecision(4) << x <<</pre>
                                           1.235e+07
    endl:
                                           1.235e+08
    x *= 10:
                                           1.235e+09
```

(Notice the rounding)



Fixed point precision

Fixed precision applies to fractional part:

```
Code:
                                            Output
                                            [io] fix:
x = 1.234567;
cout << fixed;</pre>
                                            1.2346
for (int i=0; i<10; i++) {
                                            12.3457
  cout << setprecision(4) << x << endl;</pre>
                                            123.4567
  x *= 10;
                                            1234.5670
                                            12345.6700
                                            123456.7000
                                            1234567.0000
                                            12345670.0000
                                            123456700.0000
                                            1234567000.0000
```



Aligned fixed point output

Combine width and precision:

```
Code:
                                            Output
                                            [io] align:
  x = 1.234567;
  cout << fixed;</pre>
                                                 1.2346
  for (int i=0; i<10; i++) {
                                                12.3457
    cout << setw(10) << setprecision(4)</pre>
                                              123.4567
     << x
                                             1234.5670
          << endl;
                                            12345.6700
    x *= 10:
                                            123456.7000
                                            1234567.0000
                                            12345670.0000
                                            123456700.0000
                                            1234567000.0000
```



Scientific notation

```
cout << "Combine width and precision:" << endl;
x = 1.234567;
cout << scientific;
for (int i=0; i<10; i++) {
   cout << setw(10) << setprecision(4) << x << endl;
   x *= 10;
}</pre>
```



Output

Combine width and precision:

- 1.2346e+00
- 1.2346e+01
- 1.2346e+02
- 1.2346e+03
- 1.2346e+04
- 1.2346e+05
- 1.2346e+06
- 1.2346e+07
- 1.2346e+08
- 1.2346e+09



File output



Text output to file

Streams are general: work the same for console out and file out.

```
#include <fstream>
Use:
#include <fstream>
using std::ofstream;
   /* ... */
   ofstream file_out;
   file_out.open("fio_example.out");
   /* ... */
   file_out << number << endl;
   file_out.close();</pre>
```



Binary output

```
ofstream file_out;
file_out.open
   ("fio_binary.out",ios::binary);
/* ... */
file_out.write( (char*)(&number),4);
```

