

How To Train Lora / Fine-Tune Anima Base Model

Anima Portable Standalone Trainer — Part 1: Installation

This is **Part 1** of a **3-Part** series.

- **Part 1: Installation** ← You are here
- [Part 2: How to Train a LoRA](#)
- [Part 3: How to Finetune a Model](#)

⚠ **Resource Notice:** Due to recent updates on the CivitAI platform, some file attachments in this article may no longer be visible or accessible. For all resources related to this article — including additional tools, files, and miscellaneous assets — please refer [HERE](#)

What Is the Anima Portable Standalone Trainer?

The **Anima Portable Standalone Trainer** is a completely self-contained, browser-based training tool for Lora / Fine-tuning the **Anima** diffusion model — a cutting-edge architecture built on a **Diffusion Transformer (DiT)** backbone with a **Qwen3-0.6B** text encoder and a custom image VAE.

The key selling point: **no dependency hell**. The installer sets up its own isolated Python environment (via Miniconda) that is completely separate from anything else on your system. You don't need to worry about Python versions, virtual environments, or conflicting packages. Just run a few **.bat** files and you're training.

The tool is built on top of the excellent [Kohya-sd-scripts](#) core, heavily modified to support the Anima architecture.

⚙ System Requirements

Before you start, make sure your machine meets the following:

- Requirement Minimum Spec **OS** Windows 10 / 11 (64-bit)
- **GPU** NVIDIA GPU with CUDA
- **VRAM (LoRA)** 8 GB minimum (12 GB recommended)
- **VRAM (Full Finetune)** 12 GB minimum
- **System RAM** 16 GB
- **Disk Space** ~15 GB free
- **Node.js** v18 or later

📘 If you don't have Node.js v18+ installed, download it from [nodejs.org](#) before proceeding.

📦 Step 1 — Download the Repository

Head over to the GitHub repository and download / clone the project:

→ [github.com/official-imvoid/Anima-Portable-Standalone-Trainer](#)

Click the green **< > Code** button → **Download ZIP**, then extract it to a location of your choice.

Once extracted, your folder should look like this:

```
Anima-Portable-Standalone-Trainer/
├─ Anima_lora_configs.toml
├─ anima_train.py
├─ anima_train_network.py
├─ Cmd.bat                ← Opens a pre-configured terminal
├─ download_models.bat    ← Downloads the required model weights
├─ LICENSE
├─ README.md
├─ requirements.txt
├─ SetEnv.bat             ← Fixes paths if you move the folder
├─ setup.bat              ← Installs the Conda+Python environment
├─ setup.py
├─ train_network.py
├─ training-ui/           ← The web UI lives here
│   └─ start_windows.bat  ← Launches the UI
├─ patching/
└─ wd_parallel_pkg/
```

📦 Step 2 — Download the Model Weights

Double-click **download_models.bat**.

This script will automatically download the three required base model files and place them in the **models/** directory:

- **anima_baseV10.safetensors** — the main Anima DiT model
- **qwen_3_06b_base.safetensors** — the Qwen3 text encoder
- **qwen_image_vae.safetensors** — the custom image VAE

The script may prompt you for a **Hugging Face token**. This is optional for most downloads, but if you hit access errors, generate a free token at [huggingface.co/settings/tokens](#).

⌚ The models total roughly **10–12 GB**, so download time will depend on your connection speed.

🔧 Step 3 — Run the Setup

Once the models are downloaded, double-click **setup.bat**.

This will:

- Install an isolated **Miniconda** environment (your system Python is untouched)
- Install all required dependencies from **requirements.txt** — including PyTorch with CUDA 12.8, transformers, accelerate, and all supporting libraries

This step takes several minutes. Let it run to completion. You should see progress output scrolling in the terminal window.

you can edit **requirements.txt** for pytorch-cuda 12.6 or according to your hardware support

✅ When setup is complete, the terminal will confirm and close (or pause). No errors should appear in red. If they do, check that your CUDA drivers are up to date.

	Anima_lora_configs.toml	18-05-2026 02:31	Toml Source File	2 KB
	anima_train.py	18-05-2026 02:31	Python File	56 KB
	anima_train_network.py	18-05-2026 02:31	Python File	26 KB
	Cmd.bat	18-05-2026 02:31	Windows Batch File	1 KB
	download_models.bat	18-05-2026 02:31	Windows Batch File	2 KB
	LICENSE	18-05-2026 02:31	File	3 KB
	README.md	18-05-2026 02:31	Markdown Source...	6 KB
	requirements.txt	18-05-2026 02:31	Text Document	1 KB
	SetEnv.bat	18-05-2026 02:31	Windows Batch File	1 KB
	setup.bat	18-05-2026 02:31	Windows Batch File	4 KB
	setup.py	18-05-2026 02:31	Python File	1 KB
	train_network.py	18-05-2026 02:31	Python File	109 KB

🚀 Step 4 — Launch the Training UI

Navigate into the **training-ui** folder and double-click **start_windows.bat** .

A terminal window will open. You should see output like this:

```
patching 19-05-2026 20:53
training-ui 19-05-2026 20:54
wd_parallel_pkg 19-05-2026 20:53
anima_gen.py 18-05-2026 02:31

package.json 18-05-2026 02:31
package-lock.json 18-05-2026 02:40
server.js 19-05-2026 19:54
start_windows.bat 18-05-2026 02:31
```

```
C:\WINDOWS\system32\cmd. x + v

=====
PROJECT STARTER
=====

Launching Training UI...

Open your browser at: http://localhost:3000

Press Ctrl+C to stop the server.

[setup] cuda_direct_backend verified.
[setup] wd_parallel verified.
Template validated: config_template.toml
Template validated: dataset_template.toml
Anima Training UI running at http://localhost:3000
```

Once you see **"Anima Training UI running at http://localhost:3000"**, open your browser and navigate to: [http://localhost:3000](#)

You're in! The Web UI is now running.

🔄 Moving the Folder Later?

If at any point you move **Anima-Portable-Standalone-Trainer** folder to a different drive or location, **you must double-click SetEnv.bat once** before doing anything else. This script automatically fixes all the internal environment paths to match the new location, preventing errors during training.

Note: If you're using RunPod, do use my [referral link](#)! ❤