

Kohya_SS Training Guide

Resume Training · Accelerate Configuration · GPU Driver Setup

1. Resuming a Training Run

To resume a training session from a saved checkpoint, the optimizer state must be preserved alongside the model weights. This is achieved by enabling the **Save Training State** option prior to the initial training run.

Procedure

1. Navigate to **Training Parameters** → **Advanced**.
2. Enable the **Save training state** checkbox.
3. Proceed with training as normal. The full optimizer state will be saved alongside each model checkpoint.
4. To resume, paste the path to the most recent saved-state folder into the **Resume from saved training state** field and start training.




Figure 1 — Training Parameters → Advanced: Save training state and Resume field highlighted

Example — last-state path (Windows)

```
C:\kohya_ss\output\your-lora-name\last-state
```

Important If **Save Training State** is not enabled before the run, resumption is not possible — training will restart from step 0.

2. Accelerate Path Error

On certain older installations of Kohya_SS, the following error may appear at launch:

Error message

```
Unable to create process using "C:\Users\OLD_USER\..."
```

Resolution

Reinstall a known-compatible version of Accelerate and reconfigure it:

Shell

```
pip install accelerate==0.31.0
accelerate config
```

Accelerate Configuration Settings

Parameter	Value
Compute environment	This machine
Distributed type	No distributed training
Run training on CPU only	No
Enable DeepSpeed	No
GPU ID(s) to use	0
Mixed precision type	fp16

Note Restart the Kohya_SS GUI after running `accelerate config` for the changes to take effect.

3. GPU Driver & Dependency Setup

If the default `requirements.txt` — in particular the `xformers` entry — causes installation errors, remove the `torch` line from that file and install PyTorch manually using the commands appropriate for your GPU generation.

NVIDIA RTX 50 Series (5060, 5070, 5080, 5090)

Shell — CUDA 12.8

```
pip install --no-cache-dir torch==2.7.0 torchvision==0.22.0 torchaudio==2.7.0 \
  --index-url https://download.pytorch.org/whl/cu128
pip install xformers==0.0.30
pip install -r requirements.txt
```

NVIDIA RTX 30 & 40 Series (3060, 3070, 4060, 4070, etc.)

Shell — CUDA 12.1

```
# Python 3.10.13 is recommended for this configuration
pip install torch==2.1.2+cu121 torchvision==0.16.2+cu121 torchaudio==2.1.2+cu121 \
  --index-url https://download.pytorch.org/whl/cu121
pip install xformers==0.0.23.post1
pip install -r requirements.txt
```

4. Additional Resources

The following resources provide supplementary materials, files, and tooling referenced in this guide.

Resource	URL
Article files & miscellaneous tools	github.com/official-imv0iid/Random/tree/main/Civitai-Articles
RunPod cloud GPU platform	runpod.io?ref=od0l9p8p

Note Following recent updates to the CivitAI platform, certain file attachments may no longer be accessible directly on that site. All associated resources have been mirrored to the GitHub repository listed above.