## Per-user web directories

Available Languages: en | es | fr | ja | ko | tr

On systems with multiple users, each user can be permitted to have a web site in their home directory using the <u>UserDir</u> directive. Visitors to a URL

http://example.com/~username/ will get content out of the home directory of the user "username", out of the subdirectory specified by the <u>UserDir</u> directive.

Note that, by default, access to these directories is **not** enabled. You can enable access when using <u>UserDir</u> by uncommenting the line:

#Include conf/extra/httpd-userdir.conf

in the default config file <code>conf/httpd.conf</code>, and adapting the <code>httpd-userdir.conf</code> file as necessary, or by including the appropriate directives in a <a href="mailto:subset: line block">Subset: line block within the main config file</a>.

### Per-user web directories

DirectoryMatch
AllowOverride

## Setting the file path with UserDir

The <u>UserDir</u> directive specifies a directory out of which per-user content is loaded. This directive may take several different forms.

If a path is given which does not start with a leading slash, it is assumed to be a directory path relative to the home directory of the specified user. Given this configuration:

### UserDir public html

the URL http://example.com/~rbowen/file.html will be translated to the file path /home/rbowen/public html/file.html

If a path is given starting with a slash, a directory path will be constructed using that path, plus the username specified. Given this configuration:

### UserDir /var/html

the URL http://example.com/~rbowen/file.html will be translated to the file path /var/html/rbowen/file.html

If a path is provided which contains an asterisk (\*), a path is used in which the asterisk is replaced with the username. Given this configuration:

```
UserDir /var/www/*/docs
```

the URL http://example.com/~rbowen/file.html will be translated to the file path /var/www/rbowen/docs/file.html

Multiple directories or directory paths can also be set.

```
UserDir public html /var/html
```

- Per-user web directories
- Setting the file path with UserDir
- Redirecting to external URLs
- Restricting what users are permitted to use this feature
- Enabling a cgi directory for each user
- Allowing users to alter configuration

#### See also

- <u>Mapping URLs to the</u>
   <u>Filesystem</u>
- Comments

For the URL http://example.com/~rbowen/file.html, Apache will search for ~rbowen. If it isn't found, Apache will search for rbowen in /var/html. If found, the above URL will then be translated to the file path /var/html/rbowen/file.html

## Redirecting to external URLs

The <u>UserDir</u> directive can be used to redirect user directory requests to external URLs.

```
UserDir http://example.org/users/*/
```

The above example will redirect a request for

http://example.com/~bob/abc.html to
http://example.org/users/bob/abc.html.

## Restricting what users are permitted to use this feature

Using the syntax shown in the UserDir documentation, you can restrict what users are permitted to use this functionality:

```
UserDir disabled root jro fish
```

The configuration above will enable the feature for all users except for those listed in the disabled statement. You can, likewise, disable the feature for all but a few users by using a configuration like the following:

```
UserDir disabled
UserDir enabled rbowen krietz
```

See <u>UserDir</u> documentation for additional examples.

# Enabling a cgi directory for each user

In order to give each user their own cgi-bin directory, you can use a <a href="Linearing"><u>Linearing</u></a> directive to make a particular subdirectory of a user's home directory cgi-enabled.

```
<Directory "/home/*/public_html/cgi-bin/">
   Options ExecCGI
   SetHandler cgi-script
</Directory>
```

Then, presuming that <code>UserDir</code> is set to <code>public\_html</code>, a cgi program <code>example.cgi</code> could be loaded from that directory as:

```
http://example.com/~rbowen/cgi-bin/example.cgi
```

# Allowing users to alter configuration

If you want to allows users to modify the server configuration in their web space, they will need to use .htaccess files to make these changes. Ensure that you have set <a href="AllowOverride">AllowOverride</a> to a value sufficient for the directives that you want to permit the users to modify. See the <a href="https://htaccess.tutorial">httaccess.tutorial</a> for additional details on how this works.