This chapter provides a guide on how to install WendzelNNTPd 2.x.

Linux/*nix/BSD

To install WendzelNNTPd from source you need to download the provided archive file (e.g., wendzelnntpd-2.0.0.tar.gz) file. Extract it and run ./configure. Please note that configure indicates missing libraries and packages that you may first need to install using the package system of your operating system.

```
$ tar -xzf wendzelnntpd-2.0.0.tgz
$ cd wendzelnntpd
$ ./configure
...
```

Please refer to Section Test

```
<connector>
    ;; enables STARTTLS for this port
    ;enable-starttls
               119
   port
               127.0.0.1
   listen
    ;; configure SSL server certificate (required)
    ;tls-server-certificate "/usr/local/etc/ssl/server.crt"
    ;; configure SSL private key (required)
    ;tls-server-key "/usr/local/etc/ssl/server.key"
    ;; configure SSL CA certificate (required)
    ;tls-ca-certificate "/usr/local/etc/ssl/ca.crt"
    ;; configure TLS ciphers for TLSv1.3
    ;tls-cipher-suites "TLS_AES_128_GCM_SHA256"
    ;; configure TLS ciphers for TLSv1.1 and TLSv1.2
    ;tls-ciphers "ALL:!COMPLEMENTOFDEFAULT:!eNULL"
    ;; configure allowed TLS version (1.0-1.3)
    ;tls-version "1.2-1.3"
    ;; possibility to force the client to authenticate
    ;;with client certificate (none | optional | require)
    ;tls-verify-client "required"
    ;; define depth for checking client certificate
    ;tls-verify-client-depth 0
    ;; possibility to use certificate revocation list (none | leaf | chain)
    ;tls-crl "none"
    ;tls-crl-file "/usr/local/etc/ssl/ssl.crl"
</connector>
```

1. On some nix-like operating systems you need to first run gzip -d wendzelnntpd-VERSION.tgz and then tar -xf wendzelnntpd-VERSION.tar instead of letting tar* do the whole job. ←