

6单,普通,但是不平凡。

፟ 目录视图

₩ 摘要视图

RSS 订阅

6寸智能手机















rolex+劳力士















访问: 151492次

积分: 2400

等级: 8100 5

排名: 第16080名

原创: 82篇 转载: 15篇

译文: 2篇 评论: 56条

Android adb bugreport工具分析和使用

标签: android bugreport

实、物联网(评论送书)

2016-07-19 11:53

异步赠书:9月重磅新书升级,本本经典 SDCC 2017之区块链技术实战线上峰会 程序员9月书讯

5726人阅读

评论(0)

收症

Ⅲ 分类:

Android升华之路之系统篇(6)▼

▮ 版权声明:本文为博主原创文章,未经博主允许不得转载。

目录(?)

bugreport是什么,怎么用

Android系统想要成为一个功能完备,生态繁荣的操作系统,那就 1t 固态硬盘

用开发中, app程序的调试分析是日常生产中进程会进行的工作。 🖐 🔌 🧰 💎 🔘























数据结构与算法 (6)

开源软件框架 (1)

JAVA学习 (1)

文章存档


2017年09月 (1)

2017年03月 (1)

统平台和某个app在运行一段时间之内的所有信息,专门开发了bugreport工具。这个工具使用起来十分简单,只要在终端执行(linux或者win):

1 adb bugreport > bugreport.txt

即可生成bugreport文件。但是有一个问题是,这个生成的文件有的时候异常庞大,能够达到15M+,想一想对于一个txt文本格式的文件内容长度达到了15M+是一个什么概念,如果使用文本工具打开查看将是一个噩梦。因此google针对android 5.0(api 21)以上的系统开发了一个叫做battery historiar这个工具就是用来解析这个txt文本文件,然后使用web图形的形式展现出来,这样出来的较化,更加可读。它的基本界面像下面这个样子:





6寸智能手机













rolex+劳力士

















Android ActivityManagerServic... (6) SQLite实现在线电子词典 (3) Android Settings (Preferences) ... (2) C语言编写五子棋程序 (2)

(2) Binary Search Tree C语言实现

(2) Android ActivityManagerServic...

求一个文本文件中有多少个单... (1) Brightness

CPU running

Charging on

Charging status

Health

IobScheduler

Kernel only uptime

Level 8

Package active

Partial wakelock 10

Phone scanning 11

Phone state 12

Plug 13

Plugged 14

Screen 15

16 Temperature

17 Top app

Voltage 18

Wifi on 19

Wifi running 20

21 Wifi supplicant

数据还是比较详细的。

当然,同样的bugreport数据也可以有不同的解析和阅读方式,你如

话,你还有别的选择,那就是选择Sony开源的ChkBugReport,这

视角去解读bugreport文件,界面简单明了:





6寸智能手机













rolex+劳力士













Android 6.0指纹识别App开发demo

白萝卜炒肉 : 你好 博感 感谢您写的这详细 主 小弟想请教下 指纹解锁超时后会进入onA uthenticationE...

Android 6.0指纹识别App开发demo

白萝卜炒肉:你好 博感 感谢您写的这详细 主 小弟想请教下 指纹解锁超时后会进入onA uthenticationE...

Android 6.0指纹识别App开发demo

createchance:@qaz349293703:你可以看下compat类的实现,个人感觉可能是miui的rom兼容问题。



这个项目的文档:

http://developer.sonymobile.com/2012/01/25/new-bugreport-analysis-t

开源地址首页:

https://github.com/sonyxperiadev/ChkBugReport

这里说明一下,笔者使用过ChkBugReport这个工具,感觉很不错外ChkBugReport这个工具还有一点bug,不过不影响使用。





bugreport的原理是什么?

下面我们简要分析一下adb bugreport运行的原理。我们知道,使用bugreport只要执行adb bugreport命令就可以了,因此我们的分析肯定是从adbd这个daemon进程开始,我们查看这个进程的代码的时候发现这里处理了bugreport选项:

adb_commandline@system/core/adb/commandline.cpp

```
else if (!strcmp(argv[0], "bugreport")) {
   if (argc != 1) return usage();
   return send_shell_command(ttype, serial, "shell:bugreport");
}
```

我们可以清楚地看到,这里判断如果附带的参数是bugreport的话,那就直接调用send_shell数处理,这个函数的代码比较简单,我们就不分析了,这个函数的功能就是使用shell执行参令,因此我们这里相当于执行了bugreport命令。

在android设备中, bugreport命令存在于system/bin/目录下,这是一个可执行文件,所以我们

可执行文件实现的地方,它的实现代码在/frameworks/native/cmds/

Name		Date	Size
		13-0ct-2015	4 KiB
Android.mk	HAD	13-0ct-2015	198
bugreport.cpp	H A D	13-0ct-2015	2.9 KiB

我们看到,bugreport的实现是比较简单的,只有一个Android.mk和Android.mk文件:





6寸智能手机













rolex+劳力士















```
1 LOCAL PATH:= $(call my-dir)
 2 include $(CLEAR VARS)
 4 LOCAL SRC FILES:= bugreport.cpp
 6 LOCAL MODULE:= bugreport
 8 LOCAL CFLAGS := -Wall
10 LOCAL SHARED LIBRARIES := libcutils
12 include $(BUILD EXECUTABLE)
13
```

这里我们看到该目录下的代码会被编译成一个名字叫做bugreport的可执行文件,这就是我们

现在我们看一下bugreport.cpp文件的实现,这个文件中代码比较简单,只有一个main函数:

```
// This program will trigger the dumpstate service to start a call to
    // dumpstate, then connect to the dumpstate local client to read the
    // output. All of the dumpstate output is written to stdout, including
    // any errors encountered while reading/writing the output.
     int main() {
     // Start the dumpstate service.
      property_set("ctl.start", "dumpstate");
 8
 9
      // Socket will not be available until service starts.
10
      int s;
11
      for (int i = 0; i < 20; i++) {
12
       s = socket_local_client("dumpstate", ANDROID_SOCKET_
13
                     SOCK_STREAM);
14
       if (s \ge 0)
        break;
15
       // Try again in 1 second.
16
       sleep(1);
17
18
19
      if (s == -1) {
20
```





```
21
       printf("Failed to connect to dumpstate service: %s\n", strerror(errno));
22
       return 1;
23
24
25
      // Set a timeout so that if nothing is read in 3 minutes, we'll stop
26
      // reading and quit. No timeout in dumpstate is longer than 60 seconds,
27
      // so this gives lots of leeway in case of unforeseen time outs.
28
      struct timeval tv;
29
      tv.tv_sec = 3 * 60;
      tv.tv usec = 0;
30
31
      if (setsockopt(s, SOL_SOCKET, SO_RCVTIMEO, &tv, sizeof(tv)) == -1) {
32
       printf("WARNING: Cannot set socket timeout: %s\n", strerror(errno));
33
34
35
      while (1) {
36
       char buffer[65536];
37
       ssize_t bytes_read = TEMP_FAILURE_RETRY(read(s, buffer, sizeof(buffer)));
38
       if (bytes_read == 0) {
39
        break;
40
       } else if (bytes_read == -1) {
41
        // EAGAIN really means time out, so change the errno.
42
        if (errno == EAGAIN) {
43
         errno = ETIMEDOUT;
44
45
        printf("\nBugreport read terminated abnormally (%s).\
46
        break;
47
48
49
       ssize_t bytes_to_send = bytes_read;
50
       ssize_t bytes_written;
51
       do {
52
        bytes_written = TEMP_FAILURE_RETRY(write(STDOUT_F
53
                                buffer + bytes_read - bytes_to_
54
                                bytes_to_send));
55
        if (bytes written == -1) {
```

rolex+劳力士



```
Android adb bugreport工具分析和使用 - Android Fans - CSDN博客
```

```
printf("Failed to write data to stdout: read %zd, trying to send %zd (%s)\n",
56
57
              bytes read, bytes to send, strerror(errno));
58
         return 1:
59
60
        bytes to send -= bytes written;
61
       } while (bytes written != 0 && bytes to send > 0);
62
63
64
      close(s);
     return 0;
65
66
```

这里的代码非常简单,主要的逻辑就是:

- 1.启动dumpstate service
- 2. 和dumpstate service建立socket链接
- 3. 从socket中读取数据,并且答应到stdout中
- 4. 读取完成之后关闭socket, 然后退出

因此,我们分析的重点需要转移到dumpstate中了。这里说明一下,前面启动dumpstate service

用系统属性来实现,这个属性的改变消息会被init进程收到,然后dumpstate其实也是一个可执行文件,也存在于system/bin目录下。dumpstate,只是bugreport将dumpstate包装了一下而已。

现在我们需要分析一下dumpstate的实现,它的实现代码在:frame们看下这个目录下的代码结构:

TELETA CENTRAL CONTROL CONTRO



6寸智能手机





rolex+劳力士











Name Date Size 13-0ct-2015 4 KiB Android.mk H A D 13-0ct-2015 510 dumpstate.c H A D 13-0ct-2015 26.2 KiB dumpstate.h H A D 13-0ct-2015 2.8 KiB libdumpstate default.c H A D 13-0ct-2015 677 utils.c H A D 13-Oct-2015 24.1 KiB

这里的代码也是十分简单,只要少数的几个实现文件,其中main函数在dumpstate.c文件中,这个main函 数我们这里不详细分析了,总结下它的主要工作:

- 1. 根据启动参数,初始化相关资源
- 2. 如果启动参数中带有-s的话(init启动会加上这个参数),就表示使用socket,那么就启动 在这个socket中等待链接。
- 3. 如果client端(也就是bugreport进程)链接成功,那就初始化所要用到的内存,并且设置,以为现代的 优先级,防止被OOM干掉。
- 4. 然后使用vibrator震动一下(如果设备有这个硬件的话),提示用户开始截取log了
- 5. 调用dumpstate函数开始真正的dump工作

6. dump完成之后再次调用vibrator震动3次,提示用户dump完成。

现在我们看下dumpstate函数的实现:

/* dumps the current system state to stdout */

static void dumpstate() {

unsigned long timeout;

time_t now = time(NULL);

- char build[PROPERTY_VALUE_MAX], fingerprint[PROPER]
- char radio[PROPERTY_VALUE_MAX], bootloader[PROPER]
- char network[PROPERTY VALUE MAX], date[80];
 - char build_type[PROPERTY_VALUE_MAX];















```
9
10
      property get("ro.build.display.id", build, "(unknown)");
11
      property get("ro.build.fingerprint", fingerprint, "(unknown)");
12
      property_get("ro.build.type", build_type, "(unknown)");
13
      property get("ro.baseband", radio, "(unknown)");
14
      property get("ro.bootloader", bootloader, "(unknown)");
15
      property_get("gsm.operator.alpha", network, "(unknown)");
16
      strftime(date, sizeof(date), "%Y-%m-%d %H:%M:%S", localtime(&now));
17
18
      printf("=========\n"):
19
      printf("== dumpstate: %s\n", date);
      printf("========\n"):
20
21
22
      printf("\n");
23
      printf("Build: %s\n", build);
24
      printf("Build fingerprint: '%s'\n", fingerprint); /* format is important for other tool
25
      printf("Bootloader: %s\n", bootloader);
26
      printf("Radio: %s\n", radio);
27
      printf("Network: %s\n", network);
28
29
      printf("Kernel: ");
30
      dump_file(NULL, "/proc/version");
31
      printf("Command line: %s\n", strtok(cmdline buf, "\n"));
                                                                                                关闭
32
      printf("\n");
33
34
      dump_dev_files("TRUSTY VERSION", "/sys/bus/platform/
35
      run_command("UPTIME", 10, "uptime", NULL);
36
      dump_files("UPTIME MMC PERF", mmcblk0, skip_not_sta
37
      dump_file("MEMORY INFO", "/proc/meminfo");
38
      run_command("CPU INFO", 10, "top", "-n", "1", "-d", "1",
39
      run_command("PROCRANK", 20, "procrank", NULL);
40
      dump_file("VIRTUAL MEMORY STATS", "/proc/vmstat");
41
      dump_file("VMALLOC INFO", "/proc/vmallocinfo");
                                                          1t固态硬盘
42
      dump_file("SLAB INFO", "/proc/slabinfo");
43
      dump file("ZONEINFO", "/proc/zoneinfo");
```



```
44
      dump file("PAGETYPEINFO", "/proc/pagetypeinfo");
45
      dump file("BUDDYINFO", "/proc/buddyinfo");
46
      dump file("FRAGMENTATION INFO", "/d/extfrag/unusable index");
47
48
      dump file("KERNEL WAKELOCKS", "/proc/wakelocks");
      dump file("KERNEL WAKE SOURCES", "/d/wakeup sources");
49
50
      dump_file("KERNEL CPUFREQ", "/sys/devices/system/cpu/cpu0/cpufreq/stats/time_in_state");
51
      dump file("KERNEL SYNC", "/d/sync");
52
53
      run command("PROCESSES", 10, "ps", "-P", NULL);
54
      run_command("PROCESSES AND THREADS", 10, "ps", "-t", "-p", "-P", NULL);
55
      run_command("PROCESSES (SELINUX LABELS)", 10, "ps", "-Z", NULL);
56
      run_command("LIBRANK", 10, "librank", NULL);
57
58
      do_dmesg();
59
60
      run_command("LIST OF OPEN FILES", 10, SU_PATH, "root", "lsof", NULL);
61
      for_each_pid(do_showmap, "SMAPS OF ALL PROCESSES");
62
      for each tid(show wchan, "BLOCKED PROCESS WAIT-CHANNELS");
63
64
      if (screenshot_path[0]) {
65
         ALOGI("taking screenshot\n");
66
         run_command(NULL, 10, "/system/bin/screencap", "-r
                                                                                                     关闭
67
         ALOGI("wrote screenshot: %s\n", screenshot_path);
68
69
70
      // dump_file("EVENT LOG TAGS", "/etc/event-log-tags");
71
       // calculate timeout
72
      timeout = logcat_timeout("main") + logcat_timeout("syst
73
      if (timeout < 20000) {
74
         timeout = 20000;
75
76
      run_command("SYSTEM LOG", timeout / 1000, "logcat",
                                                            1t固态硬盘
77
      timeout = logcat_timeout("events");
78
      if (timeout < 20000) {
```



```
79
          timeout = 20000;
 80
 81
        run command("EVENT LOG", timeout / 1000, "logcat", "-b", "events", "-v", "threadtime", "-d", "*:v'
 82
        timeout = logcat timeout("radio");
 83
        if (timeout < 20000) {
 84
          timeout = 20000;
 85
 86
        run_command("RADIO LOG", timeout / 1000, "logcat", "-b", "radio", "-v", "threadtime", "-d", "*:v",
 87
        run command("LOG STATISTICS", 10, "logcat", "-b", "all", "-S", NULL);
 88
 89
 90
        /* show the traces we collected in main(), if that was done */
 91
        if (dump_traces_path != NULL) {
 92
          dump file("VM TRACES JUST NOW", dump traces path);
 93
 94
 95
        /* only show ANR traces if they're less than 15 minutes old */
 96
        struct stat st;
 97
        char anr_traces_path[PATH_MAX];
 98
        property_get("dalvik.vm.stack-trace-file", anr_traces_path, "");
 99
        if (!anr_traces_path[0]) {
100
          printf("*** NO VM TRACES FILE DEFINED (dalvik.vm.stack-trace-file)\n\n");
101
        } else {
                                                                                                          关闭
102
         int fd = TEMP_FAILURE_RETRY(open(anr_traces_path,
103
                            O_RDONLY | O_CLOEXEC | O_NOFC
104
         if (fd < 0) {
           printf("*** NO ANR VM TRACES FILE (%s): %s\n\n", a
105
106
         } else {
           dump_file_from_fd("VM TRACES AT LAST ANR", anr_t
107
108
109
110
111
        /* slow traces for slow operations */
                                                                1t固态硬盘
112
        if (anr_traces_path[0] != 0) {
113
          int tail = strlen(anr traces path)-1;
```



```
114
          while (tail > 0 && anr traces path[tail] != '/') {
115
            tail--:
116
117
          int i = 0:
118
          while (1) {
119
            sprintf(anr_traces_path+tail+1, "slow%02d.txt", i);
120
            if (stat(anr_traces_path, &st)) {
121
              // No traces file at this index, done with the files.
122
              break;
123
124
            dump_file("VM TRACES WHEN SLOW", anr_traces_path);
125
126
127
128
129
        int dumped = 0;
130
        for (size_t i = 0; i < NUM_TOMBSTONES; i++) {</pre>
131
          if (tombstone_data[i].fd != -1) {
            dumped = 1;
132
133
            dump_file_from_fd("TOMBSTONE", tombstone_data[i].name, tombstone_data[i
134
            tombstone_data[i].fd = -1;
135
136
                                                                                                        关闭
137
        if (!dumped) {
138
          printf("*** NO TOMBSTONES to dump in %s\n\n", TO
139
140
141
        dump_file("NETWORK DEV INFO", "/proc/net/dev");
142
        dump_file("QTAGUID NETWORK INTERFACES INFO", "/pr
143
        dump_file("QTAGUID NETWORK INTERFACES INFO (xt)",
144
        dump_file("QTAGUID CTRL INFO", "/proc/net/xt_qtaguid
145
        dump_file("QTAGUID STATS INFO", "/proc/net/xt_qtaguid
146
                                                              1t固态硬盘
147
        if (!stat(PSTORE_LAST_KMSG, &st)) {
148
          /* Also TODO: Make console-ramoops CAP SYSLOG p
```



```
149
                        dump file("LAST KMSG", PSTORE LAST KMSG);
150
                  } else {
                        /* TODO: Make last kmsg CAP SYSLOG protected. b/5555691 */
151
152
                        dump file("LAST KMSG", "/proc/last kmsg");
153
154
155
                   /* kernels must set CONFIG PSTORE PMSG, slice up pstore with device tree */
156
                   run_command("LAST LOGCAT", 10, "logcat", "-L", "-v", "threadtime",
157
                                                                          "-b", "all", "-d", "*:v", NULL);
158
159
                   /* The following have a tendency to get wedged when wifi drivers/fw goes belly-up - +'
160
161
                   run_command("NETWORK INTERFACES", 10, "ip", "link", NULL);
162
163
                   run_command("IPv4 ADDRESSES", 10, "ip", "-4", "addr", "show", NULL);
164
                   run_command("IPv6 ADDRESSES", 10, "ip", "-6", "addr", "show", NULL);
165
166
                   run command("IP RULES", 10, "ip", "rule", "show", NULL);
                   run command("IP RULES v6", 10, "ip", "-6", "rule", "show", NULL);
167
168
169
                   dump route tables();
170
171
                   run command("ARP CACHE", 10, "ip", "-4", "neigh", "sho
                                                                                                                                                                                                                                                         关闭
172
                   run_command("IPv6 ND CACHE", 10, "ip", "-6", "neigh", '
173
                                                                                                                                                                                              Kingston
174
                   run_command("IPTABLES", 10, SU_PATH, "root", "iptable
175
                   run command("IP6TABLES", 10, SU PATH, "root", "ip6tal
176
                   run_command("IPTABLE NAT", 10, SU_PATH, "root", "iptage of the command of the com
177
                   /* no ip6 nat */
178
                   run_command("IPTABLE RAW", 10, SU_PATH, "root", "ipt
179
                   run_command("IP6TABLE RAW", 10, SU_PATH, "root", "ir
180
181
                   run_command("WIFI NETWORKS", 20,
                                                                                                                                                       1t固态硬盘
182
                              SU_PATH, "root", "wpa_cli", "IFNAME=wlan0", "list_r
183
```



```
Android adb bugreport工具分析和使用 - Android Fans - CSDN博客
184
     #ifdef FWDUMP bcmdhd
185
       run command("ND OFFLOAD TABLE", 5,
            SU PATH, "root", "wlutil", "nd hostip", NULL);
186
187
188
       run command("DUMP WIFI INTERNAL COUNTERS (1)", 20,
189
            SU PATH, "root", "wlutil", "counters", NULL);
190
191
       run command("ND OFFLOAD STATUS (1)", 5,
192
            SU_PATH, "root", "wlutil", "nd_status", NULL);
193
194
     #endif
195
       dump_file("INTERRUPTS (1)", "/proc/interrupts");
196
197
       run_command("NETWORK DIAGNOSTICS", 10, "dumpsys", "connectivity", "--diag",
198
199
     #ifdef FWDUMP bcmdhd
200
       run command("DUMP WIFI STATUS", 20,
201
            SU PATH, "root", "dhdutil", "-i", "wlan0", "dump", NULL);
202
203
       run command("DUMP WIFI INTERNAL COUNTERS (2)", 20,
204
            SU_PATH, "root", "wlutil", "counters", NULL);
205
206
       run command("ND OFFLOAD STATUS (2)", 5,
                                                                                                     关闭
207
            SU_PATH, "root", "wlutil", "nd_status", NULL);
208
     #endif
                                                                             Kingston
209
       dump_file("INTERRUPTS (2)", "/proc/interrupts");
210
211
       print_properties();
212
213
       run_command("VOLD DUMP", 10, "vdc", "dump", NULL)
214
       run_command("SECURE CONTAINERS", 10, "vdc", "asec"
215
216
       run_command("FILESYSTEMS & FREE SPACE", 10, "df", N
217
218
       run command("LAST RADIO LOG", 10, "parse radio log"
```





```
rolex+劳力士
```

```
219
220
                 printf("----- BACKLIGHTS -----\n");
221
                 printf("LCD brightness=");
222
                 dump file(NULL, "/sys/class/leds/lcd-backlight/brightness");
223
                 printf("Button brightness=");
                  dump file(NULL, "/sys/class/leds/button-backlight/brightness");
224
225
                 printf("Keyboard brightness=");
226
                  dump_file(NULL, "/sys/class/leds/keyboard-backlight/brightness");
227
                 printf("ALS mode=");
228
                 dump file(NULL, "/sys/class/leds/lcd-backlight/als");
229
                 printf("LCD driver registers:\n");
230
                 dump_file(NULL, "/sys/class/leds/lcd-backlight/registers");
231
                 printf("\n");
232
233
                 /* Binder state is expensive to look at as it uses a lot of memory. */
234
                 dump_file("BINDER FAILED TRANSACTION LOG", "/sys/kernel/debug/binder/failed
235
                  dump_file("BINDER TRANSACTION LOG", "/sys/kernel/debug/binder/transaction_log", "/sys/kernel/debug/binder/tran
236
                  dump_file("BINDER TRANSACTIONS", "/sys/kernel/debug/binder/transactions");
                  dump_file("BINDER STATS", "/sys/kernel/debug/binder/stats");
237
238
                  dump_file("BINDER STATE", "/sys/kernel/debug/binder/state");
239
240
                  printf("==========\n"):
241
                 printf("== Board\n");
                                                                                                                                                                                                                                     关闭
242
                  243
244
                 dumpstate_board();
245
                 printf("\n");
246
247
                 /* Migrate the ril_dumpstate to a dumpstate_board()? */
248
                 char ril_dumpstate_timeout[PROPERTY_VALUE_MAX] = {(
249
                  property_get("ril.dumpstate.timeout", ril_dumpstate_tim
250
                 if (strnlen(ril_dumpstate_timeout, PROPERTY_VALUE_MA
251
                      if (0 == strncmp(build_type, "user", PROPERTY_VALUE)
                                                                                                                                           1t固态硬盘
252
                           // su does not exist on user builds, so try running w
```

// This way any implementations of vril-dump that

253





```
rolex+劳力士
```

```
254
         // root can run on user builds.
255
         run_command("DUMP VENDOR RIL LOGS", atoi(ril_dumpstate_timeout),
256
             "vril-dump", NULL):
257
       } else {
258
         run command("DUMP VENDOR RIL LOGS", atoi(ril dumpstate timeout),
259
            SU PATH, "root", "vril-dump", NULL);
260
261
      }
262
263
      printf("==========\n"):
264
      printf("== Android Framework Services\n");
265
      printf("=========\n"):
266
267
      /* the full dumpsys is starting to take a long time, so we need
268
       to increase its timeout. we really need to do the timeouts in
269
       dumpsys itself... */
270
      run_command("DUMPSYS", 60, "dumpsys", NULL);
271
272
      printf("========\n");
273
      printf("== Checkins\n");
274
      printf("========\n");
275
276
      run command("CHECKIN BATTERYSTATS", 30, "dumpsys
                                                                              关闭
277
      run_command("CHECKIN MEMINFO", 30, "dumpsys", "n
278
      run_command("CHECKIN NETSTATS", 30, "dumpsys", "ne
279
      run_command("CHECKIN PROCSTATS", 30, "dumpsys", "
280
      run_command("CHECKIN USAGESTATS", 30, "dumpsys",
281
      run_command("CHECKIN PACKAGE", 30, "dumpsys", "pa
282
283
      284
      printf("== Running Application Activities\n");
285
      286
                                               1t固态硬盘
287
      run_command("APP ACTIVITIES", 30, "dumpsys", "activit
288
```



```
289
    printf("========\n"):
290
    printf("== Running Application Services\n");
291
    printf("========\n");
292
293
    run command("APP SERVICES", 30, "dumpsys", "activity", "service", "all", NULL);
294
295
    printf("=======\n");
296
    printf("== Running Application Providers\n");
    printf("=======\n"):
297
298
299
    run_command("APP SERVICES", 30, "dumpsys", "activity", "provider", "all", NULL);
300
301
302
    printf("========\n");
303
    printf("== dumpstate: done\n");
304
    printf("=======\n"):
305 }
```

上面的代码比较长,是因为所要dump的模块太多,但是基本逻辑还是比较清楚的,我们看到

来源就是:

- 1.系统属性
- 2./proc和/sys节点文件
- 3.执行shell命令获得相关输出
- 4.logcat输出
- 5.Android Framework Services信息基本使用dumpsys命令通过binde
- 这里我们需要看一下dumpsys命令的实现,这个命令也是比较简单





6寸智能手机















rolex+劳力士















```
int main(int argc, char* const argv[])
 2
       signal(SIGPIPE, SIG IGN);
       sp<IServiceManager> sm = defaultServiceManager();
       fflush(stdout);
 5
       if (sm == NULL) {
 6
         ALOGE("Unable to get default service manager!");
          aerr << "dumpsys: Unable to get default service manager!" << endl;
 8
         return 20;
 9
10
11
12
       Vector<String16> services;
       Vector<String16> args;
13
14
       bool showListOnly = false;
       if ((argc == 2) && (strcmp(argv[1], "-l") == 0)) {
15
          showListOnly = true;
16
17
       if ((argc == 1) | | showListOnly) {
18
          services = sm->listServices();
19
          services.sort(sort_func);
20
21
          args.add(String16("-a"));
22
       } else {
23
          services.add(String16(argv[1]));
         for (int i=2; i<argc; i++) {
24
25
            args.add(String16(argv[i]));
26
27
28
29
       const size_t N = services.size();
30
       if (N > 1) {
31
         // first print a list of the current services
32
          aout << "Currently running services:" << endl;</pre>
33
34
35
          for (size t i=0; i<N; i++) {
```





```
36
                sp<IBinder> service = sm->checkService(services[i]);
    37
                if (service != NULL) {
    38
                  aout << " " << services[i] << endl;</pre>
    39
    40
    41
    42
           if (showListOnly) {
    43
              return 0;
    44
    45
    46
    47
           for (size_t i=0; i<N; i++) {
              sp<IBinder> service = sm->checkService(services[i]);
    48
    49
              if (service != NULL) {
    50
                if (N > 1) {
    51
                       "-----" << endl:
    52
                  aout << "DUMP OF SERVICE " << services[i] << ":" << endl;</pre>
    53
    54
    55
                int err = service->dump(STDOUT_FILENO, args);
    56
                if (err != 0) {
    57
                  aerr << "Error dumping service info: (" << strerror(err)</pre>
    58
                       << ") " << services[i] << endl;
                                                                                                              关闭
    59
    60
             } else {
                aerr << "Can't find service: " << services[i] << endl;</pre>
    61
    62
    63
    64
    65
           return 0;
    66
我们看到它的代码逻辑就是,通过Binder的SM查找参数中的servic 1t固态硬盘
```

rolex+劳力士



6寸智能手机















rolex+劳力士

















这句来调用service的dump函数。

dumpstate会调用到所有binder中的service的dump函数,因为dumpstate函数执行了这一句:

- /* the full dumpsys is starting to take a long time, so we need
- to increase its timeout. we really need to do the timeouts in
- dumpsys itself... */
- run_command("DUMPSYS", 60, "dumpsys", NULL);

dump函数(执行dumpsys | grep "DUMP OF SERVICE"可以看到):

直接执行dumpsys,没有参数,并且注释中也说的很清楚,就是采集所有的信息。这会执行

- DUMP OF SERVICE DockObserver:
- DUMP OF SERVICE SurfaceFlinger:
- DUMP OF SERVICE accessibility:
- DUMP OF SERVICE account:
- DUMP OF SERVICE activity:
- **DUMP OF SERVICE alarm:**
- DUMP OF SERVICE android.security.keystore:
- DUMP OF SERVICE android.service.gatekeeper.IGateKeepe
- **DUMP OF SERVICE appops:**
- **DUMP OF SERVICE appwidget:** 10
- **DUMP OF SERVICE assetatlas:** 11
- **DUMP OF SERVICE audio:** 12
- DUMP OF SERVICE backup: 13
- DUMP OF SERVICE battery: 14
- **DUMP OF SERVICE batteryproperties:** 15
- DUMP OF SERVICE batterystats: 16
- DUMP OF SERVICE bluetooth_manager: 17
- DUMP OF SERVICE carrier config: 18
- DUMP OF SERVICE clipboard: 19





- DUMP OF SERVICE commontime_management:
- 21 DUMP OF SERVICE connectivity:
- 22 DUMP OF SERVICE consumer ir:
- 23 DUMP OF SERVICE content:
- 24 DUMP OF SERVICE country_detector:
- 25 DUMP OF SERVICE cpuinfo:
- 26 DUMP OF SERVICE dbinfo:
- 27 DUMP OF SERVICE device policy:
- 28 DUMP OF SERVICE deviceidle:
- 29 DUMP OF SERVICE devicestoragemonitor:
- 30 DUMP OF SERVICE diskstats:
- 31 DUMP OF SERVICE display:
- 32 DUMP OF SERVICE display.qservice:
- 33 DUMP OF SERVICE dreams:
- 34 DUMP OF SERVICE drm.drmManager:
- 35 DUMP OF SERVICE dropbox:
- 36 DUMP OF SERVICE ethernet:
- 37 DUMP OF SERVICE fingerprint:
- 38 DUMP OF SERVICE gfxinfo:
- 39 DUMP OF SERVICE graphicsstats:
- 40 DUMP OF SERVICE imms:
- 41 DUMP OF SERVICE input:
- 42 DUMP OF SERVICE input_method:
- 43 DUMP OF SERVICE iphonesubinfo:
- 44 DUMP OF SERVICE isms:
- 45 DUMP OF SERVICE isub:
- 46 DUMP OF SERVICE jobscheduler:
- 47 DUMP OF SERVICE launcherapps:
- 48 DUMP OF SERVICE location:
- 49 DUMP OF SERVICE lock_settings:
- 50 DUMP OF SERVICE media.audio_flinger:
- 51 DUMP OF SERVICE media.audio_policy:
- 52 DUMP OF SERVICE media.camera:
- 53 DUMP OF SERVICE media.camera.proxy:
- 54 DUMP OF SERVICE media.player:







- DUMP OF SERVICE media.radio:
- 56 DUMP OF SERVICE media.resource_manager:
- 57 DUMP OF SERVICE media.sound_trigger_hw:
- 58 DUMP OF SERVICE media_projection:
- 59 DUMP OF SERVICE media_router:
- 60 DUMP OF SERVICE media_session:
- 61 DUMP OF SERVICE meminfo:
- 62 DUMP OF SERVICE midi:
- 63 DUMP OF SERVICE mount:
- 64 DUMP OF SERVICE netpolicy:
- 65 DUMP OF SERVICE netstats:
- 66 DUMP OF SERVICE network_management:
- 67 DUMP OF SERVICE network score:
- 68 DUMP OF SERVICE nfc:
- 69 DUMP OF SERVICE notification:
- 70 DUMP OF SERVICE package:
- 71 DUMP OF SERVICE permission:
- 72 DUMP OF SERVICE persistent_data_block:
- 73 DUMP OF SERVICE phone:
- 74 DUMP OF SERVICE power:
- 75 DUMP OF SERVICE print:
- 76 DUMP OF SERVICE processinfo:
- 77 DUMP OF SERVICE procstats:
- 78 DUMP OF SERVICE restrictions:
- 79 DUMP OF SERVICE rttmanager:
- 80 DUMP OF SERVICE samplingprofiler:
- 81 DUMP OF SERVICE scheduling_policy:
- 82 DUMP OF SERVICE search:
- 83 DUMP OF SERVICE sensorservice:
- 84 DUMP OF SERVICE serial:
- 85 DUMP OF SERVICE servicediscovery:
- 86 DUMP OF SERVICE simphonebook:
- 87 DUMP OF SERVICE sip:
- 88 DUMP OF SERVICE statusbar:
- 89 DUMP OF SERVICE telecom:





- 严 nshile stuss on

 6 寸智能手机

rolex+劳力士

DUMP OF SERVICE telephony.registry: **DUMP OF SERVICE textservices:** DUMP OF SERVICE trust: 92 93 DUMP OF SERVICE uimode: DUMP OF SERVICE updatelock: 94 95 **DUMP OF SERVICE usagestats:** 96 DUMP OF SERVICE usb: DUMP OF SERVICE user: 97 DUMP OF SERVICE vibrator: 98 99 DUMP OF SERVICE voiceinteraction: 100 DUMP OF SERVICE wallpaper: 101 **DUMP OF SERVICE webviewupdate:** DUMP OF SERVICE wifi: 102

> DUMP OF SERVICE wifip2p: DUMP OF SERVICE wifiscanner:

DUMP OF SERVICE window:


103

104105





这里总结以下,上面的bugreport整体逻辑如下图描述(如果图片太小看不清,请下载图片并查看):



adb bugreport的其他选项

bugreport本身并没有什么选项,主要是通过dumpsys等命令配合完

页:https://github.com/google/battery-historian,以下是个总结:

1). 重置电池统计信息:

- 1 adb shell dumpsys batterystats --reset
- 2). Wakelock analysis全部wakelock信息:





6寸智能手机















rolex+劳力士

















- adb shell dumpsys batterystats --enable full-wake-history
- 3). Kernel trace analysis分析内核,主要分析wakeup source和wakelock activities,首先使能kernel分析:
 - \$ adb root
 - \$ adb shell

- # Set the events to trace.
- \$ echo "power:wakeup_source_activate" >> /d/tracing/set_event
- \$ echo "power:wakeup_source_deactivate" >> /d/tracing/set_event
- # The default trace size for most devices is 1MB, which is relatively low and might ca
- # 8MB to 10MB should be a decent size for 5-6 hours of logging.

10

11 \$ echo 8192 > /d/tracing/buffer_size_kb

12

\$ echo 1 > /d/tracing/tracing_on

然后获得log:

3

\$ echo 0 > /d/tracing/tracing_on

\$ adb pull /d/tracing/trace <some path>

Take a bug report at this time.

\$ adb bugreport > bugreport.txt

()



- Android 6.0 Overview Screen实现原理
- Android 6.0指纹识别App开发demo



6寸智能手机

















rolex+劳力士



















相关文章推荐

- adb shell bugreport分析
- Python即将成为第一语言
- android bugreport. .
- 构建企业级高性能OLAP引擎--董西成
- Android bugreport工具分析和使用
- JDK9新特性解读
- · Android 建立手机与手表数据同步机制总结
- 华为工程师,带你实战C++

- 聊一聊binder driver导致的系统重启问题
- Android自定义控件全知道
- adb启动程序命令: adb shell am start
- TensorFlow入门基础知识详解
- android跨进程通信(IPC):使用AIDL
- Android 通过adb shell am broadcast发送广
- idapython import site failed
- 一键分析Android的BugReport







查看评论

暂无评论





您还没有登录,请[登录]或[注册]

*以上用户言论只代表其个人观点,不代表CSDN网站的观点或立场

6寸智能手机



rolex+劳力士















400-660-0108 | 北京创新乐知信息技术有限公司 版权所有 | 江苏知之为计算机有限公司 | 江苏乐:

SDN.NET, All Rights Reserved



