## **Install Nextcloud steps**

In this challenge, we are going to Install NextCloud On Ubuntu 22.04 LTS, This will be a detailed step-by-step high-performance Setup.

- 1. Install PHP and MySQL packages
- 2. Configure MySQL Server
- 3. Run the Nextcloud Setup on the Browser.

Step 1 install packages:

1. Become root user:

sudo -i

1. Update and upgrade your server:

sudo apt update && sudo apt upgrade -y

3: Install the following packages:

sudo apt install apache2 mariadb-server libapache2-mod-php php-gd php-mysql php-curl php-mbstring php-intl php-gmp php-bcmath php-xml php-imagick php-zip -y

apt install libapache2-mod-php php-bz2 php-gd php-mysql php-curl php-mbstring php-imagick php-zip php-ctype php-curl php-dom php-json php-posix php-bcmath php-xml php-intl php-gmp zip unzip wget -y

4: Enable the following modules:

a2enmod rewrite dir mime env headers

Then restart your web server:

systemctl restart apache2

Step 2: Configure MySQL Server

1. Login to MySQL Prompt, Just type

mysql

1. Create MySQL Database and User for Nextcloud and Provide Permissions:

```
CREATE USER 'nextcloud'@'localhost' IDENTIFIED BY 'passw@rd';
CREATE DATABASE IF NOT EXISTS nextcloud CHARACTER SET utf8mb4 COLLATE
utf8mb4_general_ci;
GRANT ALL PRIVILEGES ON nextcloud.* TO 'nextcloud'@'localhost';
FLUSH PRIVILEGES;
quit;
```

## Step 3: Download and Install Nextcloud

Now download the latest Nextcloud archive file, Go to the Nextcloud Download Page. Or you can download from this direct link: https://download.nextcloud.com/server/releases/latest.zip.

1. Download and unzip at the web root (/var/www/html) folder:

```
cd /var/www/html
wget https://download.nextcloud.com/server/releases/latest.zip
unzip latest.zip
```

1. Move all nextcloud content to the web root (/var/www/html) folder:

cd /var/www/html/nextcloud

```
mv * .* ../
```

1. Remove empty nextcloud directory:

```
rmdir /var/www/html/nextcloud
```

1. Change the ownership of the nextcloud content directory to the HTTP user:

```
chown -R www-data:www-data/var/www/html
```

Now, Go to the Browser and type http:// [ ip or fqdn ] of the server, The below Nextcloud install page will appear. On the page we need to Provide information for: \* 1. nextcloud admin username & password \* 2. Database Credentials (db name, db user and db Password)

http://ip-address-or-dns