# Programming Shared Address Space Platforms

CSE 531
Spring 2023

Mahmut Taylan Kandemir

### **Topic Overview**

- Thread Basics
- The POSIX Thread API
- Synchronization Primitives in Pthreads
- Controlling Thread and Synchronization Attributes
- Composite Synchronization Constructs
- OpenMP: a Standard for Directive Based Parallel Programming

### Overview of Programming Models

- Programming models provide support for expressing concurrency and synchronization.
- Process-based models assume that all data associated with a process is *private*, by default, unless otherwise specified.
- Lightweight processes and threads assume that all memory is global.
- Directive-based programming models extend the threaded model by facilitating creation and synchronization of threads.

### Overview of Programming Models

A thread is a single stream of control in the flow of a program. A program like:

```
for (row = 0; row < n; row++)
 for (column = 0; column < n; column++)
        c[row][column] =
        dot product( get row(a, row),
                      get col(b, col));
```

#### can be transformed to:


```
for (row = 0; row < n; row++)
 for (column = 0; column < n; column++)
        c[row][column] =
        create thread ( dot product (get row (a, row),
                      get col(b, col));
```


In this case, one may think of the thread as an instance of a function that returns before the function has finished executing.

#### **Thread Basics**

- All memory in the logical machine model of a thread is globally accessible to every thread.
- The stack corresponding to the function call is generally treated as being local to the thread for liveness reasons.
  - Remember static memory, stack and heap?
- This implies a logical machine model with both global memory (default) and local memory (stacks).
- It is important to note that such a flat model may result in very poor performance since memory is physically distributed in typical machines.
  - Productivity vs Performance tradeoff

#### **Thread Basics**





- The logical machine model of a thread-based programming paradigm.
- In a distributed shared address space machines, the cost to access a physically local memory may be an order of magnitude less than that of accessing a remote memory.
- Caches also skew memory access times.

#### **Thread Basics**

- Threads provide software portability.
- Inherent support for latency hiding.
- Scheduling and load balancing.
- Ease of programming and widespread use.

#### The POSIX Thread API

- Commonly referred to as Pthreads, POSIX has emerged as the standard threads API, supported by most vendors.
- The concepts discussed here are largely independent of the API and can be used for programming with other thread APIs (NT threads, Solaris threads, Java threads, etc.) as well.

# Thread Basics: Creation and Termination

 Pthreads provides two basic functions for specifying concurrency in a program:

- The function pthread\_create invokes function thread\_function as a thread
- A call to pthread\_join waits for the termination of the thread whose id is given by thread

# Thread Basics: Creation and Termination (Example)

```
#include <pthread.h>
#include <stdlib.h>
#define MAX THREADS 512
void *compute pi (void *);
. . . .
main() {
    pthread t p threads[MAX THREADS];
    pthread attr t attr;
    pthread attr init (&attr);
    for (i=0; i < num threads; <math>i++) {
        hits[i] = i;
        pthread create (&p threads[i], &attr, compute pi,
              (void *) &hits[i]);
    for (i=0; i < num threads; i++) {
         pthread_join(p threads[i], NULL);
         total hits += hits[i];
```


# Thread Basics: Creation and Termination (Example)

```
void *compute pi (void *s) {
    int seed, i, *hit pointer;
    double rand no x, rand no y;
    int local hits;
   hit pointer = (int *) s;
    seed = *hit pointer;
    local hits = 0;
    for (i = 0; i < sample points per thread; i++) {</pre>
        rand no x = (double) (rand r(\&seed)) / (double) ((2 << 14) -1);
        rand no y = (double) (rand r(\&seed)) / (double) ((2 << 14) -1);
        if (((rand_no_x - 0.5) * (rand_no_x - 0.5) +
            (rand_no_y - 0.5) * (rand_no_y - 0.5)) < 0.25)
            local hits ++;
        seed *= i:
    *hit pointer = local hits;
   pthread exit(0);
```

# Programming and Performance Notes

- Note the use of the function rand\_r (instead of superior random number generators such as drand48).
- Executing this on a 4-processor machine, we observe a 3.91 fold speedup at 32 threads. This corresponds to a parallel efficiency of 0.98!
- We can also modify the program slightly to observe the effect of false-sharing.
- The program can also be used to assess the secondary cache line size.

#### Programming and Performance Notes



• Execution time of the compute\_pi program.

### Synchronization Primitives in Pthreads

- When multiple threads attempt to manipulate the same data item, the results can often be incoherent if proper care is not taken to synchronize them.
- Consider:

```
/* each thread tries to update variable best_cost as
  follows */
if (my_cost < best_cost)
  best_cost = my_cost;</pre>
```

- Assume that there are two threads, the initial value of best\_cost is 100, and the values of my cost are 50 and 75 at threads t1 and t2.
- Depending on the schedule of the threads, the value of best\_cost could be 50 or 75!
- The value 75 does not correspond to any serialization of the threads.

#### Mutual Exclusion

- The code in the previous example corresponds to a critical segment; i.e., a segment that must be executed by only one thread at any time.
- Critical segments in Pthreads are implemented using mutex locks.
- Mutex-locks have two states: locked and unlocked. At any point of time, only one thread can lock a mutex lock. A lock is an atomic operation.
- A thread entering a critical segment first tries to get a lock. It goes ahead when the lock is granted.

#### Mutual Exclusion

 The Pthreads API provides the following functions for handling mutex-locks:

```
int pthread_mutex_lock (
   pthread_mutex_t *mutex_lock);
int pthread_mutex_unlock (
   pthread_mutex_t *mutex_lock);
int pthread_mutex_init (
   pthread_mutex_t *mutex_lock,
   const pthread_mutexattr_t *lock_attr);
```

#### Mutual Exclusion

We can now write our previously incorrect code segment as:

```
pthread mutex t minimum value lock;
main() {
   pthread mutex init(&minimum value lock, NULL);
void *find min(void *list ptr) {
   pthread mutex lock(&minimum value lock);
   if (my min < minimum value)</pre>
   minimum value = my min;
   /* and unlock the mutex */
   pthread mutex unlock (&minimum value lock);
```

# Producer-Consumer Computation Using Locks

- A common use of mutex-locks is in establishing a producer-consumer relationship among threads.
- The producer-consumer scenario imposes the following constraints:
  - The producer thread must not overwrite the shared buffer when the previous task has not been picked up by a consumer thread.
  - The consumer threads must not pick up tasks until there is something present in the shared data structure.
  - Individual consumer threads should pick up tasks one at a time.

### Producer-Consumer Using Locks

```
pthread mutex t task queue lock;
int task available;
main() {
    task available = 0;
    pthread mutex init(&task queue lock, NULL);
void *producer(void *producer thread data) {
    while (!done()) {
        inserted = 0;
        create task(&my task);
        while (inserted == 0) {
             pthread mutex lock(&task queue lock);
             if (task available == 0) {
                 insert_into_queue(my_task);
                 task available = 1;
                 inserted = 1;
             pthread mutex unlock(&task queue lock);
```

We use a variable called task available: If this variable is 0, consumer threads must wait, but the producer thread can insert tasks into the shared data structure task queue. If task available iS equal to 1, the producer thread must wait to insert the task into the shared data structure, but one of the consumer threads can pick up the task available.

### Producer-Consumer Using Locks

```
void *consumer(void *consumer thread data) {
    int extracted;
    struct task my task;
    /* local data structure declarations */
    while (!done()) {
        extracted = 0;
        while (extracted == 0) {
             pthread mutex lock(&task queue lock);
             if (task available == 1) {
                 extract from queue (&my task);
                 task available = 0;
                 extracted = 1;
             pthread mutex unlock(&task queue lock);
        process task (my task);
```

### Types of Mutexes

- Pthreads supports three types of mutexes normal, recursive, and error-check.
- A normal mutex deadlocks if a thread that already has a lock tries a second lock on it.
- A recursive mutex allows a single thread to lock a mutex as many times as it wants. It simply increments a count on the number of locks. A lock is relinquished by a thread when the count becomes zero.
- An error check mutex reports an error when a thread with a lock tries to lock it again (as opposed to deadlocking in the first case, or granting the lock, as in the second case).
- The type of the mutex can be set in the attributes object before it is passed at time of initialization.

### Overheads of Locking

- Locks represent serialization points since critical sections must be executed by threads one after the other.
- Encapsulating large segments of the program within locks can lead to significant *performance degradation*.
- It is often possible to reduce the idling overhead associated with locks using an alternate function, pthread mutex trylock.

```
int pthread_mutex_trylock (
    pthread_mutex_t *mutex_lock);
```

• pthread\_mutex\_trylock is typically much faster than pthread\_mutex\_lock on typical systems since it does not have to deal with queues associated with locks for multiple threads waiting on the lock.

### Alleviating Locking Overhead (Example)

```
/* Finding k matches in a list */
void *find entries(void *start pointer) {
   /* This is the thread function */
   struct database record *next record;
   int count;
   current pointer = start pointer;
   do {
       next record = find next entry(current pointer);
       count = output record(next record);
   } while (count < requested number of records);</pre>
int output record(struct database record *record ptr) {
   int count;
   pthread mutex lock(&output count lock);
   output count ++;
   count = output count;
   pthread mutex unlock (&output count lock);
   if (count <= requested number of records)</pre>
      print record(record ptr);
   return (count);
```

### Alleviating Locking Overhead (Example)

```
/* rewritten output record function */
int output record(struct database record
  *record ptr) {
   int count;
   int lock status;
   lock status=pthread mutex trylock(&output count lock);
   if (lock status == EBUSY) {
      insert_into_local_list(record_ptr);
      return(0);
   else {
      count = output count;
      output count += number on local list + 1;
      pthread mutex unlock (&output count lock);
      print records (record ptr, local list,
          requested number of records - count);
      return(count + number on local list + 1);
```

### Condition Variables for Synchronization

- Indiscriminate use of locks can result in idling overhead from blocked threads.
- A condition variable allows a thread to block itself until specified data reaches a predefined state.
- A condition variable is associated with this predicate.
  When the predicate becomes true, the condition variable is used to signal one or more threads waiting on the condition.
- A single condition variable may be associated with more than one predicate.
- A condition variable always has a mutex associated with it. A thread locks this mutex and tests the predicate defined on the shared variable.
- If the predicate is not true, the thread waits on the condition variable associated with the predicate using the function pthread cond wait.

# Condition Variables for Synchronization

 Pthreads provides the following functions for condition variables:

```
int pthread_cond_wait(pthread_cond_t *cond,
    pthread_mutex_t *mutex);
int pthread_cond_signal(pthread_cond_t *cond);
int pthread_cond_broadcast(pthread_cond_t *cond);
int pthread_cond_init(pthread_cond_t *cond,
    const pthread_condattr_t *attr);
int pthread_cond_destroy(pthread_cond_t *cond);
```

# Producer-Consumer Using Condition Variables

```
pthread cond t cond queue empty, cond queue full;
pthread mutex t task queue cond lock;
int task available;
/* other data structures here */
main() {
   /* declarations and initializations */
   task available = 0;
   pthread init();
   pthread cond init(&cond queue empty, NULL);
   pthread cond init(&cond queue full, NULL);
   pthread mutex init(&task queue cond lock, NULL);
   /* create and join producer and consumer threads */
```

# Producer-Consumer Using Condition Variables

```
void *producer(void *producer thread data) {
   int inserted;
   while (!done()) {
      create task();
      pthread mutex lock(&task queue cond lock);
      while (task available == 1)
         pthread cond wait (&cond queue empty,
            &task queue cond lock);
      insert into queue();
      task available = 1;
      pthread cond signal (&cond queue full);
      pthread mutex unlock (&task queue cond lock);
```

# Producer-Consumer Using Condition Variables

```
void *consumer(void *consumer thread data) {
   while (!done()) {
   pthread mutex lock(&task queue cond lock);
   while (task available == 0)
      pthread cond wait (&cond queue full,
         &task queue cond lock);
      my task = extract from queue();
      task available = 0;
      pthread cond signal (&cond queue empty);
      pthread mutex unlock (&task queue cond lock);
      process task(my task);
```

# Controlling Thread and Synchronization Attributes

- The Pthreads API allows a programmer to change the default attributes of entities using attributes objects.
- An attributes object is a data-structure that describes entity (thread, mutex, condition variable) properties.
- Once these properties are set, the attributes object can be passed to the method initializing the entity.
- Enhances modularity, readability, and ease of modification.

### Attributes Objects for Threads

- Use pthread\_attr\_init to create an attributes object.
- Individual properties associated with the attributes object can be changed using the following functions:

```
pthread_attr_setdetachstate,
pthread_attr_setguardsize_np,
pthread_attr_setstacksize,
pthread_attr_setinheritsched,
pthread_attr_setschedpolicy, and
pthread_attr_setschedparam
```

### Attributes Objects for Mutexes

- Initialize the attrributes object using function: pthread mutexattr init.
- The function pthread mutexattr settype np can be used for setting the type of mutex specified by the mutex attributes object.

```
pthread_mutexattr_settype_np (
pthread_mutexattr_t *attr,
int type);
```

- Here, type specifies the type of the mutex and can take one of:
  - PTHREAD MUTEX NORMAL NP
  - PTHREAD MUTEX RECURSIVE NP
  - PTHREAD\_MUTEX\_ERRORCHECK\_NP

# Composite Synchronization Constructs

- By design, Pthreads provide support for a basic set of operations.
- Higher level constructs can be built using basic synchronization constructs.
- We discuss two such constructs:
  - Read-Write Locks and Barriers.

#### Read-Write Locks

- In many applications, a data structure is read frequently but written infrequently. For such applications, we should use read-write locks.
- A read lock is granted when there are other threads that may already have read locks.
- If there is a write lock on the data (or if there are queued write locks), the thread performs a condition wait.
- If there are multiple threads requesting a write lock, they must perform a condition wait.
- With this description, we can design functions for read locks mylib\_rwlock\_rlock, write locks mylib\_rwlock\_wlock, and unlocking mylib rwlock unlock.

#### Read-Write Locks

- The lock data type mylib\_rwlock\_t holds the following:
  - a count of the number of readers,
  - the writer (a 0/1 integer specifying whether a writer is present),
  - a condition variable readers\_proceed that is signaled when readers can proceed,
  - a condition variable writer proceed that is signaled when one of the writers can proceed,
  - a count pending writers of pending writers, and
  - a mutex read\_write\_lock associated with the shared data structure

#### Read-Write Locks

```
typedef struct {
   int readers;
   int writer;
   pthread cond t readers proceed;
  pthread cond t writer proceed;
   int pending writers;
   pthread mutex t read write lock;
} mylib rwlock t;
void mylib rwlock init (mylib rwlock t *1) {
   1 -> readers = l -> writer = l -> pending writers
    = 0;
   pthread mutex init(&(l -> read write lock),
    NULL);
  pthread cond init(&(l -> readers proceed), NULL);
  pthread cond init(&(l -> writer proceed), NULL);
```

### Read-Write Locks

```
void mylib_rwlock_rlock(mylib_rwlock_t *1) {
    /* if there is a write lock or pending writers, perform
        condition wait.. else increment count of readers and grant
        read lock */
    pthread_mutex_lock(&(l -> read_write_lock));
    while ((l -> pending_writers > 0) || (l -> writer > 0))
        pthread_cond_wait(&(l -> readers_proceed),
        &(l -> read_write_lock));
    l -> readers ++;
    pthread_mutex_unlock(&(l -> read_write_lock));
}
```

#### Read-Write Locks

```
void mylib rwlock wlock(mylib rwlock t *1) {
   /* if there are readers or writers, increment pending
     writers count and wait. On being woken, decrement
     pending writers count and increment writer count */
   pthread mutex lock(&(l -> read write lock));
   while ((1 -> writer > 0) || (1 -> readers > 0)) {}
      1 -> pending writers ++;
      pthread cond wait(&(l -> writer_proceed),
          &(l -> read write lock));
   1 -> pending writers --;
   1 -> writer ++;
   pthread mutex unlock(&(l -> read write lock));
```

#### Read-Write Locks

```
void mylib rwlock unlock(mylib rwlock t *1) {
/* if there is a write lock then unlock, else if there are
  read locks, decrement count of read locks. If the count
   is 0 and there is a pending writer, let it through, else
   if there are pending readers, let them all go through */
pthread mutex lock(&(l -> read write lock));
if (1 \rightarrow writer > 0)
   1 \rightarrow writer = 0:
else if (1 \rightarrow readers > 0)
   1 -> readers --;
pthread mutex unlock(&(l -> read write lock));
if ((1 \rightarrow readers == 0) \&\& (1 \rightarrow pending writers > 0))
   pthread cond signal(&(l -> writer proceed));
else if (1 \rightarrow readers > 0)
   pthread cond broadcast(&(l -> readers proceed));
```

- As in MPI (will be discussed later), a barrier holds a thread until all threads participating in the barrier have reached it.
- Barriers can be implemented using a counter, a mutex and a condition variable.
- A single integer is used to keep track of the number of threads that have reached the barrier.
- If the count is less than the total number of threads, the threads execute a condition wait.
- The last thread entering (and setting the count to the number of threads) wakes up all the threads using a condition broadcast.

```
typedef struct {
   pthread_mutex_t count_lock;
   pthread_cond_t ok_to_proceed;
   int count;
} mylib_barrier_t;
void mylib_init_barrier(mylib_barrier_t *b) {
   b -> count = 0;
   pthread_mutex_init(&(b -> count_lock), NULL);
   pthread_cond_init(&(b -> ok_to_proceed), NULL);
}
```

```
void mylib barrier (mylib barrier t *b, int
  num threads) {
   pthread mutex lock(&(b -> count lock));
   b -> count ++;
   if (b -> count == num threads) {
      b \rightarrow count = 0;
      pthread cond broadcast(&(b -> ok to proceed));
   else
      while (pthread cond wait(&(b -> ok to proceed),
          &(b \rightarrow count lock)) != 0);
   pthread mutex unlock(&(b -> count lock));
```

- The barrier described above is called a linear barrier.
- The trivial lower bound on execution time of this function is therefore O(n) for n threads.
- This implementation of a barrier can be sped up using multiple barrier variables organized in a tree.
- We use n/2 condition variable-mutex pairs for implementing a barrier for n threads.
- At the lowest level, threads are paired up and each pair of threads shares a single condition variable-mutex pair.
- Once both threads arrive, one of the two moves on, the other one waits.
- This process repeats up the tree.
- This is also called a log barrier and its runtime grows as O(log p).

#### Barrier Log Barrier (1000, 32 procs) Linear Barrier (1000, 32 procs) Time (seconds) Number of threads

• Execution time of 1000 sequential and logarithmic barriers as a function of number of threads on a 32 processor SGI Origin 2000.

### Tips for Designing Asynchronous Programs

- Set up all the requirements or a thread before actually creating it. This includes initializing the data, setting thread attributes, thread priorities, mutex attributes, etc
- Never rely on scheduling assumptions when exchanging data.
  - Threads are usually switched at semi-deterministic ways
- Do not rely on scheduling as a means of synchronization.
- Where possible, define and use group synchronizations and data replication. This can significantly improve program performance.

# OpenMP: a Standard for Directive Based Parallel Programming

- OpenMP is a directive-based API that can be used with FORTRAN, C, and C++ for programming shared address space machines.
- OpenMP directives provide support for concurrency, synchronization, and data handling while obviating the need for explicitly setting up mutexes, condition variables, data scope, and initialization.

- OpenMP directives in C and C++ are based on the #pragma compiler directives.
- A directive consists of a directive name followed by clauses.

```
#pragma omp directive [clause list]
```

 OpenMP programs execute serially until they encounter the parallel directive, which creates a group of threads.

```
#pragma omp parallel [clause list]
/* structured block */
```

• The main thread that encounters the parallel directive becomes the *master* of this group of threads and is assigned the thread id 0 within the group.

- The clause list is used to specify conditional parallelization, number of threads, and data handling.
  - Conditional Parallelization: The clause if (scalar expression) determines whether the parallel construct results in creation of threads.
  - Degree of Concurrency: The clause num\_threads (integer expression) specifies the number of threads that are created.
  - Data Handling: The clause private (variable list) indicates variables local to each thread. The clause firstprivate (variable list) is similar to the private, except values of variables are initialized to corresponding values before the parallel directive. The clause shared (variable list) indicates that variables are shared across all the threads.

```
int a, b;
main()
    // serial segment
    #pragma omp parallel num_threads (8) private (a) shared (b)
        // parallel segment
    // rest of serial segment
                                             Sample OpenMP program
                        int a, b;
                       main() {
                            // serial segment
                            for (i = 0; i < 8; i++)
                 Code
                                pthread create (....., internal thread fn name, ...);
             inserted by
            the OpenMP
                            for (i = 0; i < 8; i++)
               compiler
                                pthread join (.....);
                           // rest of serial segment
                       void *internal_thread_fn_name (void *packaged_argument) [
                            // parallel segment
                                                               Corresponding Pthreads translation
```

 A sample OpenMP program along with its Pthreads translation that might be performed by an OpenMP compiler.

```
#pragma omp parallel if (is_parallel== 1) num_threads(8) \
   private (a) shared (b) firstprivate(c) {
   /* structured block */
}
```

- If the value of the variable is\_parallel equals one, eight threads are created.
- Each of these threads gets private copies of variables a and c, and shares a single value of variable b.
- The value of each copy of c is initialized to the value of c before the parallel directive.
- The default state of a variable is specified by the clause default (shared) or default (none).

### Reduction Clause in OpenMP

- The reduction clause specifies how multiple local copies of a variable at different threads are combined into a single copy at the master when threads exit.
- The usage of the reduction clause is reduction (operator: variable list).
- The variables in the list are implicitly specified as being private to threads.
- The operator can be one of +, \*, -, &, |, ^,
   &&, and ||.

```
#pragma omp parallel reduction(+: sum) num_threads(8) {
/* compute local sums here */
}
/*sum here contains sum of all local instances of sums */
```

### OpenMP Programming: Example

```
*******************
An OpenMP version of a threaded program to compute PI.
*************************************
#pragma omp parallel default(private) shared (npoints) \
   reduction(+: sum) num threads(8)
   num threads = omp get num threads();
   sample points per thread = npoints / num threads;
   sum = 0;
   for (i = 0; i < sample points per thread; i++) {
       rand no x = (double) (rand r(\&seed)) / (double) ((2 << 14) -1);
       rand no y = (double) (rand r(\&seed)) / (double) ((2 << 14) -1);
       if (((rand no x - 0.5) * (rand no x - 0.5) +
          (rand no y - 0.5) * (rand no y - 0.5)) < 0.25)
          sum ++;
```

# Specifying Concurrent Tasks in OpenMP

- The parallel directive can be used in conjunction with other directives to specify concurrency across iterations and tasks.
- OpenMP provides two directives for and sections to specify concurrent iterations and tasks.
- The for directive is used to split parallel iteration spaces across threads. The general form of a for directive is as follows:

```
#pragma omp for [clause list]
   /* for loop */
```

• The clauses that can be used in this context are: private, firstprivate, lastprivate, reduction, schedule, nowait, and ordered.

# Specifying Concurrent Tasks in OpenMP: Example


### Assigning Iterations to Threads

- The schedule clause of the for directive deals with the assignment of iterations to threads.
- The general form of the schedule directive is schedule(scheduling\_class[, parameter]).
- OpenMP supports four scheduling classes: static, dynamic, guided, and runtime.

# Assigning Iterations to Threads: Example

```
/* static scheduling of matrix multiplication loops */
#pragma omp parallel default(private) shared (a, b, c, dim) \
   num threads (4)
   #pragma omp for schedule(static)
   for (i = 0; i < dim; i++) {
      for (j = 0; j < dim; j++) {
          c(i,j) = 0;
          for (k = 0; k < dim; k++) {
             c(i,j) += a(i, k) * b(k, j);
```

# Assigning Iterations to Threads: Example



 Three different schedules using the static scheduling class of OpenMP.

### Parallel For Loops

- Often, it is desirable to have a sequence of for-directives within a parallel construct that do not execute an implicit barrier at the end of each for directive.
- OpenMP provides a clause nowait,
   which can be used with a for directive.

### Parallel For Loops: Example

```
#pragma omp parallel
  #pragma omp for nowait
     for (i = 0; i < nmax; i++)
       if (isEqual(name, current list[i])
          processCurrentName(name);
  #pragma omp for
     for (i = 0; i < mmax; i++)
       if (isEqual(name, past list[i])
          processPastName(name);
```

### The sections Directive

- OpenMP supports non-iterative parallel task assignment using the sections directive.
- The general form of the sections directive is as follows:

### The sections Directive: Example

```
#pragma omp parallel
   #pragma omp sections
       #pragma omp section
           taskA();
       #pragma omp section
           taskB();
       #pragma omp section
           taskC();
```

### Nesting parallel Directives

- Nested parallelism can be enabled using the OMP\_NESTED environment variable.
- If the OMP\_NESTED environment variable is set to TRUE, nested parallelism is enabled.
- In this case, each parallel directive creates a new team of threads.

# Synchronization Constructs in OpenMP

 OpenMP provides a variety of synchronization constructs:

```
#pragma omp barrier
#pragma omp single [clause list]
  structured block
#pragma omp master
  structured block
#pragma omp critical [(name)]
  structured block
#pragma omp ordered
  structured block
```

### OpenMP Library Functions

 In addition to directives, OpenMP also supports a number of functions that allow a programmer to control the execution of threaded programs.

```
/* thread and processor count */
void omp_set_num_threads (int
  num_threads);
int omp_get_num_threads ();
int omp_get_max_threads ();
int omp_get_thread_num ();
int omp_get_num_procs ();
int omp in parallel();
```

### OpenMP Library Functions

```
/* controlling and monitoring thread creation */
void omp_set_dynamic (int dynamic_threads);
int omp_get_dynamic ();
void omp_set_nested (int nested);
int omp_get_nested ();
/* mutual exclusion */
void omp_init_lock (omp_lock_t *lock);
void omp_destroy_lock (omp_lock_t *lock);
void omp_set_lock (omp_lock_t *lock);
void omp_unset_lock (omp_lock_t *lock);
int omp_test_lock (omp_lock_t *lock);
```

- In addition, all lock routines also have a nested lock counterpart
- for recursive mutexes.

### **Environment Variables in OpenMP**

- OMP\_NUM\_THREADS: This environment variable specifies the default number of threads created upon entering a parallel region.
- OMP\_SET\_DYNAMIC: Determines if the number of threads can be dynamically changed.
- OMP NESTED: Turns on nested parallelism.
- OMP\_SCHEDULE: Scheduling of for-loops if the clause specifies runtime

# Explicit Threads versus Directive Based Programming

- Directives layered on top of threads facilitate a variety of threadrelated tasks.
- A programmer is rid of the tasks of initializing attributes objects, setting up arguments to threads, partitioning iteration spaces, etc.
- There are some drawbacks to using directives as well.
- An artifact of explicit threading is that data exchange is more apparent. This helps in alleviating some of the overheads from data movement, false sharing, and contention.
- Explicit threading also provides a richer API in the form of condition waits, locks of different types, and increased flexibility for building composite synchronization operations.
- Finally, since explicit threading is used more widely than OpenMP, tools and support for Pthreads programs are easier to find (NOTE: This may not be true soon...)