Transport layer: overview


Our goal:

- understand principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control

- learn about Internet transport layer protocols:
 - UDP: connectionless transport
 - TCP: connection-oriented reliable transport
 - TCP congestion control

Transport services and protocols

- provide logical communication between application processes running on different hosts
- transport protocols actions in end systems:
 - sender: breaks application messages into segments, passes to network layer
 - receiver: reassembles segments into messages, passes to application layer
- two transport protocols available to Internet applications
 - TCP, UDP



Transport vs. network layer services and protocols


- network layer: logical communication between hosts
- transport layer: logical communication between processes
 - relies on, enhances, network layer services


household analogy:


- 12 kids in Ann's house sending letters to 12 kids in Bill's house:
- hosts = houses
- processes = kids
- app messages = letters in envelopes

Two principal Internet transport protocols


- TCP: Transmission Control Protocol
 - reliable, in-order delivery
 - congestion control
 - flow control
 - connection setup
- UDP: User Datagram Protocol
 - unreliable, unordered delivery
 - no-frills extension of "best-effort" IP
- services not available:
 - delay guarantees
 - bandwidth guarantees








Multiplexing/demultiplexing



How demultiplexing works

- host receives IP datagrams
 - each datagram has source IP address, destination IP address
 - each datagram carries one transport-layer segment
 - each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format

Connectionless demultiplexing

Recall:

when creating socket, must specify *host-local* port #:

- when creating datagram to send into UDP socket, must specify
 - destination IP address
 - destination port #

when receiving host receives *UDP* segment:


- checks destination port # in segment
- directs UDP segment to socket with that port #



IP/UDP datagrams with same dest.

port #, but different source IP
addresses and/or source port
numbers will be directed to same
socket at receiving host

Connectionless demultiplexing: an example




Connection-oriented demultiplexing

- TCP socket identified by 4-tuple:
 - source IP address
 - source port number
 - dest IP address
 - dest port number
- demux: receiver uses all four values (4-tuple) to direct segment to appropriate socket

- server may support many simultaneous TCP sockets:
 - each socket identified by its own 4-tuple
 - each socket associated with a different connecting client

Connection-oriented demultiplexing: example



Three segments, all destined to IP address: B,

dest port: 80 are demultiplexed to different sockets

Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality



UDP: User Datagram Protocol

- "no frills," "bare bones" Internet transport protocol
- "best effort" service, UDP segments may be:
 - lost
 - delivered out-of-order to app

connectionless:

- no handshaking between UDP sender, receiver
- each UDP segment handled independently of others

Why is there a UDP?

- no connection establishment (which can add RTT delay)
- simple: no connection state at sender, receiver
- small header size
- no congestion control
 - UDP can blast away as fast as desired!
 - can function in the face of congestion

UDP: User Datagram Protocol

- UDP use:
 - streaming multimedia apps (loss tolerant, rate sensitive)
 - DNS
 - SNMP
 - HTTP/3
- if reliable transfer needed over UDP (e.g., HTTP/3):
 - add needed reliability at application layer
 - add congestion control at application layer

UDP: User Datagram Protocol [RFC 768]

RFC 768

J. Postel
ISI
28 August 1980


User Datagram Protocol

Introduction


This User Datagram Protocol (UDP) is defined to make available a datagram mode of packet-switched computer communication in the environment of an interconnected set of computer networks. This protocol assumes that the Internet Protocol (IP) $[\underline{1}]$ is used as the underlying protocol.

This protocol provides a procedure for application programs to send messages to other programs with a minimum of protocol mechanism. The protocol is transaction oriented, and delivery and duplicate protection are not guaranteed. Applications requiring ordered reliable delivery of streams of data should use the Transmission Control Protocol (TCP) [2].

Format



UDP segment header



UDP segment format

Internet checksum

Goal: detect errors (i.e., flipped bits) in transmitted segment

sender:

- treat contents of UDP segment (including UDP header fields and IP addresses) as sequence of 16-bit integers
- checksum: addition (one's complement sum) of segment content
- checksum value put into UDP checksum field

receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - not equal error detected
 - equal no error detected. But maybe errors nonetheless? More later

Internet checksum: an example


example: add two 16-bit integers

	1	1	1	0	0	1	1	0	0	1	1	0	0	1	1	0
	1	1	0	1	0	1	0	1	0	1	0	1	0	1	0	1
wraparound	1 1	0	1	1	1	0	1	1	1	0	1	1	1	0	1	1
sum	1	0	1	1	1	0	1	1	1	0	1	1	1	1	0	0
checksum	0	1	0	0	0	1	0	0	0	1	0	0	0	0	1	1

Note: when adding numbers, a carryout from the most significant bit needs to be added to the result


Internet checksum: weak protection!

example: add two 16-bit integers




Principles of reliable data transfer

- important in application, transport, link layers
 - top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Reliable data transfer protocol (rdt): interfaces



Channel with bit errors

- underlying channel may flip bits in packet
 - checksum to detect bit errors
- the question: how to recover from errors?
 - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
 - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
 - sender retransmits pkt on receipt of NAK

Problems!

what happens if ACK/NAK corrupted?

- sender doesn't know what happened at receiver!
- can't just retransmit: possible duplicate

handling duplicates:

- sender retransmits current pkt if ACK/NAK corrupted
- sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt

stop and wait

sender sends one packet, then waits for receiver response

Discussion

sender:

- seq # added to pkt
- two seq. #s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted

receiver:

- must check if received packet is duplicate
 - state indicates whether 0 or 1 is expected pkt seq #
- note: receiver can not know if its last ACK/NAK received OK at sender

NAK-free protocol

- same functionality, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
 - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

As we will see, TCP uses this approach to be NAK-free

Channels with errors and loss


new assumption: underlying channel can also lose packets (data, ACKs)


 checksum, seq. #, ACKs, retransmissions will be of help ... but not enough

approach: sender waits "reasonable" amount of time for ACK


- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but seq. #'s already handles this
 - receiver must specify seq # of pkt being ACKed
- requires countdown timer


Stop & Wait





Stop & Wait





(d) premature timeout/ delayed ACK

Performance

- Stop & wait is correct, but performance stinks
- e.g.: 1 Gbps link, 15 ms prop. delay, 8000 bit packet:

$$D_{trans} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8 \text{ microsecs}$$

U_{sender}: utilization – fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$


- if RTT=30 msec, IKB pkt every 30 msec: 33kB/sec thruput over I Gbps link
- network protocol limits use of physical resources!

Stop-and-wait operation

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R}$$

$$= \frac{.008}{30.008}$$

$$= 0.00027$$




- Stop-and-wait performance stinks!
- Protocol limits performance of underlying infrastructure (channel)

Pipelined protocols

pipelining: sender allows multiple, "in-flight", yetto-be-acknowledged pkts

- range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation


• two generic forms of pipelined protocols: go-Back-N, selective repeat

Pipelining: increased utilization



Go-Back-N: sender

- sender: "window" of up to N, consecutive transmitted but unACKed pkts
 - k-bit seq # in pkt header




- cumulative ACK: ACK(n): ACKs all packets up to, including seq # n
 - on receiving ACK(n): move window forward to begin at n+1
- timer for oldest in-flight packet
- timeout(n): retransmit packet n and all higher seq # packets in window

Go-Back-N: receiver

- ACK-only: always send ACK for correctly-received packet so far, with highest in-order seq #
 - may generate duplicate ACKs
 - need only remember rcv_base
 - on receipt of out-of-order packet:
 - can discard (don't buffer) or buffer: an implementation decision
 - re-ACK pkt with highest in-order seq #

Receiver view of sequence number space:




received and ACKed

Out-of-order: received but not ACKed

Not received


Go-Back-N in action



Selective repeat

- receiver individually acknowledges all correctly received packets
 - buffers packets, as needed, for eventual in-order delivery to upper layer
- sender times-out/retransmits individually for unACKed packets
 - sender maintains timer for each unACKed pkt
- sender window
 - N consecutive seq #s
 - limits seq #s of sent, unACKed packets

Selective repeat: sender, receiver windows



(b) receiver view of sequence numbers

Selective repeat: sender and receiver

sender

data from above:

if next available seq # in window, send packet

timeout(*n*):

resend packet n, restart timer

ACK(n) in [sendbase,sendbase+N]:

- mark packet n as received
- if n smallest unACKed packet, advance window base to next unACKed seq #

receiver

packet n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order packets), advance window to next not-yetreceived packet


packet n in [rcvbase-N,rcvbase-1]

ACK(n)

otherwise:

ignore


Selective Repeat in action




Selective repeat: a dilemma!

example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3






Selective repeat: a dilemma!

example:

- seq #s: 0, 1, 2, 3 (base 4 counting)
- window size=3

Q: what relationship is needed between sequence # size and window size to avoid problem in scenario (b)?



Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- Principles of congestion control
- TCP congestion control




TCP: overview RFCs: 793,1122, 2018, 5681, 7323

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- full duplex data:
 - bi-directional data flow in same connection
 - MSS: maximum segment size

- cumulative ACKs
- pipelining:
 - TCP congestion and flow control set window size
- connection-oriented:
 - handshaking (exchange of control messages) initializes sender, receiver state before data exchange
- flow controlled:
 - sender will not overwhelm receiver

TCP segment structure




TCP sequence numbers, ACKs

Sequence numbers:


 byte stream "number" of first byte in segment's data

Acknowledgements:

- seq # of next byte expected from other side
- cumulative ACK



TCP sequence numbers, ACKs



simple telnet scenario

TCP round trip time, timeout


- Q: how to set TCP timeout value?
- longer than RTT, but RTT varies!
- too short: premature timeout, unnecessary retransmissions
- too long: slow reaction to segment loss

- Q: how to estimate RTT?
- SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT

TCP round trip time, timeout


EstimatedRTT = $(1-\alpha)$ *EstimatedRTT + α *SampleRTT

- <u>e</u>xponential <u>w</u>eighted <u>m</u>oving <u>a</u>verage (EWMA)
- influence of past sample decreases exponentially fast
- typical value: α = 0.125



TCP round trip time, timeout

- timeout interval: EstimatedRTT plus "safety margin"
 - large variation in **EstimatedRTT:** want a larger safety margin



DevRTT: EWMA of SampleRTT deviation from EstimatedRTT:

DevRTT =
$$(1-\beta)*DevRTT + \beta*|SampleRTT-EstimatedRTT|$$
 (typically, $\beta = 0.25$)

TCP Sender (simplified)

event: data received from application

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
 - think of timer as for oldest unACKed segment
 - expiration interval:TimeOutInterval


event: timeout

- retransmit segment that caused timeout
- restart timer


event: ACK received

- if ACK acknowledges previously unACKed segments
 - update what is known to be ACKed
 - start timer if there are still unACKed segments


TCP sender (simplified)



TCP: retransmission scenarios



TCP: retransmission scenarios



TCP ACK generation [RFC 1122, RFC 2581]


event at receiver	TCP receiver action
arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
arrival of in-order segment with expected seq #. One other segment has ACK pending	immediately send single cumulative ACK, ACKing both in-order segments
arrival of out-of-order segment higher-than-expect seq. # . Gap detected	immediately send <i>duplicate ACK</i> , indicating seq. # of next expected byte
arrival of segment that partially or completely fills gap	immediate send ACK, provided that segment starts at lower end of gap

TCP fast retransmit

TCP fast retransmit

if sender receives 3 additional ACKs for same data ("triple duplicate ACKs"), resend unACKed segment with smallest seq #

 likely that unACKed segment lost, so don't wait for timeout



TCP flow control

Q: What happens if network layer delivers data faster than application layer removes data from socket buffers?

-flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast Application removing data from TCP socket buffers

TCP socket receiver buffers


TCP code

IP code

receiver protocol stack

TCP flow control

- TCP receiver "advertises" free buffer space in rwnd field in TCP header
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust
 RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow




TCP receiver-side buffering

TCP flow control

- TCP receiver "advertises" free buffer space in rwnd field in TCP header
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust
 RcvBuffer
- sender limits amount of unACKed ("in-flight") data to received rwnd
- guarantees receive buffer will not overflow

flow control: # bytes receiver willing to accept




TCP segment format

TCP connection management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters (e.g., starting seq #s)



```
Socket clientSocket =
  newSocket("hostname","port number");
```

```
application


connection state: ESTAB
connection Variables:
  seq # client-to-server
        server-to-client
        rcvBuffer size
        at server,client


network
```

```
Socket connectionSocket =
welcomeSocket.accept();
```

Agreeing to establish a connection

2-way handshake:






Q: will 2-way handshake always work in network?

- variable delays
- retransmitted messages (e.g. req_conn(x)) due to message loss
- message reordering
- can't "see" other side

Agreeing to establish a connection

2-way handshake failure scenarios:



TCP 3-way handshake

Client state

serverSocket.bind(('',serverPort)) serverSocket.listen(1) clientSocket = socket(AF_INET, SOCK_STREAM) connectionSocket, addr = serverSocket.accept() LISTEN LISTEN clientSocket.connect((serverName,serverPort choose init seq num, x send TCP SYN msq SYNSENT SYNbit=1, Seq=x choose init seq num, y send TCP SYNACK SYN RCVD msg, acking SYN SYNbit=1, Seq=y ACKbit=1; ACKnum=x+1 received SYNACK(x) indicates server is live; **ESTAB** send ACK for SYNACK; this segment may contain ACKbit=1, ACKnum=y+1 client-to-server data received ACK(y) indicates client is live **ESTAB**

Server state

serverSocket = socket(AF INET,SOCK STREAM)

Closing a TCP connection

- client, server each close their side of connection
 - send TCP segment with FIN bit = 1
- respond to received FIN with ACK
 - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

Principles of congestion control

Congestion:

• informally: "too many sources sending too much data too fast for network to handle"

- manifestations:
 - long delays (queueing in router buffers)
 - packet loss (buffer overflow at routers)
- different from flow control!
- a top-10 problem!




congestion control: too many senders, sending too fast


flow control: one sender too fast for one receiver


Simplest scenario:

- one router, infinite buffers
- input, output link capacity: R
- two flows
- no retransmissions needed




Q: What happens as arrival rate λ_{in} approaches R/2?






large delays as arrival rate λ_{in} approaches capacity


- one router, finite buffers
- sender retransmits lost, timed-out packet
 - application-layer input = application-layer output: $\lambda_{in} = \lambda_{out}$
 - transport-layer input includes retransmissions : $\lambda'_{in} \ge \lambda_{in}$



Idealization: perfect knowledge


sender sends only when router buffers available






Idealization: some perfect knowledge


- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost



Idealization: some perfect knowledge

- packets can be lost (dropped at router) due to full buffers
- sender knows when packet has been dropped: only resends if packet known to be lost







R/2

 $\lambda_{\text{in}}^{\prime}$

Realistic scenario: *un-needed duplicates*


- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered





Realistic scenario: un-needed duplicates

- packets can be lost, dropped at router due to full buffers – requiring retransmissions
- but sender times can time out prematurely, sending two copies, both of which are delivered




"costs" of congestion:

- more work (retransmission) for given receiver throughput
- unneeded retransmissions: link carries multiple copies of a packet
 - decreasing maximum achievable throughput


- *four* senders
- multi-hop paths
- timeout/retransmit

 $\underline{\mathbf{Q}}$: what happens as λ_{in} and λ_{in} increase?

<u>A:</u> as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput \rightarrow 0



Causes/costs of congestion: scenario 3




another "cost" of congestion:

when packet dropped, any upstream transmission capacity and buffering used for that packet was wasted!

Approaches towards congestion control

End-end congestion control:


- no explicit feedback from network
- congestion inferred from observed loss, delay
- approach taken by TCP



Approaches towards congestion control

Network-assisted congestion control:

- routers provide direct feedback to sending/receiving hosts with flows passing through congested router
- may indicate congestion level or explicitly set sending rate
- TCP ECN, ATM, DECbit protocols




Chapter 3: roadmap

- Transport-layer services
- Multiplexing and demultiplexing
- Connectionless transport: UDP
- Principles of reliable data transfer
- Connection-oriented transport: TCP
- Principles of congestion control
- TCP congestion control
- Evolution of transport-layer functionality




TCP congestion control: AIMD

 approach: senders can increase sending rate until packet loss (congestion) occurs, then decrease sending rate on loss event



TCP congestion control: details



TCP sending behavior:


 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

TCP rate
$$\approx \frac{\text{cwnd}}{\text{RTT}}$$
 bytes/sec

- TCP sender limits transmission: LastByteSent- LastByteAcked < cwnd
- cwnd is dynamically adjusted in response to observed network congestion (implementing TCP congestion control)

TCP slow start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = 1 MSS
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow, but ramps up exponentially fast




TCP: detecting, reacting to loss

- loss indicated by timeout:
 - cwnd set to 1 MSS;
 - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
 - dup ACKs indicate network capable of delivering some segments
 - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to 1 (timeout or 3 duplicate acks)

TCP: switching from slow start to CA

Q: when should the exponential increase switch to linear?


A: when **cwnd** gets to 1/2 of its value before timeout.



Implementation:


- variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event

Summary: TCP congestion control




TCP CUBIC

- Is there a better way than AIMD to "probe" for usable bandwidth?
- Insight/intuition:
 - W_{max}: sending rate at which congestion loss was detected
 - congestion state of bottleneck link probably (?) hasn't changed much
 - after cutting rate/window in half on loss, initially ramp to to W_{\max} faster, but then approach W_{\max} more slowly




TCP CUBIC

- K: point in time when TCP window size will reach W_{max}
 - K itself is tuneable
- increase W as a function of the cube of the distance between current time and K
 - larger increases when further away from K
 - smaller increases (cautious) when nearer K
- TCP CUBIC default in Linux, most popular TCP for popular Web servers




TCP and the congested "bottleneck link"

 TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link




TCP and the congested "bottleneck link"

- TCP (classic, CUBIC) increase TCP's sending rate until packet loss occurs at some router's output: the bottleneck link
- understanding congestion: useful to focus on congested bottleneck link



Delay-based TCP congestion control

Keeping sender-to-receiver pipe "just full enough, but no fuller": keep bottleneck link busy transmitting, but avoid high delays/buffering



Delay-based approach:

- RTT_{min} minimum observed RTT (uncongested path)
- uncongested throughput with congestion window cwnd is cwnd/RTT_{min}

```
increase cwnd linearly /* since path not congested */
else if measured throughput "far below" uncongested throughout
decrease cwnd linearly /* since path is congested */
```


Delay-based TCP congestion control

- congestion control without inducing/forcing loss
- maximizing throughout ("keeping the just pipe full...") while keeping delay low ("...but not fuller")
- a number of deployed TCPs take a delay-based approach
 - BBR deployed on Google's (internal) backbone network

Explicit congestion notification (ECN)


TCP deployments often implement *network-assisted* congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
 - policy to determine marking chosen by network operator
- congestion indication carried to destination
- destination sets ECE bit on ACK segment to notify sender of congestion
- involves both IP (IP header ECN bit marking) and TCP (TCP header C,E bit marking)



TCP fairness


Fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Q: is TCP Fair?

Example: two competing TCP sessions:

- additive increase gives slope of 1, as throughout increases
- multiplicative decrease decreases throughput proportionally



Is TCP fair?

A: Yes, under idealized assumptions:

- same RTT
- fixed number of sessions only in congestion avoidance

Fairness: must all network apps be "fair"?

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss
- there is no "Internet police" policing use of congestion control

Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this, e.g., link of rate R with 9 existing connections:
 - new app asks for 1 TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2

Evolving transport-layer functionality


- TCP, UDP: principal transport protocols for 40 years
- different "flavors" of TCP developed, for specific scenarios:

Scenario	Challenges
Long, fat pipes (large data	Many packets "in flight"; loss shuts down
transfers)	pipeline
Wireless networks	Loss due to noisy wireless links, mobility;
	TCP treat this as congestion loss
Long-delay links	Extremely long RTTs
Data center networks	Latency sensitive
Background traffic flows	Low priority, "background" TCP flows

- moving transport—layer functions to application layer, on top of UDP
 - HTTP/3: QUIC

QUIC: Quick UDP Internet Connections

- application-layer protocol, on top of UDP
 - increase performance of HTTP
 - deployed on many Google servers, apps (Chrome, mobile YouTube app)




QUIC: Quick UDP Internet Connections

adopts approaches we've studied in this chapter for connection establishment, error control, congestion control


- error and congestion control: "Readers familiar with TCP's loss detection and congestion control will find algorithms here that parallel well-known TCP ones." [from QUIC specification]
- connection establishment: reliability, congestion control, authentication, encryption, state established in one RTT
- multiple application-level "streams" multiplexed over single QUIC connection
 - separate reliable data transfer, security
 - common congestion control

QUIC: Connection establishment



TCP (reliability, congestion control state) + TLS (authentication, crypto state)


2 serial handshakes



QUIC: reliability, congestion control, authentication, crypto state

1 handshake

QUIC: streams: parallelism, no HOL blocking




(a) HTTP 1.1


Chapter 3: summary


- principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- instantiation, implementation in the Internet
 - UDP
 - TCP

Up next:

- leaving the network "edge" (application, transport layers)
- into the network "core"
- two network-layer chapters:
 - data plane
 - control plane







Delay modeling

Q: How long does it take to receive an object from a Web server after sending a request?

Ignoring congestion, delay is influenced by:

- TCP connection establishment
- data transmission delay
- slow start

Notation, assumptions:

- Assume one link between client and server of rate R
- S: MSS (bits)
- O: object size (bits)
- no retransmissions (no loss, no corruption)

Window size:


- First assume: fixed congestion window, W segments
- Then dynamic window, modeling slow start

Fixed congestion window (1)

First case:

WS/R > RTT + S/R: ACK for firs segment in window returns before window's worth of data sent

delay = 2RTT + O/R




Fixed congestion window (2)

Second case:

 WS/R < RTT + S/R: wait for ACK after sending window's worth of data sent

delay = 2RTT + O/R + (K-1)[S/R + RTT - WS/R]



TCP Delay Modeling: Slow Start (1)

Now suppose window grows according to slow start

Will show that the delay for one object is:

$$Latency = 2RTT + \frac{O}{R} + P \left[RTT + \frac{S}{R} \right] - (2^{P} - 1) \frac{S}{R}$$

where P is the number of times TCP idles at server:

$$P = \min\{Q, K-1\}$$

- where Q is the number of times the server idles if the object were of infinite size.
- and K is the number of windows that cover the object.

TCP Delay Modeling: Slow Start (2)

Delay components:


- 2 RTT for connection estab and request
- O/R to transmit object
- time server idles due to slow start

Server idles: P = min{K-1,Q} times

Example:

- \cdot O/S = 15 segments
- K = 4 windows
- Q = 2
- $P = min\{K-1,Q\} = 2$

Server idles P=2 times



TCP Delay Modeling (3)

 $\frac{S}{R}$ + RTT = time from when server starts to send segment until server receives acknowledgement


initiate TCP

 $2^{k-1} \frac{S}{R} = \text{time to transmit the kth window}$

$$\left[\frac{S}{R} + RTT - 2^{k-1} \frac{S}{R}\right]^{+} = \text{idle time after the } k\text{th window}$$

delay =
$$\frac{O}{R} + 2RTT + \sum_{p=1}^{P} idleTime_{p}$$

= $\frac{O}{R} + 2RTT + \sum_{k=1}^{P} \left[\frac{S}{R} + RTT - 2^{k-1} \frac{S}{R} \right]$
= $\frac{O}{R} + 2RTT + P[RTT + \frac{S}{R}] - (2^{P} - 1) \frac{S}{R}$



3-107

TCP Delay Modeling (4)

Recall K = number of windows that cover object

How do we calculate K?

$$K = \min\{k : 2^{0}S + 2^{1}S + \dots + 2^{k-1}S \ge O\}$$

$$= \min\{k : 2^{0} + 2^{1} + \dots + 2^{k-1} \ge O/S\}$$

$$= \min\{k : 2^{k} - 1 \ge \frac{O}{S}\}$$

$$= \min\{k : k \ge \log_{2}(\frac{O}{S} + 1)\}$$

$$= \left\lceil \log_{2}(\frac{O}{S} + 1) \right\rceil$$