Advanced Topics in Malware Analysis

Software Representation

Brendan Saltaformaggio, PhD

Assistant Professor

School of Electrical and Computer Engineering

Software Abstractions



Learning Objectives

- Describe software representation
- Describe basic blocks of software
- Reconstruct control flow graph
- Describe various types of paths
- Utilize paths to observe dependencies



Why Create Abstractions of Software?

- Original representations are hard for humans to analyze
 - Source code
 - Programs written in multiple languages
 - · Millions of lines
 - · External dependencies
 - Binaries
 - Across machines and platforms
 - Lack of semantic info. --- No symbols
 - Source code + binaries + test cases
 - Who thinks GDB is fun? I do... ☺

- These are even harder for a machine to analyze!
- And, wouldn't it be nice to make a machine do the reverse engineering for us??



Software Representations

 Software is translated into certain representations before analyses are applied

Outline:

- Basic blocks
- Control flow graphs
- Data flow graphs
- Program dependence graphs
- Super control flow graphs
- Call graph



Advanced Topics in Malware Analysis

Software Representation

Brendan Saltaformaggio, PhD

Assistant Professor

School of Electrical and Computer Engineering

Basic Blocks



Program Representation: Basic Blocks

- A basic block is a sequence of consecutive statements with a single entry and a single exit
- Each block has a **unique** entry point and exit point
- Control always enters a basic block at its entry point and exits from its exit
 point
- There is **no possibility** of **exit** or **halt** at any point **inside** the basic block
- The entry and exit points of a basic block may coincide when the block contains only a single statement



Basic Blocks: Source Code Example

- Basic blocks are a valid abstraction for software analysis at any level!
 - Both source code and binary analysis

```
1. float pow(int x, int y)
2. {
       int power;
       float z;
       if (y < 0)
          power = -y;
       else
          power = y;
       z = 1.0;
10.
      while(power != 0) {
11.
          z = z \star x;
12.
          power--;
13.
14.
       if (y < 0)
15.
          z = 1/z;
16.
       return z;
17.}
```



Basic Blocks: Source Code Example

- Basic blocks are a valid abstraction for software analysis at any level!
 - Both source code and binary analysis

| Block | Lines | Entry point | Exit point |
|-------|------------|-------------|------------|
| 1 | 2, 3, 4, 5 | 1 | 5 |
| 2 | 6 | 6 | 6 |
| 3 | 8 | 8 | 8 |
| 4 | 9 | 9 | 9 |
| 5 | 10 | 10 | 10 |
| 6 | 11, 12 | 11 | 12 |
| 7 | 14 | 14 | 14 |
| 8 | 15 | 15 | 15 |
| 9 | 16 | 16 | 16 |

```
1. float pow(int x, int y)
2. {
       int power;
       float z;
       if (y < 0)
          power = -y;
       else
          power = y;
       z = 1.0;
10.
      while(power != 0) {
11.
          z = z \star x;
12.
          power--;
13.
14.
       if (y < 0)
15.
          z = 1/z;
16.
       return z;
17.}
```



Basic Blocks: Binary Example – Binary Code (1 of 3)

```
.text:00000000000000 pow
                                     proc near
.text:00000000000000000
.text:000000000000000 var ReturnVal
                                     = dword ptr -1Ch
.text:00000000000000 var Y
                                     = dword ptr -18h
.text:00000000000000 var X
                                     = dword ptr -14h
                                     = dword ptr -8
.text:000000000000000 var Z
.text:0000000000000000 var Power
                                     = dword ptr -4
.text:00000000000000000
                                                                        Compiled on
push
                                             rbp
                                                                        64-bit Linux
.text:0000000000000001
                                             rbp, rsp
                                     mov
                                             [rbp+var X], edi
.text:0000000000000004
                                     mov
                                             [rbp+var Y], esi
.text:00000000000000007
                                     mov
                                             [rbp+var Y], 0
.text:000000000000000A
                                     cmp
                                             short loc 1A ; if (y < 0)
.text:000000000000000E
                                     jns
eax, [rbp+var Y]
                                     mov
.text:0000000000000013
                                                            ; power = -y
                                             eax
                                     neg
                                             [rbp+var Power], eax
.text:0000000000000015
                                     mov
                                             short loc 20
.text:0000000000000018
                                     jmp
```



Basic Blocks: Binary Example – Binary Code (2 of 3)

```
.text:00000000000001A
.text:00000000000001A loc 1A:
                                      eax, [rbp+var Y] ; else power = y
.text:00000000000001A
                                mov
                                      [rbp+var Power], eax
.text:000000000000001D
                                mov
                                                                Compiled on
64-bit Linux
eax, cs:const float 1 0
                                mov
                                      [rbp+var Z], eax; z = 1.0
.text:00000000000000026
                                mov
                                      short loc 42
.text:00000000000000029
                                jmp
```



Basic Blocks: Binary Example – Binary Code (3 of 3)

```
.text:00000000000002B loc 2B:
                                     cvtsi2ss xmm0, [rbp+var X]
.text:0000000000000002B
                                             xmm1, [rbp+var Z]
movss
                                            xmm0, xmm1
                                                         z = z * x
.text:0000000000000035
                                     mulss
                                            [rbp+var Z], xmm0
.text:0000000000000039
                                     movss
                                             [rbp+var Power], 1; power = power - 1;
.text:00000000000003E
                                     sub
.text:0000000000000042
                                 Prev. Slide Jumps Here
.text:0000000000000042 loc 42:
                                             [rbp+var Power], 0; while ( power != 0 )
.text:0000000000000042
                                     cmp
                                             short loc 2B
.text:0000000000000046
                                     jnz
                                             [rbp+var Y], 0; if (y < 0)
                                                                                 Compiled on
.text:0000000000000048
                                     cmp
                                                                                 64-bit Linux
.text:000000000000004C
                                     jns
                                             short loc 60
.text:00000000000004E
                                             xmm0, cs:const float 1 0
                                     movss
                                            xmm0, [rbp+var Z]; z = 1 / z;
.text:0000000000000056
                                     divss
                                             [rbp+var Z], xmm0
.text:00000000000005B
                                     movss
.text:00000000000000000000 loc 60:
eax, [rbp+var Z]
                                     mov
.text:0000000000000063
                                             [rbp+var ReturnVal], eax ; return value = z
                                     mov
                                             xmm0, [rbp+var ReturnVal]
.text:0000000000000066
                                     movss
.text:000000000000006B
                                             rbp
                                     pop
.text:00000000000006C
                                     retn
.text:00000000000006C pow
                                     endp
```

Finding The Basic Blocks (1 of 3)

```
.text:00000000000000 pow
                                     proc near
.text:00000000000000000
.text:0000000000000000 var ReturnVal
                                    = dword ptr -1Ch
.text:000000000000000 var Y
                                    = dword ptr -18h
.text:00000000000000 var X
                                    = dword ptr -14h
.text:000000000000000 var Z
                                    = dword ptr -8
                                    = dword ptr -4
.text:000000000000000 var Power
.text:00000000000000000
push
                                            rbp
.text:0000000000000001
                                     mov
                                            rbp, rsp
                                            [rbp+var X], edi
.text:0000000000000004
                                     mov
                            Block 1
                                            [rbp+var Y], esi
.text:0000000000000007
                                     mov
                                            [rbp+var Y], 0
.text:000000000000000A
                                     cmp
                                            short loc 1A ; if (y < 0)
.text:000000000000000E
                                     jns
                                            eax, [rbp+var Y]
mov
.text:0000000000000013
                                                           ; power = -y
                                     neg
                             Block 2
.text:0000000000000015
                                            [rbp+var Power], eax
                                     mov
.text:0000000000000018
                                            short loc 20
                                     dmj
.text:00000000000001A ;
```



Finding The Basic Blocks (2 of 3)

```
..text:00000000000001A loc 1A:
                                           eax, [rbp+var Y] ; else power = y
.text:00000000000001A
                            Block 3
                                            [rbp+var Power], eax
.text:000000000000001D
.text:00000000000000000000 loc 20:
                                           eax, cs:const float 1 0
mov
                                            [rbp+var Z], eax; z = 1.0
                           Block 4
.text:00000000000000026
                                    mov
                                           short loc 42
.text:00000000000000029
                                    dmt
.text:00000000000002B loc 2B:
                                    cvtsi2ss xmm0, [rbp+var X]
.text:000000000000002B
                                           xmm1, [rbp+var Z]
movss
                           Block 5
                                    mulss
                                           xmm0, xmm1
.text:000000000000035
                                            [rbp+var Z], xmm0
.text:0000000000000039
                                    movss
                                            [rbp+var Power], 1 ; power = power - 1;
.text:000000000000003E
                                    sub
```



Finding The Basic Blocks (3 of 3)

```
.text:000000000000042 loc 42:
                                                 [rbp+var Power], 0; while ( power != 0 )
.text:0000000000000042
                                Block 6
                                                short loc 2B
.text:0000000000000046
                                                 [rbp+var Y], 0; if (y < 0)
.text:0000000000000048
                                Block 7
                                                short loc 60
.text:000000000000004C
                                                xmm0, cs:const float 1 0
.text:000000000000004E
                                        movss
                                                xmm0, [rbp+var Z]; z = 1 / z;
.text:0000000000000056
                                        divss
                                Block 8
                                                 [rbp+var Z], xmm0
.text:00000000000005B
                                        movss
.text:00000000000000000
.text:00000000000000000000 loc 60:
.text:00000000000000060
                                                eax, [rbp+var Z]
                                        mov
                                                 [rbp+var ReturnVal], eax ; return value = z
.text:0000000000000063
                                        mov
                                Block 9
                                                xmm0, [rbp+var ReturnVal]
.text:000000000000066
                                        movss
.text:000000000000006B
                                                 rbp
                                        pop
.text:000000000000006C
                                        retn
.text:00000000000006C pow
                                        endp
```



Source Blocks != Binary Blocks

- Basic blocks may be a valid abstraction for software analysis at any level
- But they are not comparable across levels!
- As we have seen, compilation will significantly rearrange the logic of a program
- Consider: Our example has no optimization!



```
.text:00000000000002B loc 2B:
   .text:0000000000000002B
                                            cvtsi2ss xmm0, [rbp+var X]
                                                    xmm1, [rbp+var Z]
                                            movss
  float pow(int x, int y)
                                   Block 5
                                                    xmm0, xmm1
                                            mulss
                                                                    z = z * x
2. {
                                                    [rbp+var Z], xmm0
3.
                                            movss
        int power;
                                            sub
                                                     [rbp+var Power], 1 ; power = power - 1;
4.
        float z;
5.
        if (y < 0)
           power = -y;
                                                     [rbp+var Power], 0 ; while ( power != 0 )
7.
        else
                                   Block 6
                                                    short loc 2B
           power = y;
                                                     [rbp+var Y], 0 ; if (y < 0)
9.
       z = 1.0;
                                   Block 7
                                                    short loc 60
10.5
       while (power *!= )
11. 6
                                                    xmm0, cs:const float 1 0
                                            movss
            z = z * x;
                                                    xmm0, [rbp+var Z]; z = 1 / z;
                                   Block 8
                                            divss
12.
           power = power - 1;
                                                     [rbp+var Z], xmm0
                                            movss
13.
14.
       if (y < 0)
15.<sup>8</sup>
            z = 1/z;
                                                    eax, [rbp+var Z]
                                            mov
16.9
       return z;
                                                     [rbp+var ReturnVal], eax ; return value =
                                            mov
17. }
                                   Block 9
   .text:000000000000066
                                                    xmm0, [rbp+var ReturnVal]
                                            movss
   .text:000000000000006B
                                            pop
                                                    rbp
   .text:000000000000006C
                                            retn
                                                                                        Georgia
   .text:0000000000006C pow
                                            endp
```

Advanced Topics in Malware Analysis

Software Representation

Brendan Saltaformaggio, PhD

Assistant Professor

School of Electrical and Computer Engineering

Control Flow Graphs (CFG)



Control Flow Graph (CFG)

- The most commonly used program representation
- A CFG abstracts the paths that might be traversed through a program during its execution guided solely by branching constructs
- A control flow graph (sometimes called flow graph) G is defined as a finite set N
 of nodes and a finite set E of edges
- An edge (i, j) in **E** connects two nodes n_i and n_j in **N**
- We often write G=(N, E) to denote a control flow graph G with nodes given by N and edges by E



Control Flow Graph (CFG)

- In a control flow graph of a program, each basic block becomes a node
- Edges are used to indicate the flow of execution (i.e., control) between blocks
- A CFG edge (i, j) connecting basic blocks b_i and b_j implies that control can be transferred from block b_i to block b_j
- We assume that there exists a node labeled Start in N that has no incoming edge
 - · The Start node is assigned outgoing edges to all other nodes which have no incoming edge
- We also assume that there exists a node labeled End in N that has no outgoing edge
 - The End node is assigned incoming edges from all other nodes which have no outgoing edge
- The Start and End nodes are important to simplify automated analyses



CFG Example

```
float pow(int x, int y)
         int power;
         float z;
        if (y < 0)
             power = -y;
         else
             power = y;
     4 \Box z = 1.0;
     5 \square \text{while (power != 0)}  {
             z = z \star x;
11.
12.
             power = power - 1;
13.
14. 7 \sqsubseteq if (y < 0)
             z = 1/z;
16. 9 _return z;
17. }
```

```
int power;
                                             float z;
                                             if (y < 0)
                                                                false
                                      true
CFG(pow) = (N,E)
                                 power = -y;
                                                          power = y;
                                                                          3
N={Start, 1, 2, 3, 4, 5,
                                                z = 1.0;
            6, 7, 8, 9, End}
                                                                   false
                                          while(power != 0)
                                                     ♦ true
E={(Start,1), (1, 2), (1, 3),
                                          z = z * x;
                                          power = power - 1;
            (2,4), (3,4), (4,5),
            (5, 6), (6, 5), (5, 7),
                                               if (y < 0)
                                                              true
            (7, 8), (7, 9), (8, 9),
                                             false
                                                                        8
                                                         z = 1/z;
            (9, End)}
                                                return z;
                                                              Georgia
```

Start

End

CFG Example


 CFG nodes are typically represented by only their basic block number

```
float pow(int x, int y)
        int power;
        float z;
       if (y < 0)
             power = -y;
            power = y;
     4 \Box_z = 1.0;
10. 5 \leftarrow \text{while (power != 0)} {
             z = z * x;
11.
12.
             power = power - 1;
13.
14. 7 \sqsubseteq if (y < 0)
             z = 1/z;
16. 9 _return z;
17. }
```

```
CFG(pow) = (N,E)


N={Start, 1, 2, 3, 4, 5, 6, 7, 8, 9, End}

E={(Start,1), (1, 2), (1, 3), (2,4), (3, 4), (4, 5), (5, 6), (6, 5), (5, 7), (7, 8), (7, 9), (8, 9), (9, End)}
```



Where Have I Seen This Before?

- IDA's Graph View displays a CFG
- IDA detects basic blocks based on control transfer instructions and its (very limited) knowledge of the control transfer targets
- IDA's basic blocks will often be wrong if the control transfer target is aliased or dynamically computed



Advanced Topics in Malware Analysis

Software Representation

Brendan Saltaformaggio, PhD

Assistant Professor


School of Electrical and Computer Engineering

Paths



Paths

- A CFG represents all paths (that we know of) which **might** be traversed during execution
- To reason about actual executions we need to define the notion of a Path
- Consider a control flow graph G= (N, E)




Paths (Cont.)

- A Path P consists of k edges from E, where k>0
 - That is: P = (e_1, e_2, ... e_k)
- P denotes a path of length k through the control flow graph if the following sequence condition on the sequence of edges holds true
- Given that n_p , n_q , n_r , and n_s are nodes belonging to N and 0 < i < k
- If $e_i = (n_p, n_q)$ and $e_i+1 = (n_r, n_s)$ then n_q must be n_r
- Put simply: Every node in a Path must be reachable by a single traversal from the Path's first node to its last



Complete Paths vs. SubPaths (Cont.)


- Our definition of a Path allows for two types of valid Paths:
 - Complete Path: A valid Path (by our previous definition) which includes both the Start and End nodes from the CFG
 - Subpath: A valid Path (by our previous definition) which forms a subsequence of a Complete Path



Complete Paths vs. SubPaths (Count.)

In the figure:

- The set of bold edges forms a Complete Path:
 - P1 = (Start, 1, 2, 4, 5, 6, 5, 7, 9, End)
 - Specified unambiguously using edges:
 - P1= ((Start, 1), (1, 2), (2, 4), (4, 5), (5, 6), (6, 5), (5, 7), (7, 9), (9, End))
 - The set of dashed edges forms a Subpath:
 - P2 = (5, 7, 8, 9)
- NOT a valid Path:
 - P0 = (Start, 1, **2, 3,** 4, 5, 6, 5, 7, 9, End)



Feasible Paths vs. Infeasible Paths

- One of the most important Path analyses is Path Feasibility is used in:
 - Security (e.g., can the malware execute that payload?)
 - **Software engineering** (e.g., how can we optimize the sequence of these program components?)
 - Debugging (e.g., given our current state, which branch will the program take next?)
 - Compilers (e.g., is this dead code able to be removed?)


- A path P through a CFG is considered **feasible** if there exists at least one test case which when input to the program causes **every** node in P to be traversed
- Note that by this definition, Subpaths can also be considered feasible
- In the face of bugs or exploits, a general solution for Path feasibility is not possible
- Techniques which solve localized versions of Path feasibility do exist (compilers do it)



Feasible Paths vs. Infeasible Paths

- Two Feasible and Complete Paths:
 - P1= (Start, 1, 2, 4, 5, 6, 5, 7, 8, 9, End)
 - P2= (Start, 1, 3, 4, 5, 6, 5, 7, 9, End)
- Two Feasible Subpaths:
 - P3= (Start, 1, 2, 4)
 - P4= (5, 7, 8, 9, End)
- Two Infeasible Paths:
 - P1= (Start, 1, 3, 4, 5, 6, 5, 7, 8, 9, End)
 - P2= (Start, 1, 2, 4, 5, 7, 9, End)

Notice that Paths can be Complete but Infeasible




Number of Paths

- There can be many distinct paths through a program
- A program with no conditional statements contains exactly one path
 - It begins at the Start node, traverses every node, and terminates at the End node
- Every additional condition in the program can increase the number of distinct paths by at least one
- Depending on their location in the CFG, conditional statements can have a multiplicative effect on the number of paths
- This leads to a problem that nearly ALL static analysis techniques suffer from:
 Path Explosion!
- Research tools are always struggling to scale to real world programs because exploring all their paths becomes impossible!

Reasoning Along Paths

- Just like basic blocks make analysis easier by giving structure to sequences of statements...
- Many problems which are globally intractable (i.e., cannot be solved for entire programs) can be solved locally (i.e., on a single Path)
- This is because a single Path allows for direct inference of execution behaviors
- **Example**: What was the value of Y that produced this path?
- Now how can we teach an algorithm to figure that out??



Advanced Topics in Malware Analysis

Software Representation

Brendan Saltaformaggio, PhD

Assistant Professor


School of Electrical and Computer Engineering

Dominator Analysis



Dependency Analysis

- We can look at a path and observe dependencies
 - "The value of power depends on the value of y"
 - "The execution of block 3 depends on the execution of block 1"
 - "The loop iteration depends on the value of power"
- These dependencies can be modeled so that an algorithm can analyze them
- Control Dependencies
 - Dominator
 - Post-dominator
 - Immediate Dominator/Post-dominator
- Data Dependencies




Dominator

• X dominates Y if all possible program paths from START to Y have to pass

through X

```
void sumUp(int n) {
  int sum = 0;
  int i = 1;
  while ( i < n ) {
    i = i + 1;
    sum = sum + i;
  }
  printf("%d", sum);
}</pre>
```




Georgia

Strict Dominator

X strictly dominates Y if X dominates Y and X!=Y

```
void sumUp(int n) {
   int sum = 0;
   int i = 1;
   while ( i < n ) {
      i = i + 1;
      sum = sum + i;
   }
   printf("%d", sum);
}</pre>
```




Immediate Dominator

• X is the immediate dominator of Y if X is the last dominator of Y along a path

from Start to Y

```
void sumUp(int n) {
   int sum = 0;
   int i = 1;
   while ( i < n ) {
      i = i + 1;
      sum = sum + i;
   }
   printf("%d", sum);
}</pre>
```



 $IDOM(4) = \{2\}$




Dominators Allow for **Backward** Reasoning

- Dominators allow algorithms to determine backward control flow
- Put simply: "Who needs to execute for block X to execute?"

```
DOM(START) = {}
DOM(1) = {1}
DOM(2) = {1, 2}
DOM(3) = {1, 2, 3}
DOM(4) = {1, 2, 4}
DOM(END) = {1, 2, 4}
```

- Notice that Start and End are not true nodes!
- Notice that DOM(END) = Blocks executed for ANY input




Post-Dominator

- X post-dominates Y if every possible program path from Y to End has to pass through X
 - Similar strict post-dominator & immediate post-dominator

```
void sumUp(int n) {
   int sum = 0;
   int i = 1;
   while ( i < n ) {
      i = i + 1;
      sum = sum + i;
   }
   printf("%d", sum);
}</pre>
```

```
PDOM(3) = {2, 3, 4}
SPDOM(3) = {2, 4}
IPDOM(3) = {2}
```



Post-Dominators Allow for **Forward** reasoning

- Post-dominators allow algorithms to determine forward control flow
- Put simply: "If block X executes, then who else must execute?"

```
PDOM(START) = {1, 2, 4}

PDOM(1) = {1, 2, 4}


PDOM(2) = {2, 4}

PDOM(3) = {2, 3, 4}

PDOM(4) = {4}

PDOM(END) = {}
```


Notice that PDOM(START) = DOM(END). Why??





Back Edges

- Dominators/Post-dominators allow us to define characteristics of the CFG
- The most common: A back edge is an edge whose head dominates its tail
- A "closed loop back edge" is an edge whose head dominates AND post-dominates its tail
- What would be different if block 3 looked like this?



```
i = i + 1;
sum = sum + i;
if(sum > 100)
break;
```



Advanced Topics in Malware Analysis

Software Representation

Brendan Saltaformaggio, PhD

Assistant Professor


School of Electrical and Computer Engineering

Control Dependencies



Control Dependence


- Most importantly, Dominators & Post-dominators allow us to define **Control** Dependence
- Y is control dependent on X iff X directly determines whether Y executes
 - In general, statements inside each branch of a predicate are control dependent on the predicate



Control Dependence - Example

- Y is control dependent on X iff X directly determines whether Y executes
 - 1) X is not strictly post-dominated by Y
 - 2) There exists a path from X to Y such that every node on that path other than X is post-dominated by Y

```
X = 2, Y = 3
Tricky!! CD(2) = \{2\}
                             3 ∉ SPDOM(2) &
2->3->2'->4->End
                             2->3 = \{3\}, 3 \in PDOM(3)
X = 2, Y = 2' (2<sup>nd</sup> iteration)
                             CD(3) = \{2\}
SPDOM(2) = \{4\}
                            Why not CD(3) = \{1, 2\}?
2' ∉ SPDOM(2) &
                            X = 1, Y = 3
2->2' = \{3, 2'\}, and
                            3 ∉ SPDOM(1) &
2' ∈ PDOM(3)
                             1->3 = \{2,3\}, but
2' \in PDOM(2')
                             3 ∉ PDOM(2)
                             3 \in PDOM(3)
```



- May seem confusing, but this is really just the "unrolling" of the loop
- In fact, "loop unrolling" is the concrete term for "loop induction"
- Algorithm Analysis in Binary Analysis ... Mind = Blown



Control Dependence is **not** Syntactically Explicit

```
void sumUp(int n) {
   int sum = 0;
   int i = 1;
   while ( i < n ) {
      i = i + 1;
      if(i % 2 == 0)
            continue;
      sum = sum + i;
   }
   printf("%d", sum);
}</pre>
```

```
Start
                int sum = 0;
                int i = 1;
              while ( i < n )</pre>
CD(4) = ?
          4(sum = sum + i;
            printf("%d", sum);
                       End
```



Control Dependence is **not** Syntactically Explicit


- Y is control dependent on X iff X directly determines whether Y executes
 - 1) X is not strictly post-dominated by Y
 - 2) There exists a path from X to Y such that every node on that path other than X is post-dominated by Y

$$X = 2, Y = 4$$

SPDOM(2) = {5}

$$X = 3, Y = 4$$
 $4 \notin SPDOM(2) \&$ $2->4 = \{3, 4\}, but$ $4 \notin SPDOM(3) \&$ $4 \notin PDOM(3) &$ $4 \notin PDOM(4)$ $4 \in PDOM(4)$


So $CD(4) = \{3\}$ So, 4 is **not** control dependent on 2!





Control Dependence is VERY Tricky!

- Y is control dependent on X iff X directly determines whether Y executes
 - 1) X is not strictly post-dominated by Y
 - 2) There exists a path from X to Y such that every node on that path other than X is post-dominated by Y
- Can one statement be control dependent on two predicates?



```
if ( a || b )
   foo();
bar();
```

```
X = 2, Y = 3

SPDOM(2) = \{4\}

3 \notin SPDOM(2) \&

2->3 = \{3\}, 3 \in PDOM(3)
```

So $CD(3) = \{2\}$... but wait

You didn't think we were finished with assembly, did you??

cmp rax, 0

cmp rbx, 0

foo

bar

ine .L2

je .L3

call

call

.L3:

```
X = 1, Y = 3

SPDOM(1) = \{4\}

3 \notin SPDOM(1) \&

1->3 = \{3\}, 3 \in

PDOM(3)
```







Advanced Topics in Malware Analysis

Software Representation

Brendan Saltaformaggio, PhD

Assistant Professor

School of Electrical and Computer Engineering

Data Dependencies




Data Dependence

- X is data dependent on Y iff
 - There is a variable V that is defined at Y and used at X
 - 2) There exists a path of nonzero length from Y to X along which V is not re-defined
- Data dependence is calculated per statement
 - Rarely will results be aggregated per basic block



Data Dependence Example

```
float pow(int x, int y)
2.
3.
       int power;
       float z;
       if (y < 0)
           power = -y;
6.
        else
           power = y;
9.
       z = 1.0;
       while(power != 0) {
10.
11.
            z = z * x;
12.
           power--;
13.
14.
       if (y < 0)
15.
            z = 1/z;
16.
        return z;
17. }
```




Data Dependence Example

- X is data dependent on Y iff
 - There is a variable V that is defined at Y and used at X
 - There exists a path of nonzero length from Y to X along which V is not re-defined
- Data dependence is calculated per statement
 - Rarely will results be aggregated per basic block

 $DD(12) = \{6, 8, 12\}$

But notice, NOT on the variable **y**! Why?


Just like control dependence, data dependence only covers direct dependence, not transitive dependence!



Data Dependence Example 2

- X is data dependent on Y iff
 - There is a variable V that is defined at Y and used at X
 - There exists a path of nonzero length from Y to X along which V is not re-defined
- Data dependence is calculated per statement
 - Rarely will results be aggregated per basic block

DD(14) = {Arg2} DD(15) = {9, 11}





- X is data dependent on Y iff
 - There is a variable V that is defined at Y and used at X
 - There exists a path of nonzero length from Y to X along which V is not redefined

```
.text:00000000000000 pow
                                     proc near
.text:00000000000000000
.text:0000000000000000 var ReturnVal
                                     = dword ptr -1Ch
                                                      DD(.text:000013) =
.text:000000000000000 var Y
                                     = dword ptr -18h
                                                      {.text:000010}
.text:00000000000000 var X
                                     = dword ptr -14h
.text:000000000000000 var Z
                                     = dword ptr -8
                                                     Remember: NOT
                                     = dword ptr -4
.text:0000000000000000000 var Power
                                                     transitive dependence!
push
                                             rbp
.text:000000000000000001
                                             rbp, rsp
                                     mov
                                             [rbp+var X], edi
.text:0000000000000004
                                     mov
                                             [rbp+var Y], esi
.text:00000000000000007
                                     mov
                                             [rbp+var Y], 0
.text:000000000000000A
                                     cmp
                                             short loc 1A; if (y < 0)
.text:000000000000000E
                                      jns
                              reg. read
eax, [rbp+var Y]
                                     mov
.text:0000000000000013
                                                          ; power = -y
                                     neg
                                             eax
                                             [rbp+var Power], eax
.text:0000000000000015
                                     mov
.text:0000000000000018
                                             short loc 20
                                     jmp
.text:00000000000001A
```





- X is data dependent on Y iff
 - There is a variable V that is defined at Y and used at X
 - There exists a path of nonzero length from Y to X along which V is not redefined

```
.text:00000000000000 pow
                                     proc near
.text:00000000000000000
.text:000000000000000 var ReturnVal
                                     = dword ptr -1Ch
                                                       DD(.text:000010) = {
.text:000000000000000 var Y
                                     = dword ptr -18h
                                                        .text:000007,
.text:00000000000000 var X
                                     = dword ptr -14h
                                                        .text:000001
.text:000000000000000 var Z
                                     = dword ptr -8
                                     = dword ptr -4
.text:0000000000000000000 var Power
push
                                             rbp
                                                       reg. read
                                             rbp, rsp
.text:000000000000000001
                                     mov
                                             [rbp+var X], edi
.text:0000000000000004
                                     mov
                                             [rbp+var Y], esimem. read
.text:00000000000000007
                                     mov
                                             [rbp+var /1], 0
.text:000000000000000A
                                     cmp
                                             short loc 1A : if
.text:000000000000000E
                                     jns
rbp+var Y
                                     mov
.text:0000000000000013
                                                           power = -y
                                     neg
                                             [rbp+var Power], eax
.text:000000000000015
                                     mov
.text:0000000000000018
                                             short loc 20
                                     jmp
.text:00000000000001A
```





- X is data dependent on Y iff
 - There is a variable V that is defined at Y and used at X
 - There exists a path of nonzero length from Y to X along which V is not redefined

```
.text:00000000000000 pow
                                       proc near
.text:00000000000000000
                                                          DD(.text:00000E) =
                                       = dword ptr -1Ch
.text:0000000000000000 var ReturnVal
                                                          {.text:00000A}
.text:000000000000000 var Y
                                       = dword ptr -18h
.text:00000000000000 var X
                                       = dword ptr -14h
.text:000000000000000 var Z
                                       = dword ptr -8
                                                       Be careful of implicit
                                       = dword ptr -4
.text:0000000000000000000 var Power
                                                       data flows!
.text:00000000000000000
push
                                               rbp
.text:000000000000000001
                                       mov
                                               rbp, rsp
                                               [rbp+var X], edi
.text:00000000000000004
                                       mov
                              reg. read
                                               [rbp+var Y], esi
.text:00000000000000007
                                       mov
                              (rflags)
.text:000000000000000A
                                               [rbp+var Y], 0
                                       cmp
                                               short loc 1A; if (y < 0)
.text:00000000000000E
                                       ins
eax, [rbp+var Y]
                                       mov
                                                            ; power = -y
.text:0000000000000013
                                       neg
                                               eax
                                               [rbp+var Power], eax
.text:000000000000015
                                       mov
.text:0000000000000018
                                               short loc 20
                                       jmp
.text:00000000000001A
```





- X is data dependent on Y iff
 - There is a variable V that is defined at Y and used at X
 - There exists a path of nonzero length from Y to X along which V is not redefined

```
.text:00000000000000 pow
                                        proc near
                                                             DD(.text:000000)
.text:00000000000000000
                                                             = {START}
.text:0000000000000000 var ReturnVal
                                        = dword ptr -1Ch
.text:000000000000000 var Y
                                        = dword ptr -18h
                                                          Values which come
.text:00000000000000 var X
                                        = dword ptr -14h
                                                          from outside the
                                        = dword ptr -8
.text:000000000000000 var Z
                                                          function are marked
.text:000000000000000 var Power
                                        = dword ptr -4
.text:00000000000000000
                                                          as the START node
.text:000000000000000000
                                       push
                                                rbp
.text:000000000000000001
                                        mov
                                                rbp, rsp
                                                [rbp+var X], edi
.text:00000000000000004
                                        mov
                                                [rbp+var Y], esi
.text:00000000000000007
                                        mov
                                                [rbp+var Y], 0
.text:000000000000000A
                                        cmp
                                                short loc 1A; if (y < 0)
.text:000000000000000E
                                        ins
eax, [rbp+var Y]
                                        mov
                                                             ; power = -y
.text:0000000000000013
                                        neg
                                                [rbp+var Power], eax
.text:0000000000000015
                                        mov
.text:0000000000000018
                                                short loc 20
                                        jmp
.text:000000000000001A
```





- X is data dependent on Y iff
 - There is a variable V that is defined at Y and used at X
 - There exists a path of nonzero length from Y to X along which V is not redefined

```
.text:00000000000000 pow
                                       proc near
.text:00000000000000000
.text:000000000000000 var ReturnVal
                                       = dword ptr -1Ch
                                                          DD(.text:000004)
.text:000000000000000 var Y
                                       = dword ptr -18h
                                                          = \{.\text{text}: 000001,
.text:00000000000000 var X
                                       = dword ptr -14h
                                                          START}
.text:000000000000000 var Z
                                       = dword ptr -8
.text:0000000000000000000 var Power
                                       = dword ptr -4
.text:00000000000000000
push
                                               rbp
                               reg. read
.text:000000000000000001
                                               rbp, rsp
                               (rbp)
                                       mov
                                               [rbp+var X], edi
.text:00000000000000004
                                       mov
                                               [rbp+var Y], esi
.text:00000000000000007
                                       mov
                                               [rbp+var Y], 0
.text:000000000000000A
                                       cmp
                                               short loc 1A; if (y < 0)
.text:000000000000000E
                                       jns
eax, [rbp+var Y]
                                       mov
.text:0000000000000013
                                                            ; power = -y
                                       neg
                                               [rbp+var Power], eax
.text:000000000000015
                                       mov
.text:0000000000000018
                                               short loc 20
                                       jmp
.text:000000000000001A
```



- X is data dependent on Y iff
 - 1) There is a variable V that is defined at Y and used at X
 - 2) There exists a path of nonzero length from Y to X along which V is not re-defined

$DD(.text:0040577A) = \{ \}$

```
.text:0040575F
                           lea
                                   eax, [ebp+cbData]
.text:00405765
                           push
                                                    ; lpcbData
                                   eax
.text:00405766
                           lea
                                   eax, [ebp+Data]
.text:0040576C
                           push
                                                    ; lpData
                                   eax
.text:0040576D
                           push
                                                    ; lpType
                                   ebx
                                                    ; lpReserved
.text:0040576E
                           push
                                   ebx
                                   offset aCdkey 0 ; "CDKey"
.text:0040576F
                           push
                                 [ebp+phkResult] ; hKey
.text:00405774
                           push
                                   RegQueryValueExA
.text:0040577A
                          call
.text:00405780
                                   eax, eax
                           test
.text:00405782
                                   short loc 4057B3
                           jnz
```




- X is data dependent on Y iff
 - 1) There is a variable V that is defined at Y and used at X
 - 2) There exists a path of nonzero length from Y to X along which V is not re-defined

```
DD(.text:00405780) = \{.text:0040577A\}
                                         Calls redefine the RAX/EAX register!
.text:0040575F
                            lea
                                     eax, [ebp+cbData]
.text:00405765
                            push
                                                       ; lpcbData
                                     eax
.text:00405766
                            lea
                                           [ebp+Data]
                                     eax,
.text:0040576C
                            push
                                                       ; lpData
                                     eax
.text:0040576D
                                                       ; lpType
                            push
                                     ebx
                                                       ; lpReserved
                            push
.text:0040576E
                                     ebx
                                     offset aCdkey 0 ; "CDKey"
.text:0040576F
                            push
                                     [ebp+phkResult] ; hKey
.text:00405774
                            push
                   reg. read
                                     RegQueryValueExA
                            call
.text:0040577A
                   (eax)
.text:00405780
                                     eax, eax
                            test
.text:00405782
                                     short loc 4057B3
                            jnz
```

Don't forget about implicit flows!!



- X is data dependent on Y iff
 - 1) There is a variable V that is defined at Y and used at X
 - 2) There exists a path of nonzero length from Y to X along which V is not re-defined





- X is data dependent on Y iff
 - 1) There is a variable V that is defined at Y and used at X
 - 2) There exists a path of nonzero length from Y to X along which V is not re-defined

DD(.text:004010C1) = {.text:004010BB, ??}

```
.text:004010B8
                            push
                                     ebp
.text:004010B9
                                     ebp, esp
                            mov
                                     eax, off 429014
.text:004010BB
                            mov
                    reg. read
.text:004010C0
                                     esi
                            push
                    (eax)
.text:004010C1
                                     byte ptr [eax],
                            cmp
```

- Handling global data dependence is implementation specific!
- Options:
 - 1) Only track global data globally
 - 2) Track all data globally
 - 3) Note global dependencies at the START node & patch later



Advanced Topics in Malware Analysis

Software Representation

Brendan Saltaformaggio, PhD

Assistant Professor

School of Electrical and Computer Engineering

Def-Use Chains




- DU chains (Def-Use chains) link the definition of a variable and the use of the variable
- Pro: Very fast to collect data dependencies, easy to program (table data structure)
- Con: Must compute & store every variable, cannot omit unused variables

```
1. float pow(int x, int y)
                             // D: x, y
2. {
3.
       int power;
4.
       float z;
                              // U: y
5.
       if (y < 0)
6.
                              // D: power
           power = -y;
                                             U: v
7.
       else
8.
                              // D: power
           power = y;
                                             U: y
                              // D: z
9.
       z = 1.0;
10.
       while(power != 0) {
                             // U: power
                              // D: z
11.
           z = z * x;
                                         U: x, z
12.
                              // D: power
           power--;
                                             U: power
13.
       if (y < 0)
14.
                              // U: y
           z = 1/z;
                              // D: z
15.
                                         U: z
16.
       return z;
                              // U: z
17. }
```




- X is data dependent on Y iff
 - 1) There is a variable V that is defined at Y and used at X
 - There exists a path of nonzero length from Y to X along which V is not re-defined

```
1. float pow(int x, int y) // D: x, y
2.
3.
       int power;
       float z;
       if (y < 0)
                      // U: y
           power = -y;  // D: power
                                           U: y
7.
       else
                           // D: power
           power = y;
                                            U: y
9.
       z = 1.0;
                             // D: z
       while(power != 0) { // U: power
10.
                            // D: z
11.
           z = z \star x;
                                      U: x, z
12.
                            // D: power
           power--;
                                            U: power
13.
14.
       if (y < 0)
                             // U: y
15.
           z = 1/z;
                             // D: z
                                        U: z
16.
                              // U: z
       return z;
                                      DD(16) = ?
                  DD(16) = \{9\}
17. }
```




- X is data dependent on Y iff
 - 1) There is a variable V that is defined at Y and used at X
 - There exists a path of nonzero length from Y to X along which V is not re-defined

```
1. float pow(int x, int y) // D: x, y
3.
       int power;
       float z;
       if (y < 0)
                      // U: y
           power = -y;  // D: power
                                           U: y
7.
       else
                          // D: power
           power = y;
                                            U: y
9.
       z = 1.0;
                             // D: z
       while(power != 0) { // U: power
10.
                            // D: z
11.
           z = z \star x;
                                      U: x, z
12.
                            // D: power
           power--;
                                            U: power
13.
14.
       if (y < 0)
                             // U: y
           z = 1/z;
15.
                             // D: z
                                        U: z
16.
                             // U: z
       return z:
              DD(16) = \{9\}
                                  DD(16) = \{9, 11\}
17. }
```



- X is data dependent on Y iff
 - 1) There is a variable V that is defined at Y and used at X
 - There exists a path of nonzero length from Y to X along which V is not re-defined

```
1. float pow(int x, int y) // D: x, y
3.
       int power;
       float z;
       if (y < 0)
                      // U: y
          power = -y;  // D: power
                                           U: y
7.
       else
          power = y;  // D: power
                                            U: y
9.
       z = 1.0;
                             // D: z
       while(power != 0) { // U: power
10.
                            // D: z
11.
           z = z * x;
                                      U: x, z
12.
                            // D: power
                                            U: power
           power--;
13.
14.
       if (y < 0)
                             // U: y
15.
           z = 1/z;
                             // D: z
                                        U: z
                             // U: z
16.
       return z:
        DD(16) = \{9, 11\}
                            DD(16) = \{9, 11, 15\}
17. }
```



DU Chains on Binaries

- Def-Use chains link the definition of a data location and the use of the data location.
 - Registers or memory!

```
.text:00 pow
                       proc near
.text:00
.text:00 var ReturnVal = dword ptr -1Ch
                    = dword ptr -18h
= dword ptr -14h
.text:00 var Y
.text:00 var X
.text:00 var Z = dword ptr -8
.text:00 var Power = dword ptr -4
.text:00
.text:00 push
                               ; D: rsp, [rsp] U: rsp, rbp
              rbp
                rbp, rsp ; D: rbp U: rsp
.text:01 mov
              [rbp+var X], edi ; D: [rbp+var X] U: rbp, edi
.text:04 mov
               [rbp+var Y], esi; D: [rbp+var Y] U: rbp, esi
.text:07 mov
                [rbp+var Y], 0 ; D: rflags, U: rbp, [rbp+var Y]
.text: OA cmp
                short loc 1A ; D: U: rflags
.text: OE jns
                eax, [rbp+var Y]; D: eax U: rbp, [rbp+var Y]
.text:10 mov
                                ; D: eax U: eax
.text:13 neg
                eax
                [rbp+var Power], eax ; D: [rbp+var Power] U: rbp, eax
.text:15 mov
.text:18 jmp
                short loc 20 ; D: U:
```



Data Dep. Modelling on Binaries

- Be careful! Data dependence in terms of source lines is easy to see
 - Because our brains naturally follow the control flow!!
- · Consider:
 - The if statement (line 4) is dependent on the argument (line 1)
 - The x += 1 (line 7) is dependent on the initialization of x (line 3)
 - The return is dependent on both paths of the if statement (lines 5 and 7), since either are possible

```
1. int func(int y)
2. {
3.    int x = 1;
4.    if (y == 1):
5.         x = 2;
6.    else:
7.         x += 1;
8.    return x;
9. }
```



Data Dep. Modelling on Binaries with DU Chains

- Data Dep. must consider the CFG of the basic blocks traversed before the current block!
- For example: A linear parse of the DU Chain (not following the CFG) would incorrectly say:
 - The add esi, 1 is data dependent on mov esi, 2
 - The mov eax, esi is only data dependent on add esi, 1
- When computing data dep, you MUST follow the possible paths in the CFG!

```
1. int func(int y)
2. {
3.    int x = 1;
4.    if (y == 1):
5.         x = 2;
6.    else:
7.         x += 1;
8.    return x;
9. }
```

```
loc_start:
    ; stack setup
    mov esi, 1     ; D: esi
    test [ebp+arg_0], 1
    jne loc_skip
    mov esi, 2     ; D: esi
    jmp loc_end

loc_skip:
    add esi, 1    ; D: esi U: esi

loc_end:
    mov eax, esi ; D: eax U: esi
    ; clean up stack
    ret
```



Data Dep. Modelling on Binaries with DU Chains

1. mov esi, 1 ; D: esi Data Dep. must consider the CFG of 2. test [ebp+arg 0], 1 3. ine loc skip the basic blocks traversed before the $DD(4) = \{1\}$ current block! X is data dependent on Y iff 4. add esi, 1 ; D: esi U: esi 1) There is a variable V that is defined at Y 5. mov esi, 2 ; D: esi and used at X 6. jmp loc end 2) There exists a path of nonzero length from Y to X along which V is not re-defined 7. mov eax, esi ; D: eax U: esi 8. ret $\overline{DD(7)} = \{4, 5\}$ DD(7) = ?Georgia

Advanced Topics in Malware Analysis

Software Representation

Brendan Saltaformaggio, PhD

Assistant Professor

School of Electrical and Computer Engineering

Value Tracking



Keeping Pushes and Pops Straight!

Problem: Pushes and Pops Def and Use the same stuff!!

```
.text:00 push
                                    D: rsp, [rsp] U: rsp, rax
                                    D: rsp, [rsp] U: rsp, rbx
.text:01 push
.text:02 pop
                                                    U: rsp, [rsp]
                 rcx
                                                    U: rsp, rdx
.text:03 push
                 rdx
                                                     U: rsp, [rsp]
.text:04 pop
                 rsi
.text:05 pop
                 rdi
                                                     U: rsp, [rsp]
```

- Bigger Problem: Linear parse of the DU Chain (even following the CFG) will be incorrect
- **Solution:** Create a "Shadow Stack" --- A model stack which tracks who pushed what!



Keeping Pushes and Pops Straight!

Problem: Pushes and Pops Def and Use the same stuff!!

```
.text:00 push
                                                   U: rsp, rax
.text:01 push
                                                   U: rsp, rbx
                                                   U: rsp, [rsp]
.text:02 pop
                                 ; D: rsp, rcx
.text:03 push
                                ; D: rsp, [rsp] U: rsp, rdx
                rdx (
.text:04 pop
                                ; D: rsp, rsi
                                                 U: rsp, [rsp]
                rsi
.text:05 pop
                rdi
                                ; D: rsp, rdi
                                                   U: rsp, [rsp]
```

- Bigger Problem: Linear parse of the DU Chain (even following the CFG) will be incorrect
- Solution: Create a "Shadow Stack" --- A model stack which tracks who pushed what!

```
DD(.text:00) = { prior rax, rsp }
DD(.text:01) = { .text:00, prior rbx }
DD(.text:02) = { .text:01, .text:01 }
DD(.text:03) = { .text:02, prior rdx }
DD(.text:04) = { .text:03, .text:03 }
DD(.text:05) = { .text:04, .text:00 }
.text:03
.text:03
```



Computing Data Dependence is Hard in General

- Aliasing --- the kryptonite to the data dependence superhero!
 - Alias: A variable which can refer to multiple memory locations/objects

C loves aliases

```
int x, y,
z;
int * p;
x = 5;
y = 10;
z = 8;
p = &x;
p = p + z;
z = *p;
```

Assembly loves aliases

```
push rbp
mov rbp, rsp
push rdi
sub rsp, 16
...
cmp QWORD PTR [rbp], 0
...
mov rax, QWORD PTR
[rsp+24]
```

int c;
if (d == 0)
...
int a = d;
}

void func(int d) {

int b;


What is the value of z?

What is being moved into RAX?

The original code had no aliases!



Static Value Tracking



- Similar to Shadow Stack tracking, but now you track specific values of registers/memory
- You may have to assume "initial values" at function or program start
- As you step through the code, parse the instructions and update the tracked values
- When you need to know a value, hopefully you have tracked it!



Value Tracking

Advanced Topics in Malware Analysis

Software Representation

Brendan Saltaformaggio, PhD

Assistant Professor

School of Electrical and Computer Engineering

Program Dependence Graphs



Program Dependence Graph (PDG)

- The second most widely used program representation
- Represents the union of the two types of dependences
 - · Data dependence
 - · Control dependence
- Optional (but valuable) reading:
 - Ferrante, J., Ottenstein, K. J., & Warren, J. D. (1987). The program dependence graph and its use in optimization. *ACM Transactions on Programming Languages and Systems*, *9*(3), 319–349.
 - Horwitz, S., Reps, T., & Binkley, D. (1990). Interprocedural slicing using dependence graphs. *ACM Transactions on Programming Languages and Systems*, *12*(1), 26–60.



Program Dependence Graph

- A program dependence graph PDG = (N, Ed, Ec)
 - A finite set N of nodes which represents statements, possibly within basic blocks "super-nodes"

```
Start
```


```
1.1 int sum = 0;
1.2 int i = 1;
```

```
2.1 while ( i < n )
```

```
void sumUp(int n) {
   int sum = 0;
   int i = 1;
   while ( i < n ) {
      i = i + 1;
      sum = sum + i;
   }
   printf("%d", sum);
}</pre>
```

```
3.1 i = i + 1;
3.2 sum = sum + i;
```

```
4.1 printf("%d", sum);
```




Program Dependence Graph

- A program dependence graph PDG = (N, Ed, Ec)
 - A finite set N of nodes which represents statements, possibly within basic blocks "super-nodes"
 - A finite set Ed of edges (i, j) representing that node n_j is data dependent on node n_i
 - Recall: X is data dependent on Y iff


 (1) There exists a variable v that is defined at Y and used at X
 (2) There exists a path of nonzero length from Y to X along which v is not re-defined

```
void sumUp(int n) {
   int sum = 0;
   int i = 1;
   while ( i < n ) {
      i = i + 1;
      sum = sum + i;
   }
   printf("%d", sum);
}</pre>
```




Program Dependence Graph

- A program dependence graph PDG = (N, Ed, Ec)
 - A finite set N of nodes which represents statements, possibly within basic blocks "super-nodes"
 - A finite set Ed of edges (i, j) representing that node n_i is data dependent on node n_i
 - A finite set Ec of edges (i, j) representing that (super-) node n_i is control dependent on node n_i
 - Recall: Y is control-dependent on X iff X directly determines whether Y executes:
 - (1) **X** is not strictly post-dominated by **Y**
 - (2) There exists a path from **X** to **Y s.t.** every node in the path other than **X** and **Y** is post-dominated by **Y**
- Used to represent the set of all program statements involved in reaching any single execution point



Call Graph (CG)

- Simplest Case: Nodes represent functions; each edge represents a function invocation
- Used to perform higher-level Intraprocedural Analysis



```
void A() {
    B();
    C();
}

void C() {
    D();
    A();
}
```


```
void B() {
L1: D();
L2: D();
}
void D() {
}
```



Super Control Flow Graph (SCFG)

- Interprocedural control flow graph
 - Additional edges are added connecting each call site to the beginning of the procedure it calls
 - The return statement links back to the call site
- Rarely used in static analysis due to path explosion!
- Sometimes used in dynamic analysis due to ambiguity of function calls
 - JMP to some far away code? Fetch a return address and JMP to it?
 - JMP to a new function entry (no return address push) & then do a "double" return at RET?

```
1. for (i=0; i<n; i++) {
2.    t1= f(0);
3.    t2 = f(243);
4.    x[i] = t1 + t2;
5. }
6. int f (int v) {
7.    return (v+1);
8. }</pre>
```



Interprocedural Analysis

- Interprocedural analysis is a very deep rabbit hole!
- Excellent material:

Chong, S. (2010). Interprocedural Analysis. Harvard University School of Engineering and Applied Sciences (https://www.seas.harvard.edu/courses/cs252/2011sp/slides/Lec05-Interprocedural.pdf)

- Interprocedural analysis can provide VERY precise static analysis
- But path explosion makes global reasoning nearly impossible!
- For this class, we will selectively cover interprocedural analysis as it applies to dynamic analysis
- As we will see, dynamic analysis cannot reason locally (due to limited knowledge)
- Therefore, everything is global until we realize it is local! ☺



Lesson Summary

- Describe software representation
- Describe basic blocks of software
- Reconstruct control flow graph
- Describe various types of paths
- Utilize paths to observe dependencies

