```
This module specifies the southbound interface of \mu ONOS Config.
                              ——— Module Target —
Instance Naturals
 An empty constant
CONSTANT Nil
 The set of possible master nodes
CONSTANT Node
 The target state
Variable target
 A record of connections between nodes and the target
VARIABLE conns
This section specifies the behavior of configuration targets.
Start \triangleq
   \land \neg target.running
   \land target' = [target \ EXCEPT \ !.id]
                                                = target.id + 1,
                                    !.running = TRUE
   \land UNCHANGED \langle conns \rangle
Stop \triangleq
   \land target.running
   \land target' = [target \ EXCEPT \ !.running = FALSE,
                                     !. values = [p \in \{\} \mapsto [index \mapsto 0, value \mapsto Nil]]]
   \land conns' = [n \in Node \mapsto [conns[n] \text{ EXCEPT } !.connected = FALSE]]
This section specifies the behavior of connections to the target.
Connect(n) \triangleq
   \land \neg conns[n].connected
   \land target.running
   \wedge conns' = [conns \ EXCEPT \ ![n].id]
                                                      = conns[n].id + 1,
                                    ![n].connected = TRUE]
   \land UNCHANGED \langle target \rangle
Disconnect(n) \triangleq
   \land conns[n].connected
   \land conns' = [conns \ EXCEPT \ ![n].connected = FALSE]
```

\land UNCHANGED $\langle target \rangle$

```
TypeOK \triangleq \\ \land target.id \in Nat \\ \land \forall p \in \text{DOMAIN } target.values : \\ \land target.values[p].index \in Nat \\ \land target.values[p].value \in \text{STRING} \\ \land target.running \in \text{BOOLEAN} \\ \land \forall n \in \text{DOMAIN } conns : \\ \land n \in Node \\ \land conns[n].id \in Nat \\ \land conns[n].connected \in \text{BOOLEAN} \\ \end{cases}
```

Copyright 2023 Intel Corporation