```
— MODULE E2Node —
LOCAL INSTANCE Naturals
LOCAL INSTANCE Sequences
LOCAL INSTANCE FiniteSets
LOCAL INSTANCE TLC
 An empty value
CONSTANT Nil
 Node states
Constant Stopped, Started
 The E2 node identifier
Constant E2Node
 A set of RIC node identifiers
Constant RIC
ASSUME \land IsFiniteSet(RIC)
           \land \, \forall \, n \in RIC : n \in \mathsf{STRING}
 The state of the E2 node
VARIABLE state
 The state of the network
VARIABLE network
 The state of E2AP connections
VARIABLE conns
 Subscriptions
Variable subs
vars \; \stackrel{\Delta}{=} \; \langle state, \; network, \; conns, \; subs \rangle
LOCAL E2AP \triangleq \text{INSTANCE } E2AP \text{ WITH } conns \leftarrow network
StartNode \triangleq
    \land \, state = Stopped
    \land \mathit{state'} = \mathit{Started}
    \land UNCHANGED \langle network, conns, subs \rangle
```

 $StopNode \triangleq$

```
\land state = Started
           \land state' = Stopped
           \land UNCHANGED \langle network, conns, subs \rangle
SendE2SetupRequest(conn) \stackrel{\Delta}{=}
           \land UNCHANGED \langle conns, subs \rangle
HandleE2SetupResponse(conn, res) \triangleq
            \land E2AP! Client(E2Node)! Receive! E2SetupResponse(conn, res)
           \land UNCHANGED \langle conns, subs \rangle
 HandleRICSubscriptionRequest(conn, req) \triangleq
           \land E2AP!Client(E2Node)!Receive!RICSubscriptionRequest(conn, req)
           \land UNCHANGED \langle conns, subs \rangle
Handle RIC Subscription Delete Request(conn, req) \triangleq
            \land E2AP! Client(E2Node)! Receive! RICSubscriptionDeleteRequest(conn, req)
           \land UNCHANGED \langle conns, subs \rangle
 HandleRICControlRequest(conn, req) \stackrel{\Delta}{=}
           \land E2AP!Client(E2Node)!Receive!RICControlRequest(conn, req)
           \land E2AP!Client(E2Node)!Reply!RICControlAcknowledge(conn, [foo \mapsto "bar", bar \mapsto "baz"])
           \land UNCHANGED \langle conns, subs \rangle
HandleE2ConnectionUpdate(conn, req) \stackrel{\triangle}{=}
            \land E2AP! Client(E2Node)! Receive! E2ConnectionUpdate(conn, req)
           \land UNCHANGED \langle subs \rangle
 Handle E2Node Configuration Update Acknowledge (conn, res) \stackrel{\Delta}{=}
           \land \ E2AP! \ Client(E2Node)! \ Receive! \ E2Node Configuration Update Acknowledge (conn, \ res)
           \land UNCHANGED \langle subs \rangle
HandleRequest(c) \triangleq
            \land \lor E2AP!Client(E2Node)!Handle!RICSubscriptionRequest(c, HandleRICSubscriptionRequest)
                     \lor E2AP!Client(E2Node)!Handle!RICSubscriptionDeleteRequest(c, HandleRICSubscriptionDeleteRequest(c, HandleR
                     \vee E2AP! Client(E2Node)! Handle! RICControlRequest(c, HandleRICControlRequest)
                     \vee E2AP! Client(E2Node)! Handle! E2ConnectionUpdate(c, HandleE2ConnectionUpdate)
                     \vee E2AP!Client(E2Node)!Handle!E2NodeConfigurationUpdateAcknowledge(c, HandleE2NodeConfigurationUpdateAcknowledge(c, HandleE2NodeConfigurationUpdateAcknowledge(
           \land UNCHANGED \langle state \rangle
Init \triangleq
           \wedge E2AP! Init
```

^{*} Last modified Tue Sep 21 09:35:51 PDT 2021 by jordanhalterman

^{*} Created Tue Sep 21 02:14:57 PDT 2021 by jordanhalterman