A basic example of continuous adjoint method

Oscar Peredo

Computer Applications in Science & Engineering Department,
Barcelona Supercomputing Center

December, 2010



Original (forward) problem

Continuous method

Adjoint (backward) problem

Comparison with discrete approach

Flowchart

2/28

Very simple examples

Introducing a transient term

Original (forward) problem

Continuous method

Adjoint (backward) problem

Comparison with discrete approach

Flowchart

3/28

Very simple examples on a Introducing a transient term

Original (forward) problem

The basic example (2D) to be studied has the following state equations:

$$\Delta u(x,y) = \alpha^2, \quad (x,y) \in \Omega$$
 (1a)

$$\frac{\partial u}{\partial n}(x,y) = \beta^2, \quad (x,y) \in \Gamma_1$$
 (1b)

$$u(x,y) = \gamma^2, \quad (x,y) \in \Gamma_2$$
 (1c)

with $\alpha, \beta, \gamma \in \mathbb{R}$ and $\partial \Omega = \Gamma_1 \cup \Gamma_2$.

The design variables are α , β and γ , and the cost functional is:

$$J(u) := \frac{1}{2} \int_{\Gamma_1} (u(x, y) - \delta)^2 dS$$
 (2)

with $\delta \in \mathbb{R}$.

Original (forward) problem

The objetive of this tutorial is to minimize the cost functional subject to the state equations and using one design variable as a minimization parameter. In summary:

Supercomputing Center



Original (forward) problem

Continuous method

Adjoint (backward) problem

Comparison with discrete approach

Flowchart

6/28

Very simple examples
Introducing a transient term

Step 1: Differentiation of state equations

Differentiate the state equations (1) w.r.t. the design variable β :

$$D_{\beta}\Delta u(x,y) = D_{\beta}\alpha^{2}, \qquad (x,y) \in \Omega$$
 $D_{\beta}\frac{\partial u}{\partial n}(x,y) = D_{\beta}\beta^{2}, \qquad (x,y) \in \Gamma_{1}$
 $D_{\beta}u(x,y) = D_{\beta}\gamma^{2}, \qquad (x,y) \in \Gamma_{2}$

The resulting equations are (using the notation $\tilde{u} = D_{\beta}u$):

$$\Delta \tilde{u}(x,y) = 0, \quad (x,y) \in \Omega$$
 (5a)

$$\frac{\partial \tilde{u}}{\partial n}(x,y) = 2\beta, \quad (x,y) \in \Gamma_1$$
 (5b)
$$\tilde{u}(x,y) = 0, \quad (x,y) \in \Gamma_2$$
 (5c)

$$\tilde{u}(x,y) = 0, \quad (x,y) \in \Gamma_2$$
 (5c)



Step 2: Build $< L\tilde{u}, \psi >= 0$

8/28

Multitply by a test function ψ and integrate by parts (twice) the equation (5a):

$$\int_{\Omega} \psi \Delta \tilde{u} dV = 0$$

$$\int_{\partial \Omega} \psi \frac{\partial \tilde{u}}{\partial n} - \tilde{u} \frac{\partial \psi}{\partial n} dS + \int_{\Omega} \tilde{u} \Delta \psi dV = 0$$

$$\int_{\Gamma_{1}} \psi \frac{\partial \tilde{u}}{\partial n} - \tilde{u} \frac{\partial \psi}{\partial n} dS + \int_{\Gamma_{2}} \psi \frac{\partial \tilde{u}}{\partial n} - \tilde{u} \frac{\partial \psi}{\partial n} dS + \int_{\Omega} \tilde{u} \Delta \psi dV = 0$$

$$\int_{\Gamma_{1}} \psi 2\beta - \tilde{u} \frac{\partial \psi}{\partial n} dS + \int_{\Gamma_{2}} \psi \frac{\partial \tilde{u}}{\partial n} - 0 \frac{\partial \psi}{\partial n} dS + \int_{\Omega} \tilde{u} \Delta \psi dV = 0$$

$$\int_{\Gamma_{1}} \psi 2\beta - \tilde{u} \frac{\partial \psi}{\partial n} dS + \int_{\Gamma_{2}} \psi \frac{\partial \tilde{u}}{\partial n} dS + \int_{\Omega} \tilde{u} \Delta \psi dV = 0(6)$$

Step 3: Differentiate the cost functional

Differentiate the cost functional w.r.t. β :

$$D_{\beta}J(u) = \frac{1}{2}D_{\beta}\int_{\Gamma_{1}}(u-\delta)^{2}dS$$

$$= \frac{1}{2}\int_{\Gamma_{1}}2(u-\delta)D_{\beta}udS$$

$$= \int_{\Gamma_{1}}(u-\delta)\tilde{u}dS \qquad (7)$$

Barcelona Supercomputing Center

Centro Nacional de Supercomputación



Step 4: Couple equations

Couple the principal equations, adding (7)+(6):

$$D_{\beta}J(u) = D_{\beta}J(u) + (6)$$

$$= \int_{\Gamma_{1}} (u - \delta)\tilde{u}dS$$

$$+ \int_{\Gamma_{1}} \psi 2\beta - \tilde{u}\frac{\partial\psi}{\partial n}dS + \int_{\Gamma_{2}} \psi \frac{\partial\tilde{u}}{\partial n}dS + \int_{\Omega} \tilde{u}\Delta\psi dV$$

$$= \int_{\Gamma_{1}} \tilde{u}\left[(u - \delta) - \frac{\partial\psi}{\partial n}\right]dS + \int_{\Gamma_{2}} \psi \frac{\partial\tilde{u}}{\partial n}dS + \int_{\Omega} \tilde{u}\Delta\psi dV$$

$$+ \int_{\Gamma_{1}} \psi 2\beta dS$$
(8)

Centro Nacional de Supercomputació

Step 5: Impose constraints and build adjoint problem

Build the adjoint problem, setting the following constraints on equation (8):

$$\Delta \psi(x,y) = 0, \qquad (x,y) \in \Omega$$
 (9a)

$$\frac{\partial \psi}{\partial n}(x,y) = u(x,y) - \delta, (x,y) \in \Gamma_1$$
 (9b)
$$\psi(x,y) = 0, \qquad (x,y) \in \Gamma_2$$
 (9c)

$$\psi(x,y) = 0, \qquad (x,y) \in \Gamma_2$$
 (9c)

With this constraints, the differential of the cost function is as:

$$D_{\beta}J(u) = \int_{\Gamma_1} \psi 2\beta dS \tag{10}$$

with ψ solution of (9). This differential is used by a descent direction method to minimize the cost functional.

Original (forward) problem

Continuous method

Adjoint (backward) problem

Comparison with discrete approach

Flowchart

Very simple examples
Introducing a transient term

Adjoint (backward) problem

$$\Delta \psi(x,y) = 0,$$
 $(x,y) \in \Omega$ (11a)

$$\frac{\partial \psi}{\partial n}(x,y) = u(x,y) - \delta, (x,y) \in \Gamma_1$$
 (11b)

$$\psi(x,y) = 0, \qquad (x,y) \in \Gamma_2 \qquad (11c)$$

Barcelona Supercomputing Center

Centro Nacional de Supercomputación



Original (forward) problem

Continuous method

Adjoint (backward) problem

Comparison with discrete approach

Flowchart

14/28

Introducing a transient term puting

Center

Centro Nacional de Sur

Comparison with discrete approach

The derivatives obtained by both methods are:

Continuous:

$$D_{\beta}J(u) = \int_{\Gamma_1} \psi 2\beta dS \tag{12}$$

Discrete:

$$D_{\beta}J_{h}(u_{h}) = \int_{\Gamma_{1}} \sum_{i \in \Gamma_{1}^{h}} \psi(x_{i})\phi^{(i)}(x,y)2\beta dS$$
 (13)

The same result is obtained for both methods if the discretization used in the continuous one is the same as in the discrete one.

Original (forward) problem

Continuous method


Adjoint (backward) problem

Comparison with discrete approach

Flowchart

16/28

Introducing a transient term



Centro Nacional de Supercomputación

Original (forward) problem

Continuous method

Adjoint (backward) problem

Comparison with discrete approach


Flowchart

18/28

Very simple examples

Introducing a transient term puting


Example 1




The initial design variables are:

$$\alpha = 10$$
 $\beta = 32.75$ $\gamma = 0$ $\delta = 10$


Results: Evolution of *J*



Results: Evolution of ∇J




Example 2




The initial design variables are:

$$lpha=5 \qquad eta=35 \ \gamma=0 \qquad \delta=10$$

Results: Evolution of *J*



Results: Evolution of ∇J



Original (forward) problem

Continuous method

Adjoint (backward) problem

Comparison with discrete approach

Flowchart

25/28

Very simple examples

Introducing a transient term

Center

Transient term

If the state equations have a transient term, the problem can be formulated as follows:

$$\begin{array}{ll} \text{minimize} & \frac{1}{2} \int_0^T \int_{\Gamma_1} (u(x,y;t) - \delta)^2 dS dt \\ & \begin{cases} \partial_t u(x,y;t) + \Delta u(x,y;t) & = \alpha^2, \quad (x,y) \in \Omega, \\ & \quad t \in [0,T] \end{cases} \\ \text{subject to} & \begin{cases} \frac{\partial u}{\partial n}(x,y;t) & = \beta^2, \quad (x,y) \in \Gamma_1, \\ & \quad t \in [0,T] \end{cases} \\ & \quad u(x,y;t) & = \gamma^2, \quad (x,y) \in \Gamma_2, \\ & \quad t \in [0,T] \end{cases} \\ & \quad u(x,y;0) & = 0, \quad (x,y) \in \Omega \end{cases}$$

Transient term

The adjoint problem is:

$$\begin{aligned}
-\partial_t \psi(x, y; t) + \Delta \psi(x, y; t) &= 0, & (x, y) \in \Omega, t \in [0, T] \\
\frac{\partial \psi}{\partial n}(x, y; t) &= u(x, y; t) - \delta, (x, y) \in \Gamma_1, t \in [0, T] \\
\psi(x, y; t) &= 0, & (x, y) \in \Gamma_2, t \in [0, T] \\
\psi(x, y; T) &= 0, & (x, y) \in \Omega
\end{aligned}$$

In this case, we need to solve the adjoint equations with a **final** condition in t = T.



Thanks for your attention!

