# Paper Report — Unit Quaternion Description of Spatial Rotations in 3D cryoEM

**Group Meeting** 

Yu-Hsiang Lien

05 Oct 2021

#### Reference


Journal of Structural Biology 212 (2020) 107601



Contents lists available at ScienceDirect

#### Journal of Structural Biology

journal homepage: www.elsevier.com/locate/yjsbi



Review

#### Unit quaternion description of spatial rotations in 3D electron cryomicroscopy



Mingxu Hu<sup>a,b,c,1</sup>, Qi Zhang<sup>d,1</sup>, Jing Yang<sup>d,\*</sup>, Xueming Li<sup>a,b,c,e,\*</sup>

- Journal of Structural Biology 212 (2020) 107601
- DOI: <a href="https://doi.org/10.1016/j.jsb.2020.107601">https://doi.org/10.1016/j.jsb.2020.107601</a>

<sup>&</sup>lt;sup>a</sup> Key Laboratory of Protein Sciences (Tsinghua University), Ministry of Education, Beijing, China

<sup>&</sup>lt;sup>b</sup> School of Life Science, Tsinghua University, Beijing, China

<sup>&</sup>lt;sup>c</sup> Beijing Advanced Innovation Center for Structural Biology, China

<sup>&</sup>lt;sup>d</sup> Department of Mathematical Sciences, Tsinghua University, China

<sup>&</sup>lt;sup>e</sup> Beijing Frontier Research Center for Biological Structure, China

#### Outline

Background of the Quaternion and Unit Quaternion

Distance and Geodesic between Rotations by Unit Quaternion in cryoEM

Uniform and Quasi-Uniform Sampling in SO(3)

Statistics of Rotations in cryoEM

#### Description of Spatial Rotations

- To describe spatial rotations, three approaches widely used:
  - Rotation matrix
  - Euler angles
  - Unit quaternion

#### **Rotation Matrix**

- Most basic method
- Directly used to rotate a 3D vector/ object
- Required 9 parameters with non-linear constraints in a 3x3 matrix
  - → hard to estimate and optimize

#### **Euler Angles**

- Using three angle values to represent sequential rotations around three elemental axes
- Non-uniformity of rotation description
- Gimbal lock problem (in definition of intrinsic rotations)
- Multiple definitions and axis conventions

#### **Unit Quaternion**

- Used to perform basic rotations
- Generate uniform or quasiuniform sampling in rotation space
- Cooperate with model building

#### Background of the Quaternion and Unit Quaternion

- $\bullet$   $\overrightarrow{\mathbf{v}}$ : The 3D vector
- $\hat{\mathbf{v}} : \mathsf{The} \ \mathsf{unit} \ \mathsf{vector}$
- q: The quaternion in vector form a 4D vector
- R: The spatial rotation operator

- $\circ$  S<sup>3</sup>: All unit 4D vectors form a 3D hypersurface of the unit sphere in 4D space
- $\circ$  SO(3): The set containing all 3D spatial rotations

#### Definition of the Quaternion

- A quaternion is an extension of a complex number.
- ullet A quaternion  $old{q}$  is defined as a hypercomplex number composed of  $old{a}$  real part and three imaginary parts:

$$\mathbf{q} = q_0 + q_1 \mathbf{i} + q_2 \mathbf{j} + q_3 \mathbf{k} = \begin{pmatrix} q_0 \\ q_1 \\ q_2 \\ q_3 \end{pmatrix} = \begin{pmatrix} q_0 \\ \overrightarrow{\mathbf{n}}_{\mathbf{q}} \end{pmatrix}, \text{ where } \{\mathbf{i}, \mathbf{j}, \mathbf{k}\} \text{ are three imaginary units, } \overrightarrow{\mathbf{n}}_{\mathbf{q}} = \begin{pmatrix} q_1 \\ q_2 \\ q_3 \end{pmatrix}$$

• The conjugate of a quaternion:


$$\mathbf{q}^* = q_0 - q_1 \mathbf{i} - q_2 \mathbf{j} - q_3 \mathbf{k} = \begin{pmatrix} q_0 \\ -q_1 \\ -q_2 \\ -q_3 \end{pmatrix} = \begin{pmatrix} q_0 \\ -\overrightarrow{\mathbf{n}}_{\mathbf{q}} \end{pmatrix}$$

$$|\mathbf{q}| := \sqrt{\mathbf{q} \cdot \mathbf{q}^*} = \sqrt{q_0^2 + q_1^2 + q_2^2 + q_3^2} = \sqrt{q_0^2 + \mathbf{n}_{\mathbf{q}} \cdot \mathbf{n}_{\mathbf{q}}}$$

#### Basic Properties of the Quaternion

- $\bullet$  The multiplication of two quaternions ( $\otimes$ : the quaternion product):
  - $1 \otimes 1 = 1$
  - $1 \otimes \mathbf{i} = \mathbf{i} \otimes 1 = \mathbf{i}$
  - $1 \otimes \mathbf{j} = \mathbf{j} \otimes 1 = \mathbf{j}$
  - $1 \otimes \mathbf{k} = \mathbf{k} \otimes 1 = \mathbf{k}$

- $\mathbf{i}^2 = \mathbf{j}^2 = \mathbf{k}^2 = -1$
- $i \otimes j = k , \quad j \otimes k = i, \quad k \otimes i = j$
- $\mathbf{j} \otimes \mathbf{i} = -\mathbf{k}$ ,  $\mathbf{k} \otimes \mathbf{j} = -\mathbf{i}$ ,  $\mathbf{i} \otimes \mathbf{k} = -\mathbf{j}$



• The result of quaternion multiplication can also be written in vector form as:

From https://zh.wikipedia.org/wiki/四元數

$$\mathbf{q} \otimes \mathbf{q}' = \begin{pmatrix} q_0 \\ q_1 \\ q_2 \\ q_3 \end{pmatrix} \otimes \begin{pmatrix} q'_0 \\ q'_1 \\ q'_2 \\ q'_3 \end{pmatrix} = \begin{pmatrix} q_0 q'_0 - q_1 q'_1 - q_2 q'_2 - q_3 q'_3 \\ q_0 q'_1 + q_1 q'_0 + q_2 q'_3 - q_3 q'_2 \\ q_0 q'_2 - q_1 q'_3 + q_2 q'_0 + q_3 q'_1 \\ q_0 q'_3 + q_1 q'_2 - q_2 q'_1 + q_3 q'_0 \end{pmatrix} = \begin{pmatrix} q_0 \\ \overrightarrow{\mathbf{n}}_{\mathbf{q}} \end{pmatrix} \otimes \begin{pmatrix} q'_0 \\ \overrightarrow{\mathbf{n}}_{\mathbf{q}'} \end{pmatrix} = \begin{pmatrix} q_0 q'_0 - \overrightarrow{\mathbf{n}}_{\mathbf{q}} \cdot \overrightarrow{\mathbf{n}}_{\mathbf{q}'} \\ q_0 \overrightarrow{\mathbf{n}}_{\mathbf{q}'} + q'_0 \overrightarrow{\mathbf{n}}_{\mathbf{q}} + \overrightarrow{\mathbf{n}}_{\mathbf{q}} \times \overrightarrow{\mathbf{n}}_{\mathbf{q}'} \end{pmatrix}$$

$$\mathbf{Complex form} \qquad \mathbf{Vector form}$$

• The complex form and vector form of quaternion multiplication are equivalent.

### Basic Quaternion Algebra Property

- The properties of quaternions are similar to complex numbers, except that the multiplication of quaternions is **not** commutative:  $q_1 \otimes q_2 \neq q_2 \otimes q_1$ .
- The conjugation, norm, and multiplication of quaternions satisfies the following properties:
  - $(\mathbf{q}^*)^* = \mathbf{q}$
  - $(\mathbf{q}_1 \otimes \mathbf{q}_2)^* = \mathbf{q}_2^* \otimes \mathbf{q}_1^*$
  - $|\mathbf{q}| = |\mathbf{q}^*|$
  - $|\mathbf{q}_1 \otimes \mathbf{q}_2| = |\mathbf{q}_1| \cdot |\mathbf{q}_2|$
  - Multiplication is associative:  $(q_1 \otimes q_2) \otimes q_3 = q_1 \otimes (q_2 \otimes q_3)$
  - ▶ 1 is the multiplicative identity:  $1 \otimes \mathbf{q} = \mathbf{q} \otimes 1 = \mathbf{q}$

#### Unit Quaternion Description of 3D Spatial Rotation

- If norm equals to 1 :  $|\mathbf{q}| = 1$  —> Unit quaternion
- A unit quaternion can be used to perform 3D rotation.
- The rotation of a 3D vector  $\vec{\mathbf{v}}$  to another vector  $\vec{\mathbf{v}}'$  is performed using a  $3 \times 3$  orthogonal matrix M with a determinant of 1:

$$\overrightarrow{\mathbf{v}}' = \mathbf{M}\overrightarrow{\mathbf{v}}$$

• This operation can also be achieved by performing unit quaternion multiplication:

$$\mathbf{v}' = \begin{pmatrix} 0 \\ \overrightarrow{\mathbf{v}}' \end{pmatrix} = \mathbf{q} \otimes \begin{pmatrix} 0 \\ \overrightarrow{\mathbf{v}} \end{pmatrix} \otimes \mathbf{q}^* \equiv R_{\mathbf{q}}(\overrightarrow{\mathbf{v}})$$

• Because a pair of unit quaternion is involved in the multiplication,  $\mathbf{q}$  and  $-\mathbf{q}$  will yield same rotations:  $R_{\mathbf{q}} = R_{-\mathbf{q}}$ 


#### Unit Quaternion Description of 3D Spatial Rotation

A unit quaternion q can be written in the form:

$$\mathbf{q} = \begin{pmatrix} \cos\frac{\phi}{2} \\ \hat{\mathbf{n}}_{\mathbf{q}}\sin\frac{\phi}{2} \end{pmatrix} \implies \text{a rotation about the axis } \hat{\mathbf{n}}_{\mathbf{q}} \text{ by the angle } \phi.$$

 $\bullet$  For sequential rotation, e.g.  $R_{\mathbf{q}_1}$  followed by  $R_{\mathbf{q}_2}$ , is equivalent to  $R_{\mathbf{q}_2 \otimes \mathbf{q}_1}$ :

$$R_{\mathbf{q}_2}(R_{\mathbf{q}_1}(\overrightarrow{\mathbf{v}})) = \mathbf{q}_2 \otimes \left(\mathbf{q}_1 \otimes \begin{pmatrix} 0 \\ \overrightarrow{\mathbf{v}} \end{pmatrix} \otimes \mathbf{q}_1^* \right) \otimes \mathbf{q}_2^* = (\mathbf{q}_2 \otimes \mathbf{q}_1) \otimes \begin{pmatrix} 0 \\ \overrightarrow{\mathbf{v}} \end{pmatrix} \otimes (\mathbf{q}_2 \otimes \mathbf{q}_1)^* = R_{\mathbf{q}_2 \otimes \mathbf{q}_1}(\overrightarrow{\mathbf{v}})$$




- The dot and cross products of vectors are preserved under spatial rotations.
- The conversions between three rotation descriptions (rotation matrix, Euler angles, unit quaternion) are wellestablished.

# Swing-Twist Decomposition

- Using a directional vector to represent the orientation of a 3D object, the 3D rotation of this object can be decomposed into the product of two rotations:
  - Swing: change the directional vector to another direction.
  - **Twist**: twist about the directional vector.
    - Useful for rotation analysis and the application of constraints to rotations.

- $\bullet$  Consider a 2D experimental image in single particle cryoEM that is rotated using unit quaternion  ${\bf q}$  to match the projection of a 3D object.
- Assume the experimental image initially lies in the *XY*-plane with norm vector  $\vec{\mathbf{v}}_n = (0, 0, 1)^T$ , the rotation can be perform in two steps:



From this paper

# Swing-Twist Decomposition — Swing

• The image is rotated so that its norm vector  $\vec{\mathbf{v}}_n$  is changed to be along the projection direction  $\vec{\mathbf{v}}_p$ .


$$\begin{pmatrix} 0 \\ \overrightarrow{\mathbf{v}}_p \end{pmatrix} = \mathbf{q} \otimes \begin{pmatrix} 0 \\ \overrightarrow{\mathbf{v}}_n \end{pmatrix} \otimes \mathbf{q}^*$$

The swing rotating  $\vec{\mathbf{v}}_n$  to  $\vec{\mathbf{v}}_p$  can be obtained by a rotation about the axis  $\hat{\mathbf{v}}_r$  for the angle  $\psi_s$ :

$$\hat{\mathbf{v}}_r = \frac{\overrightarrow{\mathbf{v}}_n \times \overrightarrow{\mathbf{v}}_p}{|\overrightarrow{\mathbf{v}}_n||\overrightarrow{\mathbf{v}}_p|} , \quad \psi_s = \cos^{-1} \frac{\overrightarrow{\mathbf{v}}_n \cdot \overrightarrow{\mathbf{v}}_p}{|\overrightarrow{\mathbf{v}}_n||\overrightarrow{\mathbf{v}}_p|}$$
Swing angle

The swing quaternion is:

$$\mathbf{q}_{s} = \begin{pmatrix} \cos \frac{\psi_{s}}{2} \\ \hat{\mathbf{v}}_{r} \sin \frac{\psi_{s}}{2} \end{pmatrix}$$




# Swing-Twist Decomposition — Twist

- The image is in-plane rotated about its norm vector  $\overrightarrow{\mathbf{v}}_p$  for angle  $\psi_t$  to match the projection of the object.
- The twist quaternion is:

$$\mathbf{q}_t = \begin{pmatrix} \cos \frac{\psi_t}{2} \\ \overrightarrow{\mathbf{v}}_p \sin \frac{\psi_t}{2} \end{pmatrix}$$

- From the definition of swing-twist decomposition:  $\mathbf{q} = \mathbf{q}_t \otimes \mathbf{q}_s$ 
  - Swing-before-twist form
  - The twist quaternion can be calculated:  $\mathbf{q}_t = \mathbf{q} \otimes \mathbf{q}_s^*$ .
  - The twist angle  $\psi_t$  can be calculated.



From this paper

#### Distance and Geodesic between Rotations

 In cryoEM, it is important to examine the differences between rotation parameters. But there are no quantitative measure for such differences in cryoEM.

 This paper used the concept of distance between two rotations based on the unit quaternion system as a quantitative measure.

The definition of the distance and corresponding geodesic based on the unit quaternion has shown its advantages
as a general mathematical tool for angular analysis and rotational operations.

#### Distance between Rotation

• The angle between two 3D unit vectors  $\vec{\mathbf{v}}_1$  and  $\vec{\mathbf{v}}_2$  can be defined using the distance between them:

$$d_{S^2}(\overrightarrow{\mathbf{v}}_1, \overrightarrow{\mathbf{v}}_2) := \cos^{-1}(\overrightarrow{\mathbf{v}}_1 \cdot \overrightarrow{\mathbf{v}}_2)$$
, ranges  $[0, \pi]$ 

- Using the angle value as the distance is straightforward for orientation analysis, but the unit quaternion presents a rotation alternate to a 3D vector → distance between two rotations is not explicit.
- There are several definitions of the distance between rotations in SO(3), the definition of distance between two rotations in SO(3),  $R_{q_1}$  and  $R_{q_2}$ , in this paper is:

$$d_{SO(3)}(R_{\mathbf{q}_1}, R_{\mathbf{q}_2}) := \max_{\overrightarrow{\mathbf{v}} \in S^2} d_{S^2} \left( R_{\mathbf{q}_1}(\overrightarrow{\mathbf{v}}), R_{\mathbf{q}_2}(\overrightarrow{\mathbf{v}}) \right)$$

- the maximum distance between two 3D vectors,  $R_{\mathbf{q}_1}$  and  $R_{\mathbf{q}_2}$
- The distance can be calculated as:

$$d_{SO(3)}(R_{\mathbf{q}_1}, R_{\mathbf{q}_2}) = 2\cos^{-1}(|\mathbf{q}_1 \cdot \mathbf{q}_2|) = 2\cos^{-1}\left(1 - \frac{|\mathbf{q}_1 \cdot \mathbf{q}_2|^2}{2}\right)$$

#### Distance between Rotation

- From the definition of the distance,  $\cos^{-1}(|\mathbf{q}_1 \cdot \mathbf{q}_2|)$  is the shortest arc between  $\mathbf{q}_1$  and  $\mathbf{q}_2$  on the surface of sphere  $S^3$ .
- The absolute value in the calculation of  $|\mathbf{q}_1 \cdot \mathbf{q}_2|$  indicates that  $\mathbf{q}$  and  $-\mathbf{q}$  represent the same rotation and will yield the same distance.
- The distance provides an estimate of the possible maximal changes of projection directions from different rotations by:

$$d_{SO(3)}\left(R_{\mathbf{q}_1}, R_{\mathbf{q}_2}\right) \ge d_{S^2}\left(\overrightarrow{\mathbf{v}}_{p_{\mathbf{q}_1}}, \overrightarrow{\mathbf{v}}_{p_{\mathbf{q}_2}}\right)$$

- $\overrightarrow{\mathbf{v}}_{p_{\mathbf{q}_1}}$  and  $\overrightarrow{\mathbf{v}}_{p_{\mathbf{q}_2}}$  are the projection directions from rotations  $R_{\mathbf{q}_1}$  and  $R_{\mathbf{q}_2}$ , respectively.
- Measuring the distance of rotations between different rounds yields direct information on the convergence of 3D alignment.

#### Geodesic between Rotations

- In geometry, the geodesic is a curve or line indicating the shortest path between two points on a surface.
- o Introduce the geodesic between two rotations,  $R_{\mathbf{q}_1}$  and  $R_{\mathbf{q}_2}$ , can be used for the interpolation between two rotations.
- The geodesic between  $R_{\mathbf{q}_1}$  and  $R_{\mathbf{q}_2}$  can be described by:

$$f_l\left(R_{\mathbf{q}_1},R_{\mathbf{q}_2},t\right)$$
 , with the affine parameter  $t\in[0,\,1].$ 

The value of  $f_l\left(R_{\mathbf{q}_1},R_{\mathbf{q}_2},t\right)$  is also a unit quaternion representing the rotation  $\rightarrow$  this function describes the relation distance from  $R_{\mathbf{q}_1}$ :


$$t = \frac{d_{SO(3)}\left(R_{\mathbf{q}_1}, f_l\left(R_{\mathbf{q}_1}, R_{\mathbf{q}_2}, t\right)\right)}{d_{SO(3)}\left(R_{\mathbf{q}_1}, R_{\mathbf{q}_2}\right)} \Rightarrow \begin{cases} f_l\left(R_{\mathbf{q}_1}, R_{\mathbf{q}_2}, 0\right) = \mathbf{q}_1 \\ f_l\left(R_{\mathbf{q}_1}, R_{\mathbf{q}_2}, 1\right) = \mathbf{q}_2 \end{cases}$$

#### Geodesic between Rotations

From the geometry of the geodesic, the analytical formula of the geodesic function can be derived as:

$$f_l\left(R_{\mathbf{q}_1},R_{\mathbf{q}_2},t\right) = \begin{cases} \frac{1}{\sin\phi}\left[\sin\left(\phi(1-t)\right)\mathbf{q}_1 + \sin\left(\phi t\right)\mathbf{q}_2\right] &, \text{ if } \mathbf{q}_1 \cdot \mathbf{q}_2 \ge 0\\ \frac{1}{\sin(\pi-\phi)}\left[\sin\left((\pi-\phi)(1-t)\right)\mathbf{q}_1 + \sin\left((\pi-\phi)t\right)\mathbf{q}_2\right] &, \text{ if } \mathbf{q}_1 \cdot \mathbf{q}_2 < 0 \end{cases}$$

- The formula can be used to calculate interpolations between two rotations.
- The linear interpolation of Euler angles does not yield "linear" changes in the rotations.
- It is significantly difficult to define a geodesic in the Euler angle system.



affine parameter

#### Uniform and Quasi-Uniform Sampling in SO(3)

 Uniform and quasi-uniform sampling in entire rotational space is frequently used in cryoEM alignment to search for the global optimal solutions of molecular orientations.

- The methods used in uniform and quasi-uniform sampling are in two categories:
  - Sampling points are drawn independently from a uniform distribution.
  - Based on a quasi-regular grid generated in the rotational space, sampling is performed by sampling at grid points,
     where the sampling point are not independent.

# Sampling with Uniform Distribution

- Two methods have been predominantly used:
  - ▶ **Method 1**: By drawing three random numbers s,  $\theta_1$  and  $\theta_2$ , the uniformly unit quaternions  $\mathbf{q}$  in  $S^3$  can be performed.

$$\begin{array}{c} s \sim U[0, 1] \\ \theta_1 \sim U[0, 2\pi] \Rightarrow \\ \theta_2 \sim U[0, 2\pi] \end{array} \Rightarrow \mathbf{q} = \begin{pmatrix} \sqrt{s} \cos \theta_2 \\ \sqrt{1 - s} \sin \theta_1 \\ \sqrt{1 - s} \cos \theta_1 \\ \sqrt{s} \sin \theta_2 \end{pmatrix} \sim U_{S^3}$$

Method 2: Uses a 4D Gaussian distribution  $N_4(\mathbf{0}, \mathbf{I})$  with a mean of zero and covariance matrix of a 4 × 4 identity matrix  $\mathbf{I}$  to sample a series of 4D vectors  $\mathbf{v}$ . By normalizing these vectors to have norm 1, the uniformly unit quaternions  $\mathbf{q}$  in  $S^3$  can be performed.

$$\mathbf{v} \sim N_4(\mathbf{0}, \mathbf{I}) \Rightarrow \mathbf{q} = \frac{\mathbf{v}}{|\mathbf{v}|} \sim U_{S^3}$$


In both methods, the corresponding rotation  $R_{\bf q}$  follows a uniform distribution in SO(3).

#### Test of Sampling with Uniform Distribution

• It's also possible to apply further selection from uniformly distributed rotations to obtain rotations in a restricted angle range  $[-\phi_0, \phi_0]$ .

$$\mathbf{q} = \begin{pmatrix} \cos\frac{\phi}{2} \\ \hat{\mathbf{n}}_{\mathbf{q}}\sin\frac{\phi}{2} \end{pmatrix}, \text{ with } \left| \cos\frac{\phi}{2} \right| \ge \cos\frac{\phi_0}{2}$$

- Selecting unit quaternions in projection directions follow uniform distributions in given angle range about the projection axis.
- In-plane rotational angles concentrate around 0°.




05 Oct 2021 Yu-Hsiang Lien 21 / 29

# Sampling by Quasi-Regular Grid

Two methods were used:

K. M. Gorski et al., The Astrophysical Journal, 2005 ApJ 622 759.

- Method 1: Base on 4D platonic solid. Apexes of a 4D platonic solid form a quasi-regular grid on  $S^3$  are used to generate sampling grid.
- Method 2: Use Euler angles to represent rotations (widely adopted in several cryoEM software). Involve three steps:
  - ightharpoonup Quasi-regular grid is generated on  $S^2$ , presenting the space of projection directions, by either scaled Euler angle method or HEALPix method.
  - Sampling with equal spacing on a unit circle and representing the space of in-plane rotations is performed.
  - → Cartesian products between projection samplings and inplane rotation samplings are calculated to obtain a set of quasi-regular grid sampling on *SO*(3).



Scaled Euler angle method **HEALPix** method

In comparison, the unit quaternion based methods shows significant advantages in generating uniform samplings

→ computationally simple + sampling points are independent of each other.

#### Statistics of Rotations in CryoEM

Sampling and randomization in the rotational space is crucial for 3D reconstruction to prevent the so-called local optimization problem.

- Two types of requests for random sampling:
  - Generate samples in rotational space with a specific statistical distribution.
  - Estimate the statistical properties for a series of given rotation parameters. (Directional statistics)

- Statistical methods based on the unit quaternion is introduced in the following:
  - Calculate the average of rotations.
  - Angular Central Gaussian (ACG) Distribution.
  - Customized application of ACG distribution.

### Average Rotations

The geometric mean is defined as the average of a given set of rotations  $\{R_{\mathbf{q}_i}\}_{1 \le i \le N}$  with corresponding weights  $\{w_i\}_{1 \le i \le N}$  for each rotation:

$$\arg\min_{R_{\mathbf{q}} \in SO(3)} \sum_{i=1}^{N} w_i d_{SO(3)}^2 (R_{\mathbf{q}}, R_{\mathbf{q}_i})$$

- The geometric mean can be approximated by the projection arithmetic mean.
- A solution based on unit quaternion known as the normalized principal eigenvector of the matrix:

$$\mathbf{T} = \sum_{i=1}^{N} w_i \mathbf{q}_i \mathbf{q}_i^T$$

 Eigenvalues and eigenvectors can be determined using linear algebra techniques. Since only the principal eigenvector is required, use an iterative formula to approximate the principal eigenvector:

$$ar{\mathbf{q}} \leftarrow rac{\mathbf{T}ar{\mathbf{q}}}{|\mathbf{T}ar{\mathbf{q}}|}$$

#### Statistics Obtained Using ACG Distribution

- In local search of cryoEM 3D alignment:
  - Expect to perform intensive searches around a given rotation (orientation) with high probability.
  - If the distance from the given rotation increases, the probability of determining the accurate solution is decreased.
  - Sampling with a Gaussian distribution is used.

- The rotational space is not a linear space → Gaussian distribution with a requirement of linear space.
- The ACG distribution provides a solution in rotational space with features similar to that of a Gaussian distribution.
- The ACG distribution is a useful tool in rota-tional space to generate or analyze samples with a maximal central distribution.

#### Definition of ACG Distribution

Tyler, David E., 1987. Biometrika 74 (3), 579–589.

• Similar to the uniform distribution, the generation and normalization of 4D vectors  $\mathbf{v}$  from Gaussian distribution  $N_4(\mathbf{0}, \mathbf{A})$  with zero mean and covariance matrix  $\mathbf{A}$  leads to unit quaternions  $\mathbf{q}$ , follows the ACG distribution:

$$\mathbf{x} \sim N_4(\mathbf{0}, \mathbf{A}) \Rightarrow \mathbf{q} = \frac{\mathbf{v}}{|\mathbf{v}|} \sim ACG(\mathbf{A})$$


• The probability density function of the ACG distribution is:

$$p(\mathbf{q}; \mathbf{A}) = |\mathbf{A}|^{-\frac{1}{2}} (\mathbf{q}^T \mathbf{A}^{-1} \mathbf{q})^{-2}$$

- Reach maximum if  $\mathbf{q}$  equals the principal eigenvector of the covariance matrix  $\mathbf{A}$ .
- $\bullet$  An iterative formula is usually used to approximate **A**:

$$\mathbf{A}^{(k+1)} = 4 \left\{ \sum_{i=1}^{N} \frac{1}{\mathbf{q}_i^T \mathbf{A}^{(k)^{-1}} \mathbf{q}_i} \right\}^{-1} \left\{ \sum_{i=1}^{N} \frac{\mathbf{q}_i \mathbf{q}_i^T}{\mathbf{q}_i^T \mathbf{A}^{(k)^{-1}} \mathbf{q}_i} \right\}$$

From this paper



 $\mathbf{A} = \text{diag}(20^2, 1, 1, 1)$   $\mathbf{A} = \text{diag}(100^2, 1, 1, 1)$ 


#### Local Perturbation and Confidence Area

- Use a special form of covariance matrix to generate a set of rotations  $\{R_{\mathbf{q}_i}\}_{1 \leq i \leq N}$  that can be conveniently correlated with the angular accuracy of local search in cryoEM.
- A special covariance matrix is selected with k > 1:

$$\mathbf{A} = \begin{pmatrix} k^2 & & \\ & 1 & \\ & & 1 \\ & & 1 \end{pmatrix}$$

- The principal eigenvector of  $\bf A$  is along  ${\bf q_e}=(1,\,0,\,0,\,0)^T$ ,  $R_{\bf q_e}$  is a still rotate (no rotation).
- For the local search in cryoEM 3D alignment, the range of perturbations is directly correlated to the angular accuracy of orientation search.
- The probability density of the resulting unit vector  $\overrightarrow{\mathbf{v}}$  from rotating an arbitrary unit vector  $\overrightarrow{\mathbf{v}}_0$  by  $\mathbf{q} \sim ACG(\mathbf{A})$ :

$$p\left(\overrightarrow{\mathbf{v}}; \overrightarrow{\mathbf{v}_0}, A\right) = \frac{1}{2\sqrt{2}k} \frac{\left(\frac{1}{k^2} - 1\right)z + \left(\frac{1}{k^2} + 3\right)}{\left[\left(\frac{1}{k^2} - 1\right)z + \left(\frac{1}{k^2} + 1\right)\right]^{\frac{3}{2}}} \quad \text{, where } z = \overrightarrow{\mathbf{v}} \cdot \overrightarrow{\mathbf{v}_0} \in [-1, 1]$$



#### Local Perturbation and Confidence Area

• Introduce the concept of confidence area [ $z_0$ , 1] under a confidence level a that satisfies:


$$\int_{\{\overrightarrow{\mathbf{v}}|\overrightarrow{\mathbf{v}}\cdot\overrightarrow{\mathbf{v}}_{\mathbf{0}}\in[\mathbf{z_0},\,\mathbf{1}]\}} p\left(\overrightarrow{\mathbf{v}};\overrightarrow{\mathbf{v}}_{\mathbf{0}},\,\mathbf{A}\right) d\overrightarrow{\mathbf{v}} = a$$

- The confidence level can be considered as the percentage of samples fallen in a range with angle distance up to  $\cos^{-1}(z_0)$ 
  - Define  $e = \cos^{-1}(z_0)$  as the angular precision of rotation sampling under a given confidence level a.

$$z_0 = \frac{(z_0')^2 - \left(\frac{1}{k^2} + 1\right)}{\frac{1}{k^2} - 1}, \quad z_0' = \frac{a' + \sqrt{(a')^2 + 8}}{2}, \quad a' = \frac{\sqrt{2}(1 - k^2)(1 - a)}{k}$$

- $\longrightarrow$  calculate  $z_0$  with given k and a.
- ullet An approximation formula to calculate angular precision  $\epsilon$  from k and a:

$$\frac{1}{\epsilon} = \frac{1 - a}{2\sqrt{2a - a^2}}k \quad \Rightarrow \text{ the asymptote of } \frac{1}{\epsilon} \text{ if } k \to \infty.$$



#### Summary

- Unit quaternion systems have been shown as convenient and mathematically rigorous tools to manage and analyze the orientations of molecules or their projections.
- A disadvantage of the unit quaternion is its not intuitive compared to the Euler angles in representing the in-plane rotation and 3D orientation change → addressed by the swing-twist decomposition.
- The rotation operations represented by unit quaternions are correlated with the 4D vector in the  $S^3$  sphere in 4D space  $\rightarrow$  the properties of rotation can be directly derived/converted to the analysis of the 4D unit vectors.
- With distance and geodesic being well defined, statistics tools are established for 3D cryoEM image processing:
  - The definition of distance enables direct comparison of rotations, useful in the diagnosis of orientation stability of particles in 3D alignment.
  - The definition of geodesic enables interpolation and analysis for continuous changes of rotations that can be used in the analysis of flexible samples.
- Uniform and ACG distribution were developed from the 4D Gaussian distribution of 4D vectors → powerful tools of sampling/inference of global/local optimization of molecule orientations.

#### Back Up

#### Converting Euler Angles to Unit Quaternion

• The rotation by Euler angles  $\phi$ ,  $\theta$ , and  $\psi$  in ZYZ convention presented by corresponding unit quaternion is:

$$\mathbf{q}_{\phi\theta\psi} = \mathbf{q}_{\psi} \otimes \mathbf{q}_{\theta} \otimes \mathbf{q}_{\phi} \; ; \; \mathbf{q}_{\phi} = \begin{pmatrix} \cos\frac{\phi}{2} \\ 0 \\ 0 \\ \sin\frac{\phi}{2} \end{pmatrix}, \; \mathbf{q}_{\theta} = \begin{pmatrix} \cos\frac{\theta}{2} \\ 0 \\ \sin\frac{\theta}{2} \\ 0 \end{pmatrix}, \; \mathbf{q}_{\psi} = \begin{pmatrix} \cos\frac{\psi}{2} \\ 0 \\ 0 \\ \sin\frac{\psi}{2} \end{pmatrix}$$

#### Proof of Well-definiteness of Distance between Two Rotations

- 1. Symmetry property
- 2. Positive definiteness property
- 3. Triangle inequality property

05 Oct 2021 Yu-Hsiang Lien 32 / 29

#### Inference based on ACG Distribution

• An iterative method to determine the maximum-likelihood approximation of k from  $\{\bar{\mathbf{q}}^{-1}\otimes\mathbf{q}_i\}_{1\leq i\leq N}$ :

$$k^{2} = \frac{4}{N} \sum_{i=1}^{N} \frac{q_{0i}^{2}}{k^{-2}q_{0i}^{2} + \overrightarrow{\mathbf{n}}_{\mathbf{q}_{i}} \cdot \overrightarrow{\mathbf{n}}_{\mathbf{q}_{i}}} , \text{ where } \left(\frac{q_{0i}}{\overrightarrow{\mathbf{n}}_{\mathbf{q}_{i}}}\right) = \overline{\mathbf{q}}^{-1} \otimes \mathbf{q}_{i}$$

- A method to estimate the angular precision of the parameter search from a series of samples generated by the particle-filter algorithm in THUNDER.
- Performed the ab initio 3D reconstruction of a dataset of the proteasome (EMPIAR-10025) using 112,412 particles.

#### From this paper

