CatMove Page 1

CatMove Trans

Transfer file or directory to another directory on the same volume

#include < Files.h >

File Manager (PBxxx)

OSErr CatMove(vRefNum, dirID, oldName, newDirID, newName);

short vRefNum; volume, drive or working directory

long DirlD; ID of source directory

Str255 oldName; address of source directory name

long newDirlD; ID of destination directory

Str255 newName; address of destination directory name

returns Error Code; 0=no error

CatMove moves the directory entry of a file or directory into a different directory on the same volume. File contents are not transferred; this is strictly a directory-modification operation. It is similar to the **PBCatMove** routine, but it takes a vRefNum, dirID's and filenames instead of a complicated **CMovePBRec** structure.

Returns: an operating system Error Code. It will be one of:

noErr (0) No error

badMovErr (-122) Can't move into offspring

bdNamErr (-37) Bad file name or attempt to move into file

dupFNErr (-48) Duplicate filename (destination file/dir already exists)

fnfErr (-43) Source file not found

ioErr (-36) I/O error
nsvErr (-35) No such volume
paramErr (-50) No default volume
vLckdErr (-46) Volume is locked

wPrErr (-44) Diskette is write-protected

Notes: The file or directory specified by ioNamePtr, ioVRefNum, and ioDirID (in various combinations), is transferred to the directory identified by ioNewName and/or ioNewDirID.

CatMove cannot transfer between different disks (volumes) nor can it rename an item - use **PBHRename** for that.