ReadDateTime Page 1

ReadDateTime Copy clock-chip time to Time variable

#include <<u>OSUtils.h</u>>

Operating System Utilities

OSErr ReadDateTime(secs);

long *secs; receives number of seconds since 01/01/04

returns error reading clock; 0=no error

ReadDateTime accesses the clock chip directly and stores its return value into the low-memory variable <u>Time</u> (at 0x020C) and into the specified variable. Applications normally use <u>GetDateTime</u> or <u>GetTime</u>.

secs is the address of a 4-byte variable. Upon return, it contains the number of seconds since January 1, 1904 (as tracked by the real-time clock hardware).

Returns: an OSErr; an integer Error Code. It will be one of:

noErr (0) No error

clkRdErr (-85) Clock read error

Notes: You can convert the secs value to a more easily understood value (i.e., a DateTimeRec) via Secs2Date.

You can set the clock-chip to a new time/date using **SetDateTime**; though this is normally performed via the Control Panel DA.

Since the base date for the any "raw seconds" value is 1/1/1904 and since secs is a 32-bit value, you won't be able to calculate with dates beyond February 6, 2040.