ASPGetStatus Page 1

ASPGetStatus Get server status

#include <<u>AppleTalk.h</u>>

AppleTalk Manager

<u>OSErr</u> **ASPGetStatus**(*xParamBlock, async*);

<u>XPPParmBlkPtr</u> *xParamBlock*; pointer to an AppleTalk parameter block <u>Boolean</u> async; 0=await completion; 1=immediate return

returns Error Code; 0=no error

ASPGetStatus returns server status. This call is also used as GetServerInfo at the AFP level. This call is unique in that it transfers data over the network without having a session open. This call does not pass any data but requests that server status be returned.

xParamBlock is a pointer to a parameter block structure. The relevant fields are as follows:

Out-InName		<u>Type</u>	<u>Size</u>	<u>Offset</u>	<u>Description</u>
\leftarrow	csCode	short	2	26	Always ASPGetStatus
\leftarrow	aspTimeout	<u>char</u>	1	30	Retry interval in seconds
\leftarrow	aspRetry	<u>char</u>	1	31	Number of retries
\leftarrow	serverAddr	<u>short</u>	2	32	Server socket address
\leftrightarrow	rbSize	<u>short</u>	2	38	Reply buffer and reply size
\leftarrow	rbPtr	<u>Ptr</u>	4	40	Reply buffer pointer
\leftarrow	ccbStart	record	150	50	Start of memory for CCB

async is a <u>Boolean</u> value. Use <u>FALSE</u> for normal (synchronous) operation or <u>TRUE</u> to enqueue the request and resume control immediately. See Async I/O.

Returns: an operating system Error Code.

aspBufTooSmall (-1067) Reply is bigger than response buffer; the buffer will be filled, data will be truncated

aspNoServer (-1069) No response from server at address used in call

Notes: ASPTimeOut is the interval in seconds between retries of the call.

ASPRetry is the number of retries that will be attempted.

ServerAddr is the network identifier or address of the socket on which the server is listening.

RBSize is passed and indicates the size of the reply buffer in bytes expected by the command. RBSize is also returned and indicates the size of the reply that was actually returned.

RBPtr points to the reply buffer.

CCBStart is the start of the memory to be used by the .XPP driver for the command control block. The size of this block is equal to a maximum of 150 bytes.