SectionRecord Page 1

SectionRecord structure

#include <Editions.h>

typedef struct SectionRecord {		<u>Size</u>	<u>Offset</u>	<u>Description</u>
<u>char</u>	version;	1	0	always 0x01 in system 7.0
<u>SectionType</u>	kind;	1	1	stSubscriber or stPublisher
<u>UpdateMode</u>	mode;	2	2	auto or manual
<u>TimeStamp</u>	mdDate;	4	4	last change in document
<u>long</u>	sectionID;	4	8	app. specific, unique per
				document
<u>long</u>	refCon;	4	12	application specific
<u>AliasHandle</u>	alias;	4	16	handle to Alias Record
<u>long</u>	subPart;	4	20	which part of container file
struct SectionRecord	**nextSection;	4	24	for linked list of app's
				Sections
<u>Handle</u>	controlBlock;	4	28	used internally
EditionRefNum	refNum;	4	32	used internally
} SectionRecord:		36		•

typedef SectionRecord *SectionPtr; typedef SectionRecord **SectionHandle;

Field descriptions

version	Indicates the version of the section record,	currently

0x01.

kind Defines the section type as either publisher or

subscriber with the stPublisher or stSubscriber

constant.

mode Indicates if editions are updated automatically or

manually.

Indicates which version (modification date) of the mdDate

> section's contents is contained within the publisher or subscriber. The mdDate is set to 0 when you create a new subscriber section, and is set to the current time when you create a new publisher. Be sure to update this field each time publisher data is modified. The section's

modification date is compared to the edition's

modification date to determine whether the section and

the edition contain the same data. The section modification date is displayed in the publisher and subscriber options dialog boxes. See the section,

Closing an Edition for detailed information.

sectionID Provides a unique number for each section within a

> document. A simple way to implement this is to create a counter for each document that is saved to disk with the document. The counter should start at 1. The section ID is currently used as a tie breaker in the GoToPublisher function when there are multiple publishers to the same edition in a single document. The section ID should

SectionRecord Page 2

not be 0 or -1. See the section,

Duplicating Publishers and Subscribers for

information on multiple publishers.

refCon Available for application-specific use.

alias Contains a handle to the <u>alias record</u> for a particular

section within a document.

Whenever the user creates a publisher or subscriber, call the **NewSection** function to create the section record and the alias record.

The **NewSection** function creates a new section record (either publisher or subscriber), indicates whether editions are updated automatically or manually, sets the modification date, and creates an <u>alias record</u> from the document containing the section to the <u>edition container</u>.

The sectionDocument parameter can be NIL if your current document has never been saved. Use the <u>AssociateSection</u> function to update the <u>alias record</u> of a registered section when the user names or renames a document by choosing **Save As** from the **File** menu. If you are creating a subscriber with the *initialMode* parameter set to receive new editions automatically, your application receives a <u>Section Read event</u> each time a new edition becomes available for this subscriber.

If an error is encountered, the *sectionH* parameter is set to NIL. If not, sectionH contains the handle to the allocated section record.

Set the *initialMode* parameter to the update mode for each subscriber and publisher created. You can specify the update mode using these constants:

Constants

<u>sumAutomatic</u>	subscriber receives new editions automatically
<u>sumManual</u>	subscriber receives new editions manually
<u>pumOnSave</u>	publisher sends new editions on save
<u>pumManual</u>	publisher does not send new editions until user request

See <u>Using Publisher and Subscriber Options</u> for detailed information on update modes for publishers and subscribers.