SetDateTime Page 1

SetDateTime Set system date and time in "raw" seconds

#include <<u>OSUtils.h</u>>

Operating System Utilities

void SetDateTime(secs);

long secs; number of seconds since 01/01/1904

SetDateTime sets the system data and time by writing a "raw" seconds value to both the low-memory variable <u>Time</u> and the real-time clock chip. It also verifies that the clock chip accepted the change without error.

secs specifies the desired time. It is a count of seconds since Midnight, January 1, 1904.

Returns: an OSErr; an integer Error Code. It will be one of:

noErr (0) No error

clkWrErr (-86) Clock write error clkRdErr (-85) Clock read error

Notes: The system time needs to be changed only rarely (e.g, on switching to Daylight Savings Time) and is normally set by the user via the Control Panel DA.

The <u>Date2Secs</u> function can be used to convert a <u>DateTimeRec</u> into a "raw" seconds value. You could also use <u>SetTime</u>, which performs the conversion automatically.