# Form Errors

## Accessibility Considerations

Disabled CTAs are not keyboard focusable and may be skipped by screen readers, which can prevent users from understanding why an action is unavailable.

To ensure accessible and inclusive experiences, keep CTAs enabled and communicate issues through inline validation or page-level alerts. Error messages should be clearly associated with their inputs and announced to assistive technologies so all users understand what is required to proceed.

## Comparison of disabled CTA vs enabled CTA

This comparison highlights why enabled CTAs paired with clear error messaging provide a more usable and accessible experience than disabling actions without explanation.

❌ **Disabled CTA with Exceptions**

- Hides the reason why the action cannot be completed
- Not keyboard focusable and may be skipped by screen readers
- Provides no clear guidance on what the user needs to fix
- Increases friction and user confusion

✅ **Enabled CTA**

- Clearly explains what is missing or incorrect
- Supports inline and page-level error guidance
- Fully accessible via keyboard and screen readers
- Allows users to retry immediately after fixing errors
- Creates a clearer, more predictable user experience

Continue

VS

Continue

### BUTTON USAGE GUIDELINES IN FORMS

## Default Behavior

Primary CTAs should be enabled by default.

Buttons must not be disabled to indicate missing input, incomplete forms, or validation errors. Instead, use inline validation and/or page-level error messaging to clearly communicate what is required for the user to proceed.




## Single Error

When a user submits a form with a single invalid or missing input, keep the CTA enabled and display an inline error message for the affected field.

> **Developer Note**
> Use an anchor focus to bring the first errored input into view when it is outside the viewport.




Text input




Radio button inoput

## Multiple Errors

When a user submits a form with multiple invalid or missing inputs, keep the CTA enabled and display inline error messages for each affected field. In addition, show a page-level alert to clearly communicate that multiple issues need attention and guide the user to resolve them before proceeding.

> **Developer Note**
> Use an anchor focus to bring the alert banner into view when it is outside the viewport.




## Form submission with enabled CTA + Tile + Alert message

When a user attempts to continue without selecting a tile, keep the CTA enabled and display a page-level alert explaining that a selection is required.

> **Developer Note**
> Use an anchor focus to bring the alert banner into view when it is outside the viewport.