
Four sources of packet delay

1. nodal processing:

- check bit errors
- determine output link

2. queueing

- time waiting at output link for transmission
- depends on congestion level of router



1


Delay in packet-switched networks

3. Transmission delay:

- R=link bandwidth (bps)
- L=packet length (bits)
- time to send bits into link = L/R

4. Propagation delay:

- d = length of physical link
- s = propagation speed in medium (~2x10⁸ m/sec)
 - propagation delay = d/s




Nodal delay

$$d_{\text{nodal}} = d_{\text{proc}} + d_{\text{queue}} + d_{\text{trans}} + d_{\text{prop}}$$

- d_{proc} = processing delay
 - typically a few microsecs or less
- d_{queue} = queuing delay
 - depends on congestion
- · d_{trans} = transmission delay
 - = L/R, significant for low-speed links
- d_{prop} = propagation delay
 - a few microsecs to hundreds of msecs

3

Statistical Multiplexing and Queueing




Queueing delay (revisited)

average

- R=link bandwidth (bps)
- L=packet length (bits)
- a=average packet arrival rate

traffic intensity = La/R



- La/R ~ 0: average queueing delay small
- La/R -> 1: delays become large
- La/R > 1: more "work" arriving than can be serviced, average delay infinite!


Queueing delay and Packet loss

- Queue (aka buffer) preceding link in buffer has finite capacity
- When packet arrives to full queue, packet is dropped (aka lost)
- lost packet may be retransmitted by previous node, by source end system, or not retransmitted at all

CSci4211: Introduction


Throughput

- throughput: rate (bits/time unit) at which bits transferred between sender/receiver
 - instantaneous: rate at given point in time
 - average: rate over longer period of time




Throughput (cont'd)

• $R_s < R_c$ What is average end-end throughput?



 $\square R_s > R_c$ What is average end-end throughput?




bottleneck link

link on end-end path that constrains end-end throughput

8

Throughput: Internet scenario

- per-connection end-end throughput: $min(R_c,R_s,R/10)$
- in practice: R_c or R_s is often bottleneck



10 connections (fairly) share backbone bottleneck link R bits/sec