# Real-Time Programming

Lecture 5

Farhang Nemati Spring 2016

# Semaphores/Mutexes; Exercise

- Improve the Producer-Consumer so that:
  - There is a maximum size for the buffer:

int buffer[10];

- The producer waits (is blocked) if buffer is full
- The consumer waits (is blocked) if the buffer is empty

### Repetition

- volatile ...
- Semaphores
- Mutexes

# Semaphores/Mutexes; Solution

```
#include <pthread.h>
#include <semaphore.h>

const int MAX_BUF_SIZE = 10;
int buffer[MAX_BUF_SIZE];
void start()
{
   pthread_mutex_t mutex = PTHREAD_MUTEX_INITIALIZER;
   sem_t bufFullSem, bufEmptySem;
   pthread_t prodThrd, consThrd;
   sem_init(&bufFullSem, 0, MAX_BUF_SIZE);
   sem_init(&bufFullSem, 0, 0);
   pthread_create(&prodThrd, NULL, producer, NULL);
   pthread_create(&consThrd, NULL, consumer, NULL);
}
```

### Semaphores/Mutexes; Solution

### Problems with Semaphores and Mutexes

```
    Deadlock

  //Task1
                          //Task2
                                                 asks for sem1
                                                                             asks for sem2
  sem wait(&sem1);
                          sem wait(&sem2);
                                                 asks for sem2
  sem wait(&sem2);
                           sem wait(&sem1);
                                                sem2 is already
                                                taken, waits
                                                                             aken, waits
  sem post(&sem2);
                          sem post(&sem1);
  sem post(&sem1);
                          sem post(&sem2);
```

- Task Starvation (Indefinite Postponement)
- Error prone: One mistake can take the whole system down.

#### **Condition Variables**

- In combination with a mutex
- Two Operations
  - Wait: Always waits (suspends) for a condition. Releases the associated mutex while suspending on the condition.
  - Signal: wakes up a waiting task. The waiting task is resumed and checks the condition again. Has no effect if no task is waiting for the condition.

### **POSIX Condition Variables**

```
pthread_cond_t condition_cond = PTHREAD_COND_INITIALIZER;
pthread_cond_wait(pthread_cond_t*,pthread_mutex_t *);
pthread_cond_signal(pthread_cond_t*,pthread_mutex_t *);
```

#### Condition Variables

```
void start()
{
   pthread_mutex_t mutex =PTHREAD_MUTEX_INITIALIZER;
   pthread_cond_t cond = PTHREAD_COND_INITIALIZER;

   pthread_t prodId, oddConsId, evenConsId;
   pthread_create(&prodId, NULL, producer, NULL);
   pthread_create(&oddConsId, NULL, oddConsumer, NULL);
   pthread_create(&evenConsId, NULL, evenConsumer, NULL);
}
```

#### **Condition Variables**

```
void *oddConsumer(void *arg)
{
    while(1)
    {
        pthread_mutex_lock(&mutex);
        while(index == 0 || buffer[index] %2 == 0)
        {
            pthread_cond_wait(&cond, &mutex);
        }
        y = buffer[--index];
        pthread_mutex_unlock(&mutex);

        //Another consumer might be waiting ...
        pthread_cond_signal(&cond, &mutex);

        addOdd(y);
    }
}
```

#### Condition Variables

#### Monitors

- All critical sections and operations needed for managing synchronization are encapsulated in modules that are called Monitors.
- Critical sections and variables to be accessed under mutual exclusion are hidden from the caller.

# Monitor Example

```
const int MAX_SIZE = 100;
typedef struct Monitor
{
    pthread_mutex_t mutex;
    pthread_cond_t bufFullSem;
    pthread_cond_t bufEmptySem;
    int buffer[MAX_SIZE];
    int index = 0;
} MyMonitor;

void initMonitor(myMonitor* monitor)
{
    monitor->mutex = PTHREAD_MUTEX_INITIALIZER;
    monitor->bufFullSem = PTHREAD_COND_INITIALIZER;
    monitor->bufEmptySem = PTHREAD_COND_INITIALIZER;
}
```

#### **Barriers**

- A synchronization point for a group of tasks
- Every task in the group stops at the assigned barrier until all other tasks from the group are reached the barrier

# Monitor Example

```
void takeValue(myMonitor* monitor, int* x)
{
    pthread_mutex_lock(&(monitor->mutex));
    while(monitor->index == 0)
    {
        pthread_cond_wait(&(monitor-> bufEmptySem), &(monitor->mutex));
    }
    *x = monitor->buffer[--monitor->index];
    pthread_mutex_unlock(&(monitor->mutex));
    pthread_cond_signal(&(monitor-> bufFullSem), &(monitor->mutex));
}

void addValue(MyMonitor* monitor, int x)
{
    pthread_mutex_lock(&(monitor->mutex));
    while(monitor->index == MAX_SIZE)
    {
        pthread_cond_wait(&(monitor->bufFullSem), &(monitor->mutex));
    }
    monitor->buffer[monitor->index++] = x;
    pthread_mutex_unlock(&(monitor->mutex));
    pthread_cond_signal(&(monitor->bufEmptySem), &(monitor->mutex));
}
```