BLENDER ADD-ON MANUAL

DRH - Color Ramp Studio | Professional User Manual

Document	User Manual
Product Version	1.0.0
Host Application Compatibility	Blender 4.2.0 or later
Author / Brand	Paco Salas | DRH
Support Page	GitHub Support Page
Revision Date	2026-01-01

Document Information and Revision History

Field	Value
Document Title	DRH - Color Ramp Studio User Manual
Product	DRH - Color Ramp Studio
Version	1.0.0
Host Application Compatibility	Blender 4.2.0 or later
Author / Brand	Paco Salas | DRH
Support Page	GitHub Support Page
Document Language	English
Target Audience	Blender users, technical artists, shader artists, compositing users, support staff, and reviewers.
Document Type	Complete user manual

Revision	Date	Prepared By	Summary
1.0.0	2026-01-01	OpenAI	Initial commercial user manual edition.

Copyright and Disclaimer

> Important: Review support, legal, and distribution details against the released package when publishing updated versions.

Topic	Statement
License	Distributed under the GNU General Public License, version 3 or later.
Copyright Holder	Paco Salas | DRH.
Warranty	Unless separately stated in writing, the software is provided without warranty.
Commercial Distribution	Commercial distribution is permitted, provided GPL license terms, copyright notices, source code, and third-party notices remain available with distributed copies.
Manual Legal Status	This manual is intended for end-user guidance and product distribution documentation.

Table of Contents

Document Information and Revision History 1
Copyright and Disclaimer 1
Table of Contents 2
About This Manual 4
Audience and Intended Use 4
Product Overview 4
Key Features 5
System Requirements 5
Compatibility 6
Supported Scope and Non-Supported Scope 6
Included Components 6
Installation 7
- Prerequisites 7
- Standard Installation Method 7
- Alternative Installation or Extension Manager 8
- First Launch and Verification 8
- Update, Reinstall, and Uninstall 9
- Common Installation Problems 9

Quick Start 9
Product Preferences and Settings 10
- Host Application Preferences / Extension Manager 10
- Runtime Panel Settings 11

Interface Overview 12
Visual Interface Walkthrough 13
Main Panels, Menus, and Controls 13
- Primary Actions 13
- Primary Setup 14
- Filters, Lists, and Main Results Area 14
- Selected Item Review 14
- Secondary or Comparison Controls 15

Recommended Workflows 15
- Workflow 1: Basic Use 15
- Workflow 2: Review or Export the Current Result 15
- Workflow 3: Export or Process a Selected Subset 15
- Workflow 4: Compare Against a Previous Baseline 16

Step-by-Step Usage Instructions 16
- 1. Start or Refresh the Main View 16

2. Interpret Summary Metrics 16
3. Review Row States 17
4. Open Supporting Paths 17
Import, Export, Output, and Profiles 17
Supported Export Formats 17
Export Profiles 18
Comparison Profiles 19
Output Naming Behavior 19
Privacy, Data Handling, and Local Processing 19
Understanding Outputs, Statuses, and Decision Logic 19
Common Use Cases 20
Advanced Tips and Best Practices 20
Update and Migration Guidance 20
Troubleshooting by Scenario 20
Known Constraints and Operational Notes 21
FAQ 21
Support, Contact, and Updates 22
Support Workflow 22
Pre-Support Checklist 22
Availability 23
Legal, Disclaimer, and Credits 23
Appendix A – Glossary 23
Appendix B – Reference Layer 23
Appendix C – Specialized Technical Sections 24

About This Manual

This manual explains how to install, configure, and use DRH - Color Ramp Studio in Blender. It is intended as the primary end-user guide for first-time setup, day-to-day node editing, screen and image sampling, ramp conversion, and troubleshooting.

Conventions Used	Meaning
Bold UI labels	Product interface labels such as Refresh, Export, and Open Last Report.
Numbered steps	Action procedures that the user should perform in order.
Note / Tip / Warning / Important	Callout labels used to highlight operational details or cautions.
Important	Operational detail or caution that should be reviewed before continuing.
Figure	Illustration, interface view, or report example referenced in the guide.

> Note: This manual focuses on practical production use. Use the Quick Start section for the fastest path to a working result, then return to the detailed workflow sections as needed.

Audience and Intended Use

This manual is intended for Blender users who work with Color Ramp nodes in shader, compositor, and geometry-node workflows. It supports individual artists, technical artists, support reviewers, and production users who need reliable ramp generation, editing, transfer, and restoration tools.

Product Overview

DRH - Color Ramp Studio is a Blender add-on for generating, converting, sampling, refining, previewing, transferring, and organizing Color Ramp nodes.

Its main workflows include native ramp generation, conversion to editable group-based ramps, restoration back to native ramps, image-based palette extraction, screen gradient sampling, and day-to-day utility actions such as copy, paste, reverse, normalize, simplify, and cleanup.

> Important: Some features depend on a valid Blender node-editor context, readable image files, and platform-specific screen-capture permissions.

Capability Area	What It Does
Ramp generation	Creates Color Ramp results from built-in generation modes and presets.
Ramp conversion	Converts native Color Ramp nodes into editable group-based workflows for advanced control.
Ramp restoration	Restores converted group-based ramps back to native Color Ramp nodes when needed.
Image palette extraction	Builds ramps from readable image files and reference images.
Screen gradient sampling	Captures screen color flow and turns it into a target ramp, subject to platform support.

Capability Area	What It Does
Transfer tools	Copies and pastes ramp data between supported targets.
Cleanup utilities	Redistributes, normalizes, simplifies, randomizes, reverses, and de-duplicates stops.
Preview helpers	Supports ramp review, helper actions, and day-to-day editing utilities.

Key Features

Feature	Details
Native Color Ramp generation tools	Fast creation of ramps inside supported Blender node editors.
Editable group-based conversion	Advanced editing path for workflows that need more control than a native ramp alone.
Restore tools	Return converted ramps to native ramps when appropriate.
Image-based sampling	Extract colors from a user-selected image file.
Color Sampler	Capture on-screen gradients with overlay preview, subject to operating-system support.
Transfer and utility tools	Copy, paste, reverse, normalize, randomize, and simplify ramp data.
Context-menu helpers	Access selected tools directly from supported node context menus.

System Requirements

Requirement	Verified Information
Host application	Blender 4.2.0 or later.
Maximum tested version	Not separately stated in the available package documentation.
Supported platforms	Windows, macOS, and Linux x64 are listed in the package manifest. Screen sampling has platform-specific limits.
Dependencies	No separate end-user dependency installation is required for the packaged add-on.
Bundled binaries	None stated. The package includes bundled Python code, including the vendored mss screen-capture dependency.
Filesystem access	Readable image-file access is required for image-based palette extraction and reference image loading.
Internet access	Not required for normal operation.
Disk space / memory	Typical Blender add-on footprint; resource use depends on Blender session complexity and image size.

Compatibility

Area	Compatibility Notes
Host application	Blender 4.2.0 or later. Main workflows target the Node Editor sidebar.
Windows	Supported. Screen capture depends on standard OS permission and window-state conditions.
macOS	Partial. Core add-on workflows are supported, but screen sampling may be blocked until Screen Recording permission is granted to Blender.
Linux	Partial. Core add-on workflows are supported. The bundled screen-capture backend does not support pure Wayland sessions; X11 or XWayland is required for the sampler feature.
File format or data compatibility	Works with Blender Color Ramp nodes, converted helper groups, readable image files, and saved Blender project data.
Installation or discovery logic	Install the ZIP package through Blender preferences or extension workflow, then enable the add-on and use the DRH-Ramp Studio tab in the Node Editor sidebar.

Supported Scope and Non-Supported Scope

> Warning: Screen sampling is platform-sensitive and should not be treated as universally available in every display-session configuration.

The add-on is designed to accelerate Color Ramp work inside Blender and to provide more flexible editing and sampling workflows. It does not replace Blender itself, does not guarantee identical behavior between native and converted group-based ramps in every case, and should not be treated as a general-purpose color-management system outside supported Blender node contexts.

Included Components

Component	Purpose
Add-on package	Installs the Color Ramp Studio functionality into Blender.
Panel interface	Provides the main Node Editor sidebar workspace.
Generator tools	Create or reshape ramps from presets and operator settings.
Conversion tools	Convert between native and editable group-based ramp workflows.
Transfer tools	Copy and paste ramp data between supported targets.
Color Sampler tools	Capture screen gradients into a ramp when platform conditions allow.
Image tools	Load a reference image for image-based ramp generation.
Utility tools	Reverse, normalize, randomize, simplify, and clean stops.
Preferences	Store panel defaults and related add-on behavior.

Component	Purpose
Bundled notices	License, copyright, and third-party attribution files included with the package.

Installation

Prerequisites

1. Confirm that Blender 4.2.0 or later is installed and that you can access the Node Editor.
2. Download the DRH - Color Ramp Studio ZIP package.
3. Confirm that Blender can install add-ons from disk and, if you plan to use Color Sampler, that screen-capture permissions can be granted on your platform.
4. Restart Blender after installation only if your environment requires it.

Standard Installation Method

1. Open Blender.
2. Go to Edit > Preferences.
3. Use Get Extensions or Install from Disk / Install Add-on from Disk, depending on your Blender version and setup.
4. Select the ZIP package and complete the installation.
5. Enable DRH - Color Ramp Studio.
6. Open the Node Editor sidebar.
7. Confirm that the DRH-Ramp Studio tab is present.



> Note: After installation, confirm the add-on is enabled and that the DRH-Ramp Studio tab is visible in the Node Editor sidebar.

Alternative Installation or Extension Manager

1. If your Blender setup uses the extensions workflow, install the ZIP package through that interface rather than a legacy add-on import path.
2. After installation, verify that the add-on is listed as enabled.
3. Open Node Editor > Sidebar and confirm the panel location.

> Important: Blender version, active editor context, and screen-capture permissions can affect whether every tool is immediately available.

First Launch and Verification

1. Open a supported Node Editor in Blender.
2. Select a Color Ramp node and apply a generator or utility action.
3. Open DRH - Color Ramp Studio and run a simple generator or utility action.
4. Review panel settings and preferences if a tool is hidden or behaves differently than expected.

Update, Reinstall, and Uninstall

Task	Recommended Procedure
Update	Install the newer package version through Blender, re-enable the add-on if needed, then verify the sidebar tab, preferences, and key workflows.
Reinstall	Disable the add-on, remove the installed copy if required by your environment, install the package again, and re-enable it in Blender.
Uninstall	Disable the add-on in Blender preferences and remove the installed package from your add-on or extensions location if a full removal is required.
Preserve outputs	Ramp data stored inside saved .blend files remains subject to Blender project state. Review converted groups, preferences, and sampler-dependent workflows after any reinstall or update.

Common Installation Problems

Issue	Likely Cause	Resolution
The add-on does not appear in Blender	Package not installed or not enabled	Reinstall the ZIP package and enable DRH - Color Ramp Studio in Blender preferences.
The sidebar tab is missing	Wrong editor context or panel not enabled	Open the Node Editor sidebar and confirm the add-on is enabled and the panel is not hidden.
Image-based generation fails	Unreadable or invalid image path	Verify that the selected file exists and that Blender can read it.
Color Sampler cannot capture	Missing permission or unsupported display backend	Grant OS capture permissions where needed, and on Linux use X11 or XWayland instead of a pure Wayland session.

Quick Start

Area	Verified Status
Activation	No separate activation workflow is described in the package documentation.
License model	GPL-3.0-or-later.
Commercial support terms	Support and related commercial services may be offered separately from the software distribution itself.
Initial setup tasks	Enable the add-on, open the Node Editor sidebar, select a target Color Ramp node, and test a generator or utility action.

After enabling the add-on, open the Node Editor sidebar, select a Color Ramp node, open the DRH-Ramp Studio tab, choose a generator or utility action, and apply it to confirm the add-on is active and writing results to the selected ramp.

Product Preferences and Settings

Color Ramp Studio includes add-on preferences and runtime panel controls that govern panel behavior, default section visibility, generator options, conversion behavior, transfer helpers, sampling features, and preview-oriented tools.

Host Application Preferences / Extension Manager

Preferences Section	Purpose
Panel Defaults	Controls default expansion state and general panel behavior.
Generator	Stores preferred generator-related defaults.
Conversion	Controls conversion behavior and restore preferences.
Tools	Holds defaults for transfer, sampler, and stop-editing helpers.
Context Menu	Optionally enables supported context-menu integration.
Spline Bake Return	Sets how sampled spline groups return during restoration.









Runtime Panel Settings

Setting	Description
Show as Tabs	Switches the main panel between tabbed and expanded section presentation.
Enable Context Menu	Adds supported helper actions to node context menus.
Generator section state	Controls whether generator tools are open by default.
Conversion section state	Controls whether conversion tools are open by default.
Tools section state	Controls whether utility tools are open by default.
Preview section state	Controls preview/helper section visibility.
Default samples	Defines a preferred sample count for relevant operations.

Setting	Description
Default sampled return mode	Determines how baked sampled spline groups are restored.
Reference image path	Points image-based generation tools to a readable source image.

Default Rules and Status Logic

Most actions in the add-on are context-sensitive. Operators become useful only when Blender is in a supported node-editor context and when the selected node or target image path is valid for the chosen operation.

Default Risk Band	Issue Keys in the Default Rules
Valid node context	Most operators require a supported Node Editor context and a valid target node.
Readable image path	Image-based palette extraction requires a readable file path.
Capture permission available	Color Sampler needs operating-system permission and supported backend conditions.

> Important: When a tool appears inactive or unavailable, verify the current editor type, selected node, image path, and platform permissions before assuming a product fault.

Interface Overview

The main interface appears in the Node Editor sidebar under the DRH-Ramp Studio tab. The workspace is organized around generator, conversion, tools, sampler, preview, and utility sections, with panel settings available from the header.

Area	What It Contains
Panel header	Shows the panel title, icon, and access to panel settings.
Main sections	Contains generator, conversion, tools, preview, and sampler-oriented controls.
Runtime controls	Displays action buttons, toggles, and value fields for the active workflow.
Image helper area	Exposes reference-image loading and Image Editor helper actions when relevant.



Visual Interface Walkthrough

The interface centers on a sidebar panel in the Node Editor. Core actions are grouped into expandable sections so users can keep the workspace compact while focusing on generation, conversion, transfer, cleanup, or sampling tasks. When image-based tools are used, related controls also appear for loading a reference image and opening helper Image Editor windows.

Main Panels, Menus, and Controls

Primary Actions

Control	Function
Convert Selection	Converts selected native Color Ramp nodes to editable groups or converts supported groups back to native ramps.
Copy Ramp	Copies the active ramp data for reuse.
Paste Ramp	Applies previously copied ramp data to a supported target.
Reset All	Restores supported settings or defaults for a clean working state.

Primary Setup

Field	Purpose
Group Blend	Defines interpolation used by generated Map Range nodes when preserve mode is disabled.
Preserve native interpolation	Keeps native interpolation when conversion can preserve it.
Group name template	Controls naming behavior for generated helper groups.
Reference image	Supplies the source file for image-based ramp generation.
Default sample count	Sets the typical stop count or sampling granularity for relevant tools.

Filters, Lists, and Main Results Area

Control	Purpose
Preset browser	Filters and selects generator presets.
Generator mode	Chooses how a new ramp is produced.
Transfer tools	Copies or pastes ramp data between targets.
Simplify / cleanup tools	Reduces redundant or overly similar stops.
Color Sampler controls	Captures a visible screen gradient into a ramp.
Image helper controls	Loads, clears, and manages reference-image workflows.

Selected Item Review

Displayed Value	Notes
Selected node state	Indicates whether the current target is a native ramp or converted group.
Interpolation settings	Shows how color transitions are currently defined.
Stop positions and colors	Represents the active ramp content being edited or generated.
Reference image status	Confirms whether an image source is loaded for image-based generation.
Sampler readiness	Reflects whether capture-related tools are available in the current session.
Restore behavior	Shows how sampled spline groups will be returned during restoration.

Secondary or Comparison Controls

Control	Function
Expand All / Collapse All	Opens or closes all main sections for faster navigation.
Panel Settings	Opens runtime and default-panel configuration controls.
Open Image Editor Window	Creates an Image Editor workspace for reference image review.
Close All Open Image Editor Windows	Closes helper Image Editor windows opened by the add-on.
Load Reference Image	Selects an image for image-based generation.
Clear Reference Image	Removes the active reference image selection.

Recommended Workflows

Workflow 1: Basic Use

1. Open the Node Editor sidebar and the DRH-Ramp Studio tab.
2. Select a Color Ramp node and apply a generator or utility action.
3. Confirm that the selected ramp updates as expected.
4. Adjust generator, cleanup, or sampler settings as needed.
5. Review the resulting stop layout, colors, and interpolation behavior.

Workflow 2: Review or Export the Current Result

1. Choose the workflow that matches your goal, such as native editing, conversion, image sampling, or screen sampling.
2. Select a preset or operator setting that fits the intended color flow.
3. Confirm the active ramp target or generated group before applying changes.
4. If you will share screenshots or files, review whether image paths or project names should remain visible.
5. Run the action.
6. Check the resulting ramp in the active node context.

> Tip: Save a small test .blend file with representative ramps before large version changes so you can verify generator, conversion, and restore behavior quickly.

Workflow 3: Export or Process a Selected Subset

1. Select the exact ramp or converted group you want to modify.
2. Confirm the target node selection.
3. Choose the relevant utility, cleanup, or transfer tool.
4. Apply the action and inspect the result.

> Important: Focused edits work best when the intended target ramp is clearly selected before transfer, cleanup, or restore operations.

Workflow 4: Compare Against a Previous Baseline

1. Save a working .blend file or keep a known-good ramp available for reference.
2. Open the relevant node editor and target ramp.
3. Load the reference image or copied ramp data if your workflow depends on it.
4. Compare the new result against the known-good visual target.
5. Adjust settings, simplify stops, or restore the native ramp as needed.
6. Save the .blend file once the result is acceptable.

Step-by-Step Usage Instructions

1. Start or Refresh the Main View

Select the target Color Ramp node or converted group, review the active panel section, then run the required generator, conversion, restore, transfer, or cleanup action. Re-run the operator after changing source colors, sampling data, or utility settings to refresh the result.

> Note: Many tools apply immediately to the selected node. If a result seems unchanged, verify the target selection and re-run the action after adjusting the relevant settings.

2. Interpret Summary Metrics

Metric	Meaning
Native ramp selected	A standard Blender Color Ramp node is active.
Converted group selected	A supported generated helper group is active and can be edited or restored.
Reference image loaded	Image-based tools have a valid source file available.
Capture backend available	Screen-sampling backend is present for the current platform session.
Sampler permission granted	The operating system is allowing the required capture operation.
Preset match found	Current browser filters resolve to one or more presets.
Preserve interpolation enabled	Conversion will try to maintain native interpolation behavior.
Group blend mode	Generated helper groups will use the chosen blend rule where applicable.
Stop count target	The active generator or cleanup tool has a defined stop count or simplification goal.

Metric	Meaning
Restore mode	Sampled spline groups will restore either the original spline or a baked linear state.

3. Review Row States

State	Operational Meaning
Ready	The current context supports the chosen action.
No valid target	No supported Color Ramp node or converted group is selected.
Image missing	The referenced image path is invalid or unreadable.
Permission blocked	The operating system is not allowing the capture action.
Unsupported session	The current display/session backend does not support the requested sampler action.
Converted	The active target is a generated editable group rather than a native ramp.
Restorable	The selected converted target can be returned to a native ramp workflow.
Error reported	The operator detected a problem and returned an explicit error rather than generating unrelated output.

4. Open Supporting Paths

1. Open the Node Editor and inspect the active target directly in Blender.
2. Review the resulting native ramp or converted group in the current file.
3. When image-based tools are involved, reopen the selected image path to validate the source.

> Warning: File selection and path-opening behavior follow your operating system and Blender environment. On Linux, screen sampling additionally depends on X11 or XWayland for the bundled capture backend.

Import, Export, Output, and Profiles

Supported Export Formats

Format	Use Case
Blender node data	Primary result format written directly into native Color Ramp nodes.
Converted helper groups	Editable grouped representation for advanced ramp workflows.
Reference image input	Readable image files used for palette extraction.

Format	Use Case
Copied ramp data	Temporary in-session transfer content used by copy and paste tools.
Saved .blend files	Persistent storage of generated and edited ramp results.
Screen capture samples	Temporary sampled color-flow data used to build a ramp.
Image Editor helper state	Workspace support for reviewing reference images during sampling workflows.

Supported Comparison or Baseline Input Formats

The add-on does not expose a dedicated comparison-import subsystem. Instead, users work directly with Blender node data, reference images, and copied ramp data inside the active Blender session.

Accepted File Type	Notes
Readable image file	Used for image-based palette extraction and reference loading.
Blender project data	.blend file state stores native ramps, converted groups, and related settings.
Visible screen region	Used by Color Sampler when capture permissions and backend support are present.
Copied ramp state	Used when pasting previously copied ramp data.
Selected Color Ramp node	Primary live input target for most operations.
Converted helper group	Advanced editable target used by conversion and restore workflows.

Export Profiles

Profile	Description	Typical Use
Native editing workflow	Operate directly on standard Blender Color Ramp nodes.	Fast everyday editing and generation.
Converted editing workflow	Use group-based ramps for extended control and spline-aware work.	Advanced iterative editing.
Image sampling workflow	Load a source image and generate ramp content from it.	Palette extraction from artwork or references.
Screen sampling workflow	Capture visible screen gradients into a ramp.	Building ramps from existing on-screen material.
Transfer workflow	Copy one ramp and paste it into another target.	Reusing approved ramps across nodes.

Profile	Description	Typical Use
Cleanup workflow	Normalize, simplify, randomize, or redistribute stops.	Refining ramps before final use.
Restore workflow	Return a converted group to a native ramp result.	Handing work back to native Blender workflows.
Preview workflow	Review reference images and helper windows while editing.	Visual inspection and support tasks.
Context-menu workflow	Use supported actions from the node context menu.	Faster access during repetitive editing.

Comparison Profiles

Comparison Profile	Columns Included
Native-to-converted review	Selected node type, interpolation mode, stop layout, and expected edit path.
Sampler readiness review	Reference image state, capture permission state, and active platform conditions.
Restore validation review	Converted target identity, return mode, and resulting native-ramp behavior.

Output Naming Behavior

The add-on primarily writes results into Blender node data and generated helper groups. Export-style naming therefore depends on Blender project naming, image-file selection, and any user-managed asset naming inside the .blend file.

> Note: Naming is usually driven by Blender node and project naming rather than by a separate export-profile system inside the add-on.

Privacy, Data Handling, and Local Processing

Color Ramp Studio operates locally inside Blender. It reads node context, selected image paths for palette extraction, and screen pixels for the sampler where platform permissions allow. It writes Color Ramp data, generated helper groups, related node settings, and temporary runtime state inside the current Blender session and saved .blend file. No internet connection or external service is required for normal operation.

Understanding Outputs, Statuses, and Decision Logic

Most outputs are direct visual changes to the selected Color Ramp or generated helper group. Generator actions produce new stop distributions or interpolations, conversion actions replace or restore editable structures, sampler actions build ramps from captured color flow, and transfer actions copy ramp state between supported targets. Error messages generally indicate invalid context, missing files, unsupported platform state, or missing permissions.

Common Use Cases

Use Case	How the Product Helps
Build a new gradient quickly	Use generator tools and presets to create a ramp faster than manual stop-by-stop editing.
Extract a palette from artwork	Load a readable image and derive ramp colors from the reference.
Match an on-screen gradient	Use Color Sampler to capture a visible color flow and apply it to the active ramp.
Refine a complex ramp	Use conversion, simplify, redistribute, and cleanup tools for more controlled editing.
Reuse a proven ramp	Copy an approved ramp and paste it to another supported target.

Typical use cases include building gradients faster, extracting palettes from an image, sampling colors from the screen, converting ramps into more editable grouped controls, restoring those groups back to native ramps, and cleaning or redistributing stops before final shading or compositing work.

Advanced Tips and Best Practices

Run a fresh Primary scan before exporting a report that will be shared or archived.

Use the Selected profile for focused troubleshooting exports instead of sending the full product environment every time.

- Turn on Sanitize Paths before exporting outside your organization if user-home paths should not be exposed.
- When investigating duplicates, compare Duplicate, Conflict, Shadow, and Newest Safe together rather than in isolation.
- Treat Compatibility = Unknown as a review item, not a pass result.

Before major Blender or pipeline changes, save a working .blend test case so you can compare ramp behavior, converted groups, and sampler results after the update.

Update and Migration Guidance

After updating or reinstalling, verify that the add-on is still enabled, confirm that the DRH-Ramp Studio tab appears in the Node Editor sidebar, review any add-on preferences that control panel defaults or context-menu features, and test generator, conversion, and sampler tools in a supported node context before resuming production work.

Troubleshooting by Scenario

Symptom or Message	Probable Cause	Recommended Action
The panel opens but tools seem unavailable	Unsupported editor context or no valid target selected	Switch to a supported Node Editor context and select a native ramp or supported converted group.
Convert Selection fails	Selected node is unsupported or context is	Verify the current node type and retry with a supported Color Ramp target.

Symptom or Message	Probable Cause	Recommended Action
	invalid	
Image-based generator reports an error	The image file is missing, unreadable, or unsupported by Blender	Check the file path and confirm Blender can load the image normally.
Color Sampler cannot start	Permissions or platform backend do not allow capture	Grant capture permission where applicable and confirm the current platform session is supported.
Screen sampling fails on Linux	Pure Wayland session in use	Use X11 or XWayland for the sampler feature.
Screen sampling fails on macOS	Screen Recording permission not granted to Blender	Enable the required permission in macOS privacy settings, then retry.
Pasted result is not what you expected	The copied source or target selection changed	Copy again from the intended source and verify the active target before pasting.
Converted ramp behaves differently	Group-based editing path does not exactly mirror every native expectation	Review preserve/restore options and return to a native ramp when the native workflow is preferred.
No useful result after a utility action	Action settings or target state do not match the intended workflow	Review the selected node, current settings, and whether a native or converted workflow is more appropriate.

Known Constraints and Operational Notes

Current results reflect the active Blender session and the selected node context; they do not validate unrelated files or unsaved external changes.

Compatibility is based on declared metadata and installation version detection, not on executing every product.

Platform-sensitive features, especially screen sampling, may behave differently when required permissions or supported display backends are not available.

Comparison comparison supports only the documented export file types and enforces input safety limits such as a 64 MiB file-size limit.

Large comparisons are subject to row-count and workbook safety limits in the comparison loader.

FAQ

Question	Answer
Where do I find the add-on after installation?	Open the Node Editor sidebar and look for the DRH-Ramp Studio tab.
What Blender versions are supported?	The package documentation states Blender 4.2.0 or later.

Question	Answer
Does the add-on require internet access?	No. Normal operation is local and does not require an external service.
Can I restore a converted ramp back to a native ramp?	Yes. The add-on includes restore tools for supported converted workflows.
Why is screen sampling unavailable on my system?	The sampler depends on OS permissions and supported display-session backends.
Does Linux support the Color Sampler?	Yes, but not in pure Wayland sessions with the bundled backend; X11 or XWayland is required.
What file types are needed for image-based ramp generation?	Use a readable image file that Blender can load successfully.
Where should I request support or report issues?	Use the GitHub Support Page listed in this manual.

Support, Contact, and Updates

Item	Current Status
Support Page	GitHub Support Page
Support Scope	Public issue tracking, documentation follow-up, release-related questions, and reproducible problem reports.
Issue Reporting	Provide version details, Blender version, operating system, reproduction steps, and safe-to-share screenshots or sample files when possible.
Release Notes / Updates	Use the GitHub support repository for public update and issue-tracking information.
Marketplace Availability	This product may be available through multiple marketplaces and storefronts.

Support Workflow

Use the GitHub support repository as the central public support hub. A useful request should include the add-on version, Blender version, operating system, the editor context in use, exact steps to reproduce the issue, whether the issue affects native ramps, converted ramps, image sampling, or screen sampling, and any safe-to-share screenshots or .blend examples that demonstrate the behavior.

Pre-Support Checklist

[Describe what information users should gather before requesting support, such as product version, host application version, operating system, steps to reproduce, screenshots, and safe-to-share outputs or logs.]

Availability

This product may be available through multiple marketplaces and storefronts.

For support, documentation, and issue tracking, please use this GitHub repository as the central public support hub.

Legal, Disclaimer, and Credits

Area	Text
Credits	Product by Paco Salas | DRH. Blender is the host application used by this add-on.
License Notice	Distributed under the GNU General Public License, version 3 or later. Keep license and source-availability obligations aligned with distributed copies.
Warranty Notice	Unless separately stated in writing, the software is provided without warranty.
Trademark Acknowledgement	Third-party product and platform names are referenced only to identify compatibility and workflow context.
Third-Party Dependencies	The package redistributes the mss screen-capture component and includes third-party notices with the release.
Distribution Notice	When redistributing the package, retain copyright notices, license files, source availability, and bundled third-party notices.

Appendix A – Glossary

Term	Definition in This Manual
Native ramp	A standard Blender Color Ramp node.
Converted group	An editable group-based ramp structure created by the add-on.
Restore	The process of returning a converted group to a native ramp result.
Color Sampler	The feature used to capture on-screen color flow into a ramp.
Reference image	A readable image file used as a source for image-based ramp generation.
Transfer	Copying ramp data from one supported target and pasting it into another.
Interpolation	The rule used to transition between ramp colors.
Context menu helper	A supported add-on action exposed through Blender node context menus.

Appendix B – Reference Layer

This appendix provides a reference layer for key interface terms, workflow concepts, and output-related notes used throughout the manual.

Appendix C – Specialized Technical Sections

This appendix summarizes technical notes that matter to advanced users, including platform-specific screen-capture constraints and bundled dependency notes.

Topic	Note
Automation / CLI / API	No dedicated command-line or public API layer is described in the packaged end-user materials.
Platform capture backend	The bundled mss dependency provides cross-platform screen-capture support with documented limits on pure Wayland sessions.
Bundled dependency notice	Third-party attribution for the vendored mss package is included with the release archive.