# Lecture 21 — Condition Variables, Monitors, Atomic Types

Jeff Zarnett jzarnett@uwaterloo.ca

Department of Electrical and Computer Engineering
University of Waterloo

August 13, 2025

ECE 252 Fall 2022 1/34

### **Condition Variables**



Condition variables are another way to achieve synchronization.

ECE 252 Fall 2022 2/3

#### **Condition Variables**

How do we know if some condition has been fulfilled?

Signal on a semaphore?

Lock mutex, read variable(s), unlock mutex?

Or: a Condition Variable.

ECE 252 Fall 2022 3/34

#### **Condition Variable**

We can think of condition variables as "events" that occur.

What differentiates it: broadcast!

We have the option, when an event occurs, to signal either one thread waiting for that event to occur, or to broadcast (signal) to all threads waiting for the event.

ECE 252 Fall 2022 4/34

#### **Condition Variable Syntax**

```
pthread_cond_init( pthread_cond_t *cv, pthread_condattr_t *attributes );
pthread_cond_wait( pthread_cond_t *cv, pthread_mutex_t *mutex );
pthread_cond_signal( pthread_cond_t *cv );
pthread_cond_broadcast( pthread_cond_t *cv );
pthread_cond_destroy( pthread_cond_t *cv );
```

As with other pthread functions we've seen there are create and destroy calls.

Signal is self-explanatory; but broadcast is new and wait looks weird!

ECE 252 Fall 2022 5/34

#### Wait, in Two Parts

Condition variables are always used in conjunction with a mutex.

pthread\_cond\_wait takes the condition variable and a mutex.

This routine should be called only while the mutex is locked.

It will automatically release the mutex while it waits for the condition!

When the condition is true, then the mutex will be automatically locked again so the thread may proceed.

Then, manually unlock when finished.

ECE 252 Fall 2022 6/34

#### HEY GUYS!!! GUESS WHAT!!!



pthread\_cond\_broadcast signals all threads waiting on that condition variable.

It's this "broadcast" idea that makes the condition variable more interesting than the simple "signalling" pattern we covered much earlier on.

ECE 252 Fall 2022 7/34

#### **Condition Variable Example**

```
#include <pthread.h>
#include < stdio.h>
#include < stdlib .h>
#define NUM THREADS 3
#define COUNT LIMIT 12
int count = 0:
pthread_mutex_t count_mutex:
pthread_cond_t count_threshold_cv;
void* inc_count( void* arg ) {
  for (int i = 0: i < 10: i++) {
    pthread_mutex_lock( &count_mutex );
    count++:
    if ( count == COUNT_LIMIT ) {
      printf( "Condition Fulfilled!\n" );
      pthread_cond_signal( &count_threshold_cv ):
      printf( "Sent_signal.\n" );
    pthread_mutex_unlock( &count_mutex ):
  pthread_exit( NULL ):
```

ECE 252 Fall 2022 8 / 34

### **Condition Variable Example**

```
void* watch_count( void *arg ) {
  pthread_mutex_lock( &count_mutex );
  if ( count < COUNT_LIMIT ) {
    pthread_cond_wait( &count_threshold_cv, &count_mutex );
    printf( "Watcher_has_woken_up.\n" );
    /* Do something useful here now that condition is fulfilled. */
  }
  pthread_mutex_unlock( &count_mutex );
  pthread_exit( NULL );
}</pre>
```

ECE 252 Fall 2022 9 / 34

### **Condition Variable Example**

```
int main( int argc. char **argv ) {
  pthread_t threads[3]:
  pthread_mutex_init( &count_mutex. NULL ):
  pthread_cond_init ( &count_threshold_cv, NULL );
  pthread_create( &threads[0], NULL, watch_count, NULL );
  pthread_create( &threads[1], NULL, inc_count, NULL );
  pthread_create( &threads[2]. NULL. inc_count. NULL ):
  for ( int i = 0; i < NUM_THREADS; i++ ) {</pre>
   pthread_ioin(threads[i]. NULL):
  pthread_mutex_destroy( &count_mutex );
  pthread_cond_destroy( &count_threshold_cv );
  pthread_exit( NULL ):
```

ECE 252 Fall 2022 10 / 34

# **Anybody Listening?**

If a thread signals a condition variable that an event has occurred, but no thread is waiting for that event, the event is "lost".

This is sometimes called the "lost wakeup problem", because threads don't get woken up if they weren't waiting for this.

That's usually an error, but it might be acceptable.

ECE 252 Fall 2022 11/34

## Can We Apply This To What We Know?

The condition variable with broadcast can be used to replace some of the synchronization constructs we've seen already.

What patterns could be replaced?

ECE 252 Fall 2022 12/34

Consider the barrier pattern from earlier.

There are *n* threads and we wait for the last one to arrive.

```
1. wait( mutex )
                                             1. wait( mutex )
2. count++
                                             2. count++
if count == n
                                             3. if count < n
       post( barrier )

    cond_wait( barrier, mutex )

                                             5. else
end if
6. post( mutex )
                                                   cond broadcast( barrier )
7. wait( barrier )
                                             7. end if
8. post( barrier )
                                             8. post( mutex )
```

The wait takes place before the post on mutex. That looks strange, doesn't it?

ECE 252 Fall 2022 13/34

# **Spidey Sense Tingling?**

We give up the mutex lock when we wait on the condition variable.

The fact that we don't get to the unlock statement first does not cause a problem.

So we are alright.

The last thread doesn't wait on the condition at all because there's no need to!

It knows that it is last and there's nothing to wait for so it should proceed.

ECE 252 Fall 2022 14/34

## **Barrier Pattern Code Example**

```
int count;
pthread_mutex_t lock;
pthread_cond_t cv;

void barrier() {
   pthread_mutex_lock( &lock );
   count++;
   if ( count < NUM_THREADS ) {
      pthread_cond_wait( &cv, &lock );
   } else {
      pthread_cond_broadcast( &cv );
   }
   pthread_mutex_unlock( &lock );
}</pre>
```

Will this work?

ECE 252 Fall 2022 15/34

## **Monitors**



Uh... wait... this isn't the right kind.

ECE 252 Fall 2022 16/34

#### What's a Monitor?

A condition variable can be used to create a monitor, a higher level synchronization construct.

This is a bit like in OOP the idea of a class.

When we use a monitor we are packaging up the shared data and operations on that data.

Eliminate the need to write synchronization code ourselves.

ECE 252 Fall 2022 17/34

## Did We Forget Something?

```
void foo() {
  pthread_mutex_lock( &l );
  /* Read some data */
  if ( condition ) {
     printf( "Cannot_continue_due_to_reasons...\n" );
     return;
  }
  /* More stuff */
  pthread_mutex_unlock( &l );
}
```

ECE 252 Fall 2022 18/34

#### **Control Flow Problems**

It looks super obvious in this case, but in real life it's harder to see!

ECE 252 Fall 2022 19/34

The idea of monitors should be familiar to you if you have used Java synchronization constructs, notably the synchronized keyword.

In Java we can declare a method to be synchronized.

There is a lock created around that method. Locking and unlocking is handled automatically.

```
public synchronized void doSomething() {
    // Synchronized area
}
```

ECE 252 Fall 2022 20 / 34

## Synchronized Blocks

in Java one can also define a block as synchronized:

This sort of "automatic" locking and releasing is intended to simplify the process of writing multithreaded code.

ECE 252 Fall 2022 21/34

### This isn't an endorsement of Java...

Monitors don't have to be written in Java (or similar).

They do frequently appear in Object-Oriented languages because the concepts are familiar enough.

ECE 252 Fall 2022 22 / 34

## **Atomic Types**




Image Credit: Wikipedia user JabberWok

A testament to how good humans are at blowing things up...

ECE 252 Fall 2022 23/34

Frequently we have a code pattern that looks something like this:

```
pthread_mutex_lock( lock );
shared_var++;
pthread_mutex_unlock( lock );
```

It seems like a lot of work to lock and unlock the mutex, no?

Thinking back to the "test and set" type of instruction from earlier, wouldn't it be nice if we could do that sort of thing for something like incrementing a variable?

ECE 252 Fall 2022 24/34

## Hey glibc, Could You Please...

The GNU (Linux) standard C library (glibc) provides operations that are guaranteed to execute atomically, to avoid simple race conditions

Where possible, the compiler will try to turn these into uninterruptible hardware instructions.

Otherwise a function that has locking will be used to implement the atomic nature.

ECE 252 Fall 2022 25 / 34

#### You Can't Take It With You

These are, however, glib specific, and not necessarily available or portable.

In the C11 (2011) standard, atomic types were finally introduced as part of the language specification.

In the specification, we see type as the type.

In its place you would use an int for an integer.

A valid type is one that 1, 2, 4, or 8 bytes in length (integral or pointer).

ECE 252 Fall 2022 26/34

## **Atomic Operations**

#### To set a value:

```
type __sync_lock_test_and_set( type *ptr, type value );
```

The following functions are used to swap two values, only if the old value matches the expected (i.e., what was provided as the second argument):

```
bool __sync_bool_compare_and_swap( type *ptr, type oldval, type newval ); type __sync_val_compare_and_swap( type *ptr, type oldval, type newval );
```

ECE 252 Fall 2022 27 / 34

#### The following functions perform the operation and return the *old* value:

```
type __sync_fetch_and_add( type *ptr, type value );
type __sync_fetch_and_sub( type *ptr, type value );
type __sync_fetch_and_or( type *ptr, type value );
type __sync_fetch_and_and( type *ptr, type value );
type __sync_fetch_and_xor( type *ptr, type value );
type __sync_fetch_and_nand( type *ptr, type value );
```

#### The following functions perform the operation and return the new value:

```
type __sync_add_and_fetch( type *ptr, type value );
type __sync_sub_and_fetch( type *ptr, type value );
type __sync_or_and_fetch( type *ptr, type value );
type __sync_and_and_fetch( type *ptr, type value );
type __sync_xor_and_fetch( type *ptr, type value );
type __sync_nand_and_fetch( type *ptr, type value );
```

ECE 252 Fall 2022 28 / 34

## Reading is... Fun?

Interestingly, for x86 there is no atomic read operation.

The (normal) read itself is atomic for 32-bit-aligned data.

This behaviour is specific to x86 and we try to avoid that.

If we do rely on this, however, we could get an out-of-date value.

If you want to really be sure you did get the latest, you can use one of the above functions and add or subtract 0.

ECE 252 Fall 2022 29/34

## **Use Tool Appropriately**

```
struct point {
   volatile int x;
   volatile int y;
};
__sync_lock_test_and_set( pl->x, 0 );
__sync_lock_test_and_set( pl->y, 0 );

/* Somewhere else in the program */
__sync_lock_test_and_set( pl->x, 25 );
__sync_lock_test_and_set( pl->y, 30 );
```

Does this work?

ECE 252 Fall 2022 30 / 34

# **Use Tool Appropriately**

Although the set of each of x and y is atomic, the operation as a whole is not.

We could see invalid states, like (25, 0) or (0, 30).

ECE 252 Fall 2022 31/34

## You Spin Me Right Round...

Another common technique for protecting a critical section in Linux is the *spinlock*.

This is a handy way to implement constant checking to acquire a lock.

Unlike semaphores where the process is blocked if it fails to acquire the lock, a thread will constantly try to acquire the lock.

When would we want this behaviour?

ECE 252 Fall 2022 32 / 34

#### When It's Worth It!

It would be better to let another thread execute.

Except when the amount of time waiting on the lock might be small.

Specifically, less than it would take to block the process, switch to another, and unblock it when the value changes.

ECE 252 Fall 2022 33/34

```
spin_lock( &lock )
  /* Critical Section */
spin_unlock( &lock )
```

In addition to the regular spinlock, there are reader-writer-spinlocks.

Like the readers-writers problem discussed earlier, the goal is to allow multiple readers but give exclusive access to a writer.

Counter	Flag	Interpretation
0	1	The spinlock is released and available.
0	0	The spinlock has been acquired for writing.
n (n > 0)	0	The spin lock has been acquired for reading by <i>n</i> threads.
n (n > 0)	1	Invalid state.

ECE 252 Fall 2022 34/34