Stedi maintains this guide based on public documentation from X12 HIPAA. Contact X12 HIPAA for official EDI specifications. To report any errors in this guide, please **contact us**.

Go to Stedi Network

X12 HIPAA

X12 999 Implementation Acknowledgment (X231)

X12 Release 5010 Revised June 5, 2024

This X12 Transaction Set contains the format and establishes the data contents of the Implementation Acknowledgment Transaction Set (999) for use within the context of an Electronic Data Interchange (EDI) environment. The transaction set can be used to define the control structures for a set of acknowledgments to indicate the results of the syntactical and relational analysis of the electronically encoded documents, based upon a full or implemented subset of X12 transaction sets. The encoded documents are the transaction sets, which are grouped in functional groups, used in defining transactions for business data interchange. This standard does not cover the semantic meaning of the information encoded in the transaction sets.

Delimiters ~ Segment * Element > Component ^ Repetition

View the latest version of this implementation guide as an interactive webpage
https://www.stedi.com/app/guides/view/hipaa/implementation-acknowledgment-x231/01HRF41ES1DVGCA6X1EHSRPFXZ

POWERED BY stedi

Build EDI implementation guides at **stedi.com**

Overview

ISA	-	Interchange Control Header	Max use 1	Required
GS	-	Functional Group Header	Max use 1	Required

Heading

ST	0100	Transaction Set Header	Max use 1	Required
AK1	0200	Functional Group Response Header	Max use 1	Required

Transaction Set Response Header Loop

AK2	0300	Transaction Set Response Header	Max use 1	Required

Error Identification Loop

IK3	0400	Error Identification	Max use 1	Required
CTX	0500	Segment Context	Max use 9	Optional
CTX	0500	Business Unit Identifier	Max use 1	Optional

Implementation Data Element Note Loop

IK4	0600	Implementation Data Element Note	Max use 1	Required
CTX	0700	Element Context	Max use 10	Optional

IK5	0800	Transaction Set Response Trailer	Max use 1	Required
AK9	0900	Functional Group Response Trailer	Max use 1	Required
SE	1000	Transaction Set Trailer	Max use 1	Required
GE	-	Functional Group Trailer	Max use 1	Required
IEA	-	Interchange Control Trailer	Max use 1	Required

ISA

Max use 1 Required

Interchange Control Header

To start and identify an interchange of zero or more functional groups and interchange-related control segments

Example

```
ISA*00*          *00*          *XX*XXXXXXXXXXXXXX
X*XX*XXXXXXXXXXXXXXX*240925*1626*^*00501*00000000
0*X*X*>~
```

ISA-01 **I01 Authorization Information Qualifier** Identifier (ID) Required

Code identifying the type of information in the Authorization Information

00 No Authorization Information Present (No Meaningful Information in I02)

ISA-02 **I02 Authorization Information** Min 10 Max 10 String (AN) Required

Information used for additional identification or authorization of the interchange sender or the data in the interchange; the type of information is set by the Authorization Information Qualifier (I01)

ISA-03 **I03 Security Information Qualifier** Identifier (ID) Required

Code identifying the type of information in the Security Information

00 No Security Information Present (No Meaningful Information in I04)

ISA-04 **I04 Security Information** Min 10 Max 10 String (AN) Required

This is used for identifying the security information about the interchange sender or the data in the interchange; the type of information is set by the Security Information Qualifier (I03)

ISA-05 **I05 Interchange ID Qualifier** Min 2 Max 2 Identifier (ID) Required

Code indicating the system/method of code structure used to designate the sender or receiver ID element being qualified

› Codes

ISA-06 **I06 Interchange Sender ID** Min 15 Max 15 String (AN) Required

Identification code published by the sender for other parties to use as the receiver ID to route data to them; the sender always codes this value in the sender ID element

ISA-07 **I05 Interchange ID Qualifier** Min 2 Max 2 Identifier (ID) Required

Code indicating the system/method of code structure used to designate the sender or receiver ID element being qualified

› Codes

ISA-08 **I07 Interchange Receiver ID** Min 15 Max 15 String (AN) Required

Identification code published by the receiver of the data; When sending, it is used by the sender as their sending ID, thus other parties sending to them will use this as a receiving ID to route data to them

ISA-09 **I08 Interchange Date** YYMMDD format Date (DT) Required

Date of the interchange

ISA-10 **I09 Interchange Time** HHMM format Time (TM) Required

Time of the interchange

ISA-11 **I65 Repetition Separator** Min 1 Max 1 String (AN) Required

Type is not applicable; the repetition separator is a delimiter and not a data element; this field provides the delimiter used to separate repeated occurrences of a simple data element or a composite data structure; this value must be different than the data element separator, component element separator, and the segment terminator

^ Repetition Separator

ISA-12 **I11 Interchange Control Version Number** Identifier (ID) Required

Code specifying the version number of the interchange control segments

00501 Standards Approved for Publication by ASC X12 Procedures Review Board through October 2003

ISA-13 **I12 Interchange Control Number** Min 9 Max 9 # Numeric (N0) Required

A control number assigned by the interchange sender

ISA-14 **I13 Acknowledgment Requested** Min 1 Max 1 Identifier (ID) Required

Code indicating sender's request for an interchange acknowledgment

0 No Interchange Acknowledgment Requested
1 Interchange Acknowledgment Requested (TA1)

ISA-15 **I14 Interchange Usage Indicator** Min 1 Max 1 **Identifier (ID)** Required

Code indicating whether data enclosed by this interchange envelope is test, production or information

I Information
P Production Data
T Test Data

ISA-16 **I15 Component Element Separator** Min 1 Max 1 **String (AN)** Required

Type is not applicable; the component element separator is a delimiter and not a data element; this field provides the delimiter used to separate component data elements within a composite data structure; this value must be different than the data element separator and the segment terminator

> Component Element Separator

GS

Max use 1 Required

Functional Group Header

To indicate the beginning of a functional group and to provide control information

Example

```
GS*FA*XXXXXX*XXXXXXX*20240925*1257*000000000*XX*0
05010X231~
```

GS-01 **479 Functional Identifier Code** Identifier (ID) Required

Code identifying a group of application related transaction sets

FA Functional or Implementation Acknowledgment Transaction Sets (997, 999)

GS-02 **142 Application Sender's Code** Min 2 Max 15 String (AN) Required

Code identifying party sending transmission; codes agreed to by trading partners

GS-03 **124 Application Receiver's Code** Min 2 Max 15 String (AN) Required

Code identifying party receiving transmission; codes agreed to by trading partners

GS-04 **373 Date** CCYYMMDD format Date (DT) Required

Date expressed as CCYYMMDD where CC represents the first two digits of the calendar year

GS-05 **337 Time** HHMM, HHMMSS, HHMMSSD, or HHMMSSDD format Time (TM) Required

Time expressed in 24-hour clock time as follows: HHMM, or HHMMSS, or HHMMSSD, or HHMMSSDD, where H = hours (00-23), M = minutes (00-59), S = integer seconds (00-59) and DD = decimal seconds; decimal seconds are expressed as follows: D = tenths (0-9) and DD = hundredths (00-99)

GS-06 **28 Group Control Number** Min 1 Max 9 # Numeric (N0) Required

Assigned number originated and maintained by the sender

GS-07 **455 Responsible Agency Code** Min 1 Max 2 Identifier (ID) Required

Code identifying the issuer of the standard; this code is used in conjunction with Data Element 480

T Transportation Data Coordinating Committee (TDCC)

X Accredited Standards Committee X12

GS-08

480 Version / Release / Industry Identifier Code

T String (AN) Required

Code indicating the version, release, subrelease, and industry identifier of the EDI standard being used, including the GS and GE segments; if code in DE455 in GS segment is X, then in DE 480 positions 1-3 are the version number; positions 4-6 are the release and subrelease, level of the version; and positions 7-12 are the industry or trade association identifiers (optionally assigned by user); if code in DE455 in GS segment is T, then other formats are allowed

005010X231

Heading

ST 0100 Heading > ST Max use 1 Required

Transaction Set Header

To indicate the start of a transaction set and to assign a control number

Usage notes

- When acknowledging a healthcare implementation guide (TR3) based transaction, only a single transaction set 999 can be used. When acknowledging a healthcare implementation guide (TR3) based transaction, the transaction set 997 must not be used.

Example

```
ST*999*0001*005010X231~
```

ST-01 **143 Transaction Set Identifier Code** Identifier (ID) Required

Code uniquely identifying a Transaction Set

- The transaction set identifier (ST01) is used by the translation routines of the interchange partners to select the appropriate transaction set definition (e.g., 810 selects the Invoice Transaction Set).

999 Implementation Acknowledgment

ST-02 **329 Transaction Set Control Number** Min 4 Max 9 # Numeric (N) Required

Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set

Usage notes

- The Transaction Set Control Numbers in ST02 and SE02 must be identical. The number is assigned by the originator and must be unique within a functional group (GS-GE). The number also aids in error resolution research. For example, start with the number 0001 and increment from there.

ST-03 **1705 Implementation Convention Reference** String (AN) Required

Reference assigned to identify Implementation Convention

- The implementation convention reference (ST03) is used by the translation routines of the interchange partners to select the appropriate implementation convention to match the transaction set definition. When used, this implementation convention reference takes precedence over the implementation reference specified in the GS08.

Usage notes

- This field contains the same value as data element GS08. This value is always 005010X231 when this implementation guide is utilized. Some translator products strip off the ISA and GS segments prior to application processing. Providing the information

from GS08 at this level will help ensure the appropriate application mapping is utilized at translation time.

005010X231

AK1 0200 Heading > AK1 Max use 1 Required

Functional Group Response Header

To start acknowledgment of a functional group

Example

AK1*XX*0000000*XXXXXX~

AK1-01 **479 Functional Identifier Code** Min 2 Max 2 Identifier (ID) Required

Code identifying a group of application related transaction sets

- AK101 is the functional ID found in the GS segment (GS01) in the functional group being acknowledged.

Usage notes

- Use the value in GS01 from the functional group to which this 999 transaction set is responding.

AK1-02 **28 Group Control Number** Min 1 Max 9 # Numeric (N0) Required

Assigned number originated and maintained by the sender

- AK102 is the functional group control number found in the GS segment in the functional group being acknowledged.

Usage notes

- Use the value in GS06 from the functional group to which this 999 transaction set is responding.

AK1-03 **480 Version, Release, or Industry Identifier Code** String (AN) Required Min 1 Max 12

Code indicating the version, release, subrelease, and industry identifier of the EDI standard being used, including the GS and GE segments; if code in DE455 in GS segment is X, then in DE 480 positions 1-3 are the version number; positions 4-6 are the release and subrelease, level of the version; and positions 7-12 are the industry or trade association identifiers (optionally assigned by user); if code in DE455 in GS segment is T, then other formats are allowed

- AK103 is the version release industry identifier code in the GS segment (GS08) in the functional group being acknowledged.

Usage notes

- Use the value in GS08 from the functional group to which this 999 transaction set is responding.

2000 Transaction Set Response Header Loop

Max >1 Optional

AK2 0300 Heading > Transaction Set Response Header Loop > AK2

Max use 1 Required

Transaction Set Response Header

To start acknowledgment of a single transaction set

Usage notes

- Required when an error is present in a transaction set contained in the functional group to which this 999 transaction set is responding. If not required by this implementation guide, may be provided at the sender's discretion but cannot be required by the receiver.
- While it is not required that an AK2 loop be included for each transaction set received, it is required that an AK2 loop be included for each transaction set that contains an error. When AK2 loops are included in this transaction set, they must be in the same order as received in the functional group to which this 999 is responding.

Example

```
AK2*XXX*0001*005010X221A1~
```

AK2-01 143 Transaction Set Identifier Code

Min 3 Max 3 Identifier (ID) Required

Code uniquely identifying a Transaction Set

- AK201 is the transaction set ID found in the ST segment (ST01) in the transaction set being acknowledged.

Usage notes

- Use the value in ST01 from the transaction set to which this 999 transaction set is responding.

AK2-02 329 Transaction Set Control Number

Min 4 Max 9 # Numeric (N) Required

Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set

- AK202 is the transaction set control number found in the ST segment in the transaction set being acknowledged.

Usage notes

- Use the value in ST02 from the transaction set to which this 999 transaction set is responding.

AK2-03 1705 Implementation Convention Reference

Min 1 Max 35 T String (AN) Optional

Reference assigned to identify Implementation Convention

- AK203 is the implementation convention reference, if any, found in the ST segment (ST03) in the transaction set being acknowledged.

Usage notes

- When used, this is the value in ST03 from the transaction set to which this 999 transaction set is responding.

2100 Error Identification Loop

Max >1 Optional

IK3 0400 Heading > Transaction Set Response Header Loop > Error Identification Loop > IK3 Max use 1 Required

Error Identification

To report implementation errors in a data segment and identify the location of the data segment

Usage notes

- Required when an error is present in the transaction set identified in this AK2 loop and the location of the data segment containing the error can be identified by the submitter of this 999. If not required by this implementation guideline, do not send.

Example

IK3*XX*000*XX*8~

IK3-01 721 Segment ID Code

Min 2 Max 3 Identifier (ID) Required

Code defining the segment ID of the data segment in error (See Appendix A - Number 77)

IK3-02 719 Segment Position in Transaction Set

Min 1 Max 10 # Numeric (N0) Required

The numerical count position of this data segment from the start of the transaction set: the transaction set header is count position 1

Usage notes

- The value to use in IK302 is the numerical count position of this data segment, relative to the transaction set instance (not the transaction set diagram), from the start of the transaction set. The transaction set header (i.e. ST) is count position 1.

IK3-03 447 Loop Identifier Code

Min 1 Max 4 String (AN) Optional

The loop ID number given on the transaction set diagram is the value for this data element in segments LS and LE

Usage notes

- Only the first four characters of the loop identifier must be used.

IK3-04 620 Implementation Segment Syntax Error Code

Identifier (ID) Required

Code indicating implementation error found based on the syntax editing of a segment

1 Unrecognized segment ID
2 Unexpected segment
3 Required Segment Missing
4 Loop Occurs Over Maximum Times

- **5** Segment Exceeds Maximum Use
- **6** Segment Not in Defined Transaction Set
- **7** Segment Not in Proper Sequence
- **8** Segment Has Data Element Errors
- **I4** Implementation "Not Used" Segment Present
- **I6** Implementation Dependent Segment Missing
- **I7** Implementation Loop Occurs Under Minimum Times
- **I8** Implementation Segment Below Minimum Use
- **I9** Implementation Dependent "Not Used" Segment Present

CTX 0500 Heading > Transaction Set Response Header Loop > Error Identification Loop > CTX Max use 9 Optional

Segment Context

Describes an event context in terms of the application or implementation contexts in force at the time the event occurred and the position in the EDI stream at which that context was activated

Usage notes

- Required when the error identified in this IK3 loop was triggered by a situational requirement of the implementation guide and the error occurs at the segment level. If not required by this implementation guide, do not send.
- The CTX segment is used to identify the data that triggered the situational requirement.

Example

```
CTX*XXXX*XX*000*XX*0>0>0*000~
```

Variants (all may be used)
CTX Business Unit Identifier

CTX-01 C998 Context Identification

Holds information to identify a context

Max use 10 Required

C998-01 9999 Context Name

Min 1 Max 35 String (AN) Required

Holds the name or 'tag' of a context

Usage notes

- Always contains the value "SITUATIONAL TRIGGER".

CTX-02 721 Segment ID Code

Min 2 Max 3 Identifier (ID) Required

Code defining the segment ID of the data segment in error (See Appendix A - Number 77)

CTX-03 719 Segment Position in Transaction Set

Min 1 Max 10 # Numeric (N0) Required

The numerical count position of this data segment from the start of the transaction set: the transaction set header is count position 1

CTX-04 447 Loop Identifier Code

Min 1 Max 4 String (AN) Optional

The loop ID number given on the transaction set diagram is the value for this data element in segments LS and LE

Usage notes

- Only the first four characters of the loop identifier must be used.

CTX-05 **C030 Position in Segment**

Max use 1 Optional

Code indicating the relative position of the simple data element or composite data structure in error within a segment, count beginning with 1 for the position immediately following the segment ID; additionally indicating the relative position of a repeating structure in error, count beginning with 1 for the position immediately following the preceding element separator; additionally indicating the relative position of a component of a composite data structure in error, count beginning with 1 for the position following the preceding element or repetition separator

Usage notes

Required when the situational requirement relates to an element. If not required by this implementation guide, do not send.

C030-01 **722 Element Position in Segment** Min 1 Max 2 # Numeric (N0) Required

This is used to indicate the relative position of a simple data element, or the relative position of a composite data structure with the relative position of the component within the composite data structure, in error; in the data segment the count starts with 1 for the simple data element or composite data structure immediately following the segment ID

C030-02 **1528 Component Data Element Position in Composite** # Numeric (N0) Optional Min 1 Max 2

To identify the component data element position within the composite that is in error

C030-03 **1686 Repeating Data Element Position** Min 1 Max 4 # Numeric (N0) Optional

To identify the specific repetition of a data element that is in error

CTX-06 **C999 Reference in Segment**

Max use 1 Optional

To hold the reference number of a data element and optionally a component data element within a composite

Usage notes

Required when CTX05 is used and the data element reference number of the data element identified in CTX05-1 is known by the sumbitter of the 999, and it is NOT a composite data element. If not required by this implementation guide, do not send.

C999-01 **725 Data Element Reference Number** Min 1 Max 4 # Numeric (N0) Required

Reference number used to locate the data element in the Data Element Dictionary

- This element holds the reference number of the simple or composite element at segment level.

CTX 0500 Heading > Transaction Set Response Header Loop > Error Identification Loop > CTX Max use 1 Optional

Business Unit Identifier

Describes an event context in terms of the application or implementation contexts in force at the time the event occurred and the position in the EDI stream at which that context was activated

Usage notes

- Required when the error reported in this IK3 loop is within a business unit and the business unit identifier is known by the submitter of the 999. If not required by this implementation guide, do not send.
- Valid values for the business unit identifier are:
  TRN02 269 business unit identifier
  TRN02 270 business unit identifier
  TRN02 271 business unit identifier
  NM109 274 business unit identifier
  PATIENT NAME NM109 275 business unit identifier
  TRN02 276 business unit identifier
  TRN02 277 business unit identifier
  SUBSCRIBER NAME NM109 278 business unit identifier
  ENT01 820 business unit identifier
  SUBSCRIBER NUMBER REF02 834 business unit identifier
  TRN02 835 business unit identifier
  CLM01 837 business unit identifier

Example

```
CTX*XXXXX>XXXXX~
```

Variants (all may be used)
CTX Segment Context

CTX-01 **C998 Context Identification**
Holds information to identify a context
Max use 10 Required

C998-01 **9999 Context Name**
Min 1 Max 35 String (AN) Required

Holds the name or 'tag' of a context

Usage notes

- This contains one of the following values, depending on the value in AK201:
  TRN02 269 business unit identifier
  TRN02 270 business unit identifier
  TRN02 271 business unit identifier
  NM109 274 business unit identifier
  PATIENT NAME NM109 275 business unit identifier
  TRN02 276 business unit identifier
  TRN02 277 business unit identifier
  SUBSCRIBER NAME NM109 278 business unit identifier
  ENT01 820 business unit identifier
  SUBSCRIBER NUMBER REF02 834 business unit identifier

TRN02 835 business unit identifier
CLM01 837 business unit identifier

C998-02 9998 Context Reference

Min 1 Max 35 String (AN) Required

Holds a reference to or for a context

Usage notes

- This contains the value from the business unit identifier specified in CTX01-1.

2110 Implementation Data Element Note Loop

Max >1 Optional

IK4 0600 Heading > Transaction Set Response Header Loop > Error Identification Loop > Implementation Data Element Note Loop > IK4 Max use 1 Required

Implementation Data Element Note

To report implementation errors in a data element or composite data structure and identify the location of the data element

Usage notes

- Required when the error in the segment described in the IK3 segment applies to a data element and the location of the data element containing the error can be identified by the submitter of the 999. If not required by this implementation guideline, do not send.

Example

```
IK4*0>00>0*00*I6*XXXXX~
```

IK4-01 **C030 Position in Segment** Max use 1 Required

Code indicating the relative position of the simple data element or composite data structure in error within a segment, count beginning with 1 for the position immediately following the segment ID; additionally indicating the relative position of a repeating structure in error, count beginning with 1 for the position immediately following the preceding element separator; additionally indicating the relative position of a component of a composite data structure in error, count beginning with 1 for the position following the preceding element or repetition separator

C030-01 **722 Element Position in Segment** Min 1 Max 2 # Numeric (N0) Required

This is used to indicate the relative position of a simple data element, or the relative position of a composite data structure with the relative position of the component within the composite data structure, in error; in the data segment the count starts with 1 for the simple data element or composite data structure immediately following the segment ID

C030-02 **1528 Component Data Element Position in Composite** # Numeric (N0) Optional Min 1 Max 2

To identify the component data element position within the composite that is in error

C030-03 **1686 Repeating Data Element Position** Min 1 Max 4 # Numeric (N0) Optional

To identify the specific repetition of a data element that is in error

IK4-02 **725 Data Element Reference Number** Min 1 Max 4 # Numeric (N0) Optional

Reference number used to locate the data element in the Data Element Dictionary

IK4-03

621 Implementation Data Element Syntax Error Code

Identifier (ID) Required

Code indicating the implementation error found after syntax edits of a data element

1	Required Data Element Missing
2	Conditional Required Data Element Missing
3	Too Many Data Elements
4	Data Element Too Short
5	Data Element Too Long
6	Invalid Character In Data Element
7	Invalid Code Value
8	Invalid Date
9	Invalid Time
10	Exclusion Condition Violated
12	Too Many Repetitions
13	Too Many Components
I10	Implementation "Not Used" Data Element Present
I11	Implementation Too Few Repetitions
I12	Implementation Pattern Match Failure
I13	Implementation Dependent "Not Used" Data Element Present
I6	Code Value Not Used in Implementation
I9	Implementation Dependent Data Element Missing

IK4-04

724 Copy of Bad Data Element

Min 1 Max 99 String (AN) Optional

This is a copy of the data element in error

CTX 0700 Heading > Transaction Set Response Header Loop > Error Identification Loop > Implementation Data Element Note Loop > CTX

Max use 10 Optional

Element Context

Describes an event context in terms of the application or implementation contexts in force at the time the event occurred and the position in the EDI stream at which that context was activated

Usage notes

- Required when the error identified in this IK4 loop was triggered by a situational requirement of the implementation guide and the error occurs at the element level. If not required by this implementation guide, do not send.
- The CTX segment is used to identify the data that triggered the situational requirement.

Example

```
CTX*X*XXX*0*XXXX*0>0>00*00~
```

CTX-01 C998 Context Identification

Holds information to identify a context

Max use 10 Required

C998-01 9999 Context Name

Min 1 Max 35 String (AN) Required

Holds the name or 'tag' of a context

Usage notes

- Always contains the value "SITUATIONAL TRIGGER".

CTX-02 721 Segment ID Code

Min 2 Max 3 Identifier (ID) Required

Code defining the segment ID of the data segment in error (See Appendix A - Number 77)

CTX-03 719 Segment Position in Transaction Set

Min 1 Max 10 # Numeric (N0) Required

The numerical count position of this data segment from the start of the transaction set: the transaction set header is count position 1

CTX-04 447 Loop Identifier Code

Min 1 Max 4 String (AN) Optional

The loop ID number given on the transaction set diagram is the value for this data element in segments LS and LE

Usage notes

- Only the first four characters of the loop identifier must be used.

CTX-05 C030 Position in Segment

Code indicating the relative position of the simple data element or composite data structure in error within a segment, count beginning with 1 for the position immediately following the segment ID; additionally indicating the relative position of a repeating structure in error, count beginning with 1 for the position immediately following the preceding element separator; additionally indicating the relative position of a component of a composite data structure in error, count beginning with 1 for the position following the preceding element or repetition separator

Max use 1 Optional

Usage notes

Required when the situational requirement relates to an element. If not required by this implementation guide, do not send.

C030-01 **722 Element Position in Segment** Min 1 Max 2 # Numeric (N0) Required

This is used to indicate the relative position of a simple data element, or the relative position of a composite data structure with the relative position of the component within the composite data structure, in error; in the data segment the count starts with 1 for the simple data element or composite data structure immediately following the segment ID

C030-02 **1528 Component Data Element Position in Composite** # Numeric (N0) Optional Min 1 Max 2

To identify the component data element position within the composite that is in error

C030-03 **1686 Repeating Data Element Position** Min 1 Max 4 # Numeric (N0) Optional

To identify the specific repetition of a data element that is in error

CTX-06 **C999 Reference in Segment**

To hold the reference number of a data element and optionally a component data element within a composite

Max use 1 Optional

Usage notes

Required when CTX05 is used and the data element reference number of the data element identified in CTX05-1 is known by the sumbitter of the 999, and it is NOT a composite data element. If not required by this implementation guide, do not send.

C999-01 **725 Data Element Reference Number** Min 1 Max 4 # Numeric (N0) Required

Reference number used to locate the data element in the Data Element Dictionary

- This element holds the reference number of the simple or composite element at segment level.

2110 Implementation Data Element Note Loop end

2100 Error Identification Loop end

IK5 0800 Heading > Transaction Set Response Header Loop > IK5 Max use 1 Required

Transaction Set Response Trailer

To acknowledge acceptance or rejection and report implementation errors in a transaction set

Example

```
IK5*R*7*XXX*XXX*X*XX~
```

IK5-01 717 Transaction Set Acknowledgment Code

Identifier (ID) Required

Code indicating accept or reject condition based on the syntax editing of the transaction set

- **A** Accepted
- **E** Accepted But Errors Were Noted
  - The transaction set indicated in this AK2 loop contained errors, but was forwarded for further processing.
- **M** Rejected, Message Authentication Code (MAC) Failed
- **R** Rejected
  - The transaction set indicated in this AK2 loop contained errors, and was NOT forwarded for further processing. It will need to be corrected and resubmitted.
- **W** Rejected, Assurance Failed Validity Tests
- **X** Rejected, Content After Decryption Could Not Be Analyzed

IK5-02 618 Implementation Transaction Set Syntax Error Code

Identifier (ID) Optional

Code indicating implementation error found based on the syntax editing of a transaction set

- **1** Transaction Set Not Supported
- **2** Transaction Set Trailer Missing
- **3** Transaction Set Control Number in Header and Trailer Do Not Match
- **4** Number of Included Segments Does Not Match Actual Count
- **5** One or More Segments in Error
- **6** Missing or Invalid Transaction Set Identifier
- **7** Missing or Invalid Transaction Set Control Number
- **8** Authentication Key Name Unknown
- **9** Encryption Key Name Unknown
- **10** Requested Service (Authentication or Encrypted) Not Available
- **11** Unknown Security Recipient
- **12** Incorrect Message Length (Encryption Only)
- **13** Message Authentication Code Failed
- **15** Unknown Security Originator
- **16** Syntax Error in Decrypted Text
- **17** Security Not Supported
- **18** Transaction Set not in Functional Group
- **19** Invalid Transaction Set Implementation Convention Reference
- **23** Transaction Set Control Number Not Unique within the Functional Group
- **24** S3E Security End Segment Missing for S3S Security Start Segment

25 S3S Security Start Segment Missing for S3E Security End Segment
26 S4E Security End Segment Missing for S4S Security Start Segment
27 S4S Security Start Segment Missing for S4E Security End Segment
I5 Implementation One or More Segments in Error
I6 Implementation Convention Not Supported

IK5-03 **618 Implementation Transaction Set Syntax Error Code**

Identifier (ID) Optional
Min 1 Max 3

Code indicating implementation error found based on the syntax editing of a transaction set

IK5-04 **618 Implementation Transaction Set Syntax Error Code**

Identifier (ID) Optional
Min 1 Max 3

Code indicating implementation error found based on the syntax editing of a transaction set

IK5-05 **618 Implementation Transaction Set Syntax Error Code**

Identifier (ID) Optional
Min 1 Max 3

Code indicating implementation error found based on the syntax editing of a transaction set

IK5-06 **618 Implementation Transaction Set Syntax Error Code**

Identifier (ID) Optional
Min 1 Max 3

Code indicating implementation error found based on the syntax editing of a transaction set

2000 Transaction Set Response Header Loop end

AK9 0900 Heading > AK9 Max use 1 Required

Functional Group Response Trailer

To acknowledge acceptance or rejection of a functional group and report the number of included transaction sets from the original trailer, the accepted sets, and the received sets in this functional group

Example

```
AK9*E*000000*0000*00*17*XXX*XXX*XXX*XX~
```

AK9-01 715 Functional Group Acknowledge Code

Identifier (ID) Required

Code indicating accept or reject condition based on the syntax editing of the functional group

- If AK901 contains the value "A" or "E", then the transmitted functional group is accepted.

A Accepted
- This code value can only be used if there are no AK2 loops or all IK501 values = `A'.

E Accepted, But Errors Were Noted.
- The functional group indicated in this 999 contained errors, but was forwarded for further processing.

M Rejected, Message Authentication Code (MAC) Failed

P Partially Accepted, At Least One Transaction Set Was Rejected

R Rejected
- The functional group indicated in this 999 contained errors, and was NOT forwarded for further processing. It will need to be corrected and resubmitted.

W Rejected, Assurance Failed Validity Tests

X Rejected, Content After Decryption Could Not Be Analyzed

AK9-02 97 Number of Transaction Sets Included

Min 1 Max 6 # Numeric (N0) Required

Total number of transaction sets included in the functional group or interchange (transmission) group terminated by the trailer containing this data element

AK9-03 123 Number of Received Transaction Sets

Min 1 Max 6 # Numeric (N0) Required

Number of Transaction Sets received

AK9-04 2 Number of Accepted Transaction Sets

Min 1 Max 6 # Numeric (N0) Required

Number of accepted Transaction Sets in a Functional Group

AK9-05 716 Functional Group Syntax Error Code

Identifier (ID) Optional

Code indicating error found based on the syntax editing of the functional group header and/or trailer

1 Functional Group Not Supported
2 Functional Group Version Not Supported
3 Functional Group Trailer Missing
4 Group Control Number in the Functional Group Header and Trailer Do Not Agree
5 Number of Included Transaction Sets Does Not Match Actual Count
6 Group Control Number Violates Syntax
10 Authentication Key Name Unknown
11 Encryption Key Name Unknown
12 Requested Service (Authentication or Encryption) Not Available
13 Unknown Security Recipient
14 Unknown Security Originator
15 Syntax Error in Decrypted Text
16 Security Not Supported
17 Incorrect Message Length (Encryption Only)
18 Message Authentication Code Failed
19 Functional Group Control Number not Unique within Interchange
23 S3E Security End Segment Missing for S3S Security Start Segment
24 S3S Security Start Segment Missing for S3E End Segment
25 S4E Security End Segment Missing for S4S Security Start Segment
26 S4S Security Start Segment Missing for S4E Security End Segment

AK9-06 **716 Functional Group Syntax Error Code** Min 1 Max 3 Identifier (ID) Optional

Code indicating error found based on the syntax editing of the functional group header and/or trailer

AK9-07 **716 Functional Group Syntax Error Code** Min 1 Max 3 Identifier (ID) Optional

Code indicating error found based on the syntax editing of the functional group header and/or trailer

AK9-08 **716 Functional Group Syntax Error Code** Min 1 Max 3 Identifier (ID) Optional

Code indicating error found based on the syntax editing of the functional group header and/or trailer

AK9-09 **716 Functional Group Syntax Error Code** Min 1 Max 3 Identifier (ID) Optional

Code indicating error found based on the syntax editing of the functional group header and/or trailer

SE 1000 Heading > SE

Max use 1 Required

Transaction Set Trailer

To indicate the end of the transaction set and provide the count of the transmitted segments (including the beginning (ST) and ending (SE) segments)

Example

```
SE*0000000000*0001~
```

SE-01 **96 Number of Included Segments** Min 1 Max 10 # Numeric (N0) Required

Total number of segments included in a transaction set including ST and SE segments

SE-02 **329 Transaction Set Control Number** Min 4 Max 9 # Numeric (N) Required

Identifying control number that must be unique within the transaction set functional group assigned by the originator for a transaction set

Usage notes

- The Transaction Set Control Numbers in ST02 and SE02 must be identical. The number is assigned by the originator and must be unique within a functional group (GS-GE). The number also aids in error resolution research. For example, start with the number 0001 and increment from there.

Heading end

GE

Max use 1 Required

Functional Group Trailer

To indicate the end of a functional group and to provide control information

Example

```
GE*0*00~
```

GE-01 **97 Number of Transaction Sets Included** Min 1 Max 6 # Numeric (N0) Required

Total number of transaction sets included in the functional group or interchange (transmission) group terminated by the trailer containing this data element

GE-02 **28 Group Control Number** Min 1 Max 9 # Numeric (N0) Required

Assigned number originated and maintained by the sender

IEA Max use 1 Required

Interchange Control Trailer

To define the end of an interchange of zero or more functional groups and interchange-related control segments

Example

```
IEA*00*000000000~
```

IEA-01 **I16 Number of Included Functional Groups** Min 1 Max 5 # Numeric (N0) Required

A count of the number of functional groups included in an interchange

IEA-02 **I12 Interchange Control Number** Min 9 Max 9 # Numeric (N0) Required

A control number assigned by the interchange sender

EDI Samples

Example 1: Response to a Functional Group Containing Three 837s

```
ISA*00* *00*
*ZZ*123456789012345*ZZ*123456789012346*080503*1705*^*00501*000010216*0*T*>~
GS*FA*1234567890*2345678901*20080503*1705*20213*X*005010X231~
ST*999*2870001*005010X231~
AK1*HC*17456*005010X222A2~
AK2*837*0001~
IK5*A~
AK2*837*0002~
IK3*CLM*22**8~
CTX*CLM01>123456789~
IK4*2*782*1~
IK5*R*5~
AK2*837*0003~
IK3*REF*57**3~
CTX*SITUATIONAL TRIGGER*CLM*43**5>3~
CTX*CLM01>987654321~
IK5*R*5~
AK9*P*3*3*1~
SE*16*2870001~
GE*1*20213~
IEA*1*000010216~
```

Stedi is a registered trademark of Stedi, Inc. All names, logos, and brands of third parties listed on this page are trademarks of their respective owners (including “X12”, which is a trademark of X12 Incorporated). Stedi, Inc. and its products and services are not endorsed by, sponsored by, or affiliated with these third parties. Use of these names, logos, and brands is for identification purposes only, and does not imply any such endorsement, sponsorship, or affiliation.