Exercise 7: Producing and Consuming

AMQ7.12 has many features. We are going to work through a couple of those features, but at the end of this lab you should feel comfortable with some of the basics.

Use cases:

- Send messages to the broker
- Receive messages from the broker
- Request Reply
- Dead Letter Queue (DLQ)
- Last Value queue

Before we begin

In the previous labs we've installed and configured our broker. We eliminated the individual ports/protocols and are happy to have all protocols go through the default Acceptor at port 61616. For the remainder of this section, please verify that your broker is running and able to take connections. Each of the next sections assumes this is the case.

Send

What if you just want to quickly test whether the broker is up? Or that some configuration you changed is working as expected? What if you just want to send some sample load to the broker and don't want to build a producer/client from scratch? Luckily, Artemis comes with some tools for exploring these scenarios.

You should have your myfirstbroker running with:

```
$ ./bin/artemis run
```

This should give you a broker running in the foreground.

In a different window try running the following command:

```
$ ./bin/artemis help producer
```


This should show a help guide for how to use a simple producer to send messages to the AMQ7.12 broker.

Let's try sending messages:

```
$ ./bin/artemis producer --destination address.helloworld --message-count 100 -
-url tcp://localhost:61616
```

If we go to the Broker web console at http://localhost:8161/ we should see that we now have 100 messages in the foo queue. Remember from the first lab, we created a new address called address.helloworld and bound it as an Anycast address to the foo queue.

Note: use the credentials you set when we created the broker; admin/admin



Let's use the same tools to consume messages.

Receive

Let' use the same CLI tools to simulate consumption from addresses on the broker. Let's try to consume from the same address address.helloworld -- but let's not consume all the messages. Let's start by consuming 50 of the messages. Just like in the previous section, we want to make sure the broker is up and running and listening on port 61616. In a separate window, let's take a look at the parameters for the consumer command:

```
$ ./bin/artemis help consumer
```

Now let's try to consume 50 messages from the foo queue (remember, our Anycast address was bound to foo):


```
$ ./bin/artemis consumer --destination foo --message-count=50 --url
tcp://localhost:61616
```

You should get output similar to this:

```
Consumer:: filter = null
Consumer ActiveMQQueue[foo], thread=0 wait until 50 messages are consumed
Consumer ActiveMQQueue[foo], thread=0 Received test message: 0
.
```

```
.
Consumer ActiveMQQueue[foo], thread=0 Received test message: 39
Consumer ActiveMQQueue[foo], thread=0 Received test message: 40
Consumer ActiveMQQueue[foo], thread=0 Received test message: 41
Consumer ActiveMQQueue[foo], thread=0 Received test message: 42
Consumer ActiveMQQueue[foo], thread=0 Received test message: 43
Consumer ActiveMQQueue[foo], thread=0 Received test message: 44
Consumer ActiveMQQueue[foo], thread=0 Received test message: 45
Consumer ActiveMQQueue[foo], thread=0 Received test message: 46
Consumer ActiveMQQueue[foo], thread=0 Received test message: 47
Consumer ActiveMQQueue[foo], thread=0 Received test message: 48
Consumer ActiveMQQueue[foo], thread=0 Received test message: 48
Consumer ActiveMQQueue[foo], thread=0 Received test message: 49
```

So now if we look at our console, we should see that 50 messages are still left on our queue foo:



No go find where your broker is running and let's kill the broker. If we try to consume from the broker at this point, we should see that we cannot establish a connection. When we restart the broker, we exepct our messages to still be on the broker and available for consumption. Let's fire up the broker again:

```
$ ./bin/artemis run
```


Navigate back to the web console and verify we still have 50 messages on the queue foo.

```
Let's consume the last 50 messages:

$ ./bin/artemis consumer --destination foo --message-count=50 --url

tcp://localhost:61616
```

And we should see our queue is now empty:



Request Reply

Messaging is typically used to decouple producers and consumers in two main dimensions: time, and space. When will a consumer see messages? Who knows, but it's not the producer's responsibility. Where do the consumers even live? Again, not a detail a producer should be coupled to. However, there are use cases where producing messages/events will necessitate a response from *some* consumer downstream. You may already have usecases implemented like this using some legacy proprietary queuing system and would like a nice replacement for that legacy system but cannot change your application. However you come across a request-reply usecase here's what it looks like with JBoss AMQ7.12.

In the root of the AMQ7.12 broker installation, there is an examples folder. There are a handful of nice examples here. Navigate to:

```
$ cd $AMQ7_EXAMPLE_HOME/examples/features/standard/request-reply
```

Let's run the example. Note, just like in the previous sections, we need to have a broker running:

```
$ mvn verify -DnoServer=true
```

We should see an output like this:

```
[INFO] --- artemis-maven-plugin:2.0.0.amq-700005-redhat-1:runClient (runClient)
@ request-reply ---
Request message sent.
Received request message: A request message
Reply to queue: ActiveMQTemporaryQueue[d6677193-fef2-4fee-9f8b-d84b08eaff37]
Reply sent
Received reply: A reply message
```

So what happened here? We sent a message to a queue and got a response. But what does this look like?

If you open the Java source file in the requestreply project src/main/java//org/apache/activemq/artemis/jms/example/RequestReply Example.java we can see a little about how this happens.

First we set up the connection-factory infromation and make a connection to the broker. Then we do the following:

1. Set up the producer

For this, we create a producer to the "request queue" but we also create a temporary destination and attach a consumer to that temporary destination. This simulates the producer sending a message and also waiting for a response on the temporary destination:

```
MessageProducer producer = session.createProducer(requestQueue);
TemporaryQueue replyQueue = session.createTemporaryQueue();
MessageConsumer replyConsumer = session.createConsumer(replyQueue);
```

Next, we create our message and send it. Before we send it, however, we set a JMS property to specify where the response should be sent. It should, of course, be sent to our temporary destination like we are expecting:

```
TextMessage requestMsg = session.createTextMessage("A request message");
requestMsg.setJMSReplyTo(replyQueue);
producer.send(requestMsg);
```

We should optionally try to coordinate/correlate the response when it comes back to us. We'll save the message ID or some correlation ID that we specify:

```
requestMap.put(requestMsg.getJMSMessageID(), requestMsg);
```

1. Set up the consumer

On the consumer side, we should consume the message like normal (either using a receive method or onMessage listener) but also check the ReplyTo header. We should generate a response and send that response to the destination specified in the ReplyTo header:

```
public void onMessage(final Message request) {
         System.out.println("Received request message: " + ((TextMessage)
request).getText());
         // Extract the ReplyTo destination
         Destination replyDestination = request.getJMSReplyTo();
         System.out.println("Reply to queue: " + replyDestination);
         // Create the reply message
         TextMessage replyMessage = session.createTextMessage("A reply
message");
         // Set the CorrelationID, using message id.
         replyMessage.setJMSCorrelationID(request.getJMSMessageID());
         // Send out the reply message
         replyProducer.send(replyDestination, replyMessage);
         System.out.println("Reply sent");
      } catch (JMSException e) {
         e.printStackTrace();
```

Dead Letter Queue

What happens when a consumer cannot process a message? Or what happens when a transaction is rolled back? A JMS message in the AMQ7 broker will be redelivered (and possibly to other consumers) if a consumer is having trouble with it. The problem is, we cannot just redeliver for ever because it will starve other consumers and messages it that come later in the queue. To deal with this, we can send the non-consumable message to the "dead letter queue".

First, we'll need to configure the broker for dead-letter queue (DLQ) behavior. Let's open our myfirstbroker configuration file in etc/broker.xml and navigate to the address-settings location. We should see an entry similar to this:

This configuration sets up a "dead-letter queue" for "#" (which is all, recursive) destinations set to a value of DLQ. If you look in the web console, you'll see a queue named DLQ.

By default, the max number of retries is 10 but for this lab, we want to change it to a smaller number. Let's change it to 3 by adding a configuration <max-delivery-attempts>3</max-delivery-attempts> to our address-settings. Your config should look like this:

Now save your broker.xml file. If you had your broker running while you made the change, you should see the configuration auto-reload with a message similar to this in the broker logs:

```
15:26:47,336 INFO [org.apache.activemq.artemis.core.server] AMQ221056:
Reloading configuration ...security
15:26:47,339 INFO [org.apache.activemq.artemis.core.server] AMQ221056:
Reloading configuration ...address settings
15:26:47,340 INFO [org.apache.activemq.artemis.core.server] AMQ221056:
Reloading configuration ...diverts
15:26:47,340 INFO [org.apache.activemq.artemis.core.server] AMQ221056:
Reloading configuration ...addresses
15:26:47,351 INFO [org.apache.activemq.artemis.core.server] AMQ221003:
Deploying queue foo
15:26:47,352 INFO [org.apache.activemq.artemis.core.server] AMQ221003:
Deploying queue DLQ
15:26:47,352 INFO [org.apache.activemq.artemis.core.server] AMQ221003:
Deploying queue ExpiryQueue
```

Now, let's go to the dead-letter example from the examples that ship with the AMQ7.12 broker:

```
$ cd $AMQ7_EXAMPLE_HOME/examples/features/standard/dead-letter
```

The example will try to consume messages a few times and try rolling them back 3 times to force the message to the DLQ queue. One thing we want to change: we want to configure out example to use DLQ as the dead-letter queue. To do this, let's open the src/main/resources/jndi.properties file dn change the queue.queue/deadLetterQueue to be DLQ

Your file should look like this:

```
java.naming.factory.initial=org.apache.activemq.artemis.jndi.ActiveMQInitialCon
textFactory
connectionFactory.ConnectionFactory=tcp://localhost:61616
queue.queue/exampleQueue=exampleQueue
queue.queue/deadLetterQueue=DLQ
```

Let's run the example

```
$ mvn verify -DnoServer=true
```

We should see output like this:

```
Sent message to exampleQueue: this is a text message


1st delivery from exampleQueue: this is a text message

2nd delivery from exampleQueue: this is a text message

3rd delivery from exampleQueue: this is a text message

4th delivery from exampleQueue: null
```

If we check the DLQ queue in the web console, we can see that it now has one message in it:



Last Value queue

A last-value queue is a special kind of queue that keeps only the most recent message for a specific type of message (defined by a Last-Value property). This could be useful for stock price updates where we really only care about the most recent updates.

First, we'll need to configure the broker for last-value queue behavior for the destinations we define. We don't want all of our queues to be last-value, so we need to explicitly set up a specific queue. Let's open our myfirstbroker configuration file in etc/broker.xml and navigate to the address-settings location. We will add a configuration for a queue named exampleQueue to be a last-value queue:

We will also add a new Anycast address and bind it to a queue named exampleQueue:

Now, let's go to the last-value-queue example from the examples that ship with the AMQ7 broker:

```
$ cd $AMQ7_BASE/examples/features/standard/last-value-queue
```

Let's run the example

```
$ mvn verify -DnoServer=true
```

We should see output like this:

```
[INFO] --- artemis-maven-plugin:2.0.0.amq-700005-redhat-1:runClient (runClient) @ last-value-queue ---
Sent message: 1st message with Last-Value property set
Sent message: 2nd message with Last-Value property set
Sent message: 3rd message with Last-Value property set
Message in the queue: 3rd message with Last-Value property set
Received message: 3rd message with Last-Value property set
Received message: null
```

Let's take a closer look at what's going on.

If you open the Java source file in the last-valuequeue project src/main/java//org/apache/activemq/artemis/jms/example/LastValueQue ueExample.java we can see a little about how this happens. When we send messages to the exampleQueue queue (which was earlier configured for Last Value semantics), we are adding a JMS property named _AMQ_LVQ_NAME which is the field that the last-value queue implementation will match on:

```
TextMessage message = session.createTextMessage("1st message with
Last-Value property set");
    message.setStringProperty("_AMQ_LVQ_NAME", "STOCK_NAME");
    producer.send(message);
```

If the queue sees multiple messages with the same _AMQ_LVQ_NAME property, then it will only keep the most recent message. The example sends in three messages with the same value (_AMQ_LVQ_NAME1 equal to STOCK_NAME) and tries to consume from the exampleQueue queue. It finds only the 3rd message sent.