

Many of the slides in this lecture are either from or adapted from slides provided by the authors of the textbook "Computer Systems: A Programmer's Perspective." 2nd Edition and are provided from the website of Carnegie-Mellon University, course 15-213, taught by Randy Bryant and David O'Hallaron in Fall 2010. These slides are indicated "Supplied by CMU" in the notes section of the slides.

Number Representation

- · Hindu-Arabic numerals
 - developed by Hindus starting in 5th century
 - » positional notation
 - » symbol for 0
 - adopted and modified somewhat later by Arabs
 - » known by them as "Rakam Al-Hind" (Hindu numeral system)
 - 1999 rather than MCMXCIX
 - » (try doing long division with Roman numerals!)

CS33 Intro to Computer Systems

VII-2

Which Base? 1999 base 10 9·10°+9·10¹+9·10²+1·10³ base 2 11111001111 1·2°+1·2¹+1·2²+1·2³+0·2⁴+0+2⁵+1·2⁶+1·2⁻+1·2⁶+1·2⁵+1·2⁰+1·2¹⁰ base 8 3717 7·8°+1·8¹+7·8²+3·8³

Base 2 is known as "binary" notation.

Base 8 is known as "octal" notation.

Base 10 is known as "decimal" notation.

base 167CF


CS33 Intro to Computer Systems

» why are we interested?

• 15·16⁰+12·16¹+7·16² » why are we interested?

Base 16 is known as "hexadecimal" notation. Note that "hexa" is derived from the Greek language and "decimal" is derived from the Latin language. Many people feel you shouldn't mix languages when you invent words, but IBM, who coined the term "hexadecimal" in the 1960s, didn't think their corporate image could withstand "sexadecimal".

VII-3



Note that a byte consists of two hexadecimal digits, which are sometimes known as "nibbles". A 32-bit computer word would then have eight nibbles; a 64-bit computer word would have sixteen nibbles.

```
Void baseX(unsigned int num, unsigned int base) {
   char digits[] = {'0', '1', '2', '3', '4', '5', '6', ... };
   char buf[8*sizeof(unsigned int)+1];
   int i;

for (i = sizeof(buf) - 2; i >= 0; i--) {
    buf[i] = digits[num%base];
    num /= base;
   if (num == 0)
        break;
   }

buf[sizeof(buf) - 1] = '\0';
   printf("%s\n", &buf[i]);
}
CS33 Intro to Computer Systems

VII-5 Copyright © 2015 Thomas W. Doeppner. All rights reserved.
```

This routine prints the base base representation of *num*. (Note that the "..." is not heretofore unexplained C syntax, but is shorthand for "fill this in to the extent needed.")

```
Or ...

$ bc
obase=16
1999
7CF
$

CS33 Intro to Computer Systems

VII-6 Copyright © 2015 Thomas W. Doeppner. All rights reserved.
```

"bc" (it stands for basic calculator, or perhaps better calculator) is a standard Unix command that handles arbitrary-precision arithmetic. Among its features is the ability to specify which base to use for input and output of numbers. The default base for both input and output is ten. Setting *obase* to 16 sets the base for output to 16. Similarly, one can change the base for input numbers by setting *ibase*.

Quiz 1

- What's the decimal (base 10) equivalent of 23₁₆?
 a) 19

 - b) 33
 - c) 35
 - d) 37

CS33 Intro to Computer Systems

VII-7

Encoding Byte Values

- Byte = 8 bits
 - binary 000000002 to 111111112
 - decimal: 0₁₀ to 255₁₀
 - hexadecimal 00₁₆ to FF₁₆
 - » base 16 number representation
 - » use characters '0' to '9' and 'A' to 'F'
 - » write FA1D37B₁₆ in C as
 - 0xFA1D37B
 - 0xfa1d37b

He	t De	eimal Binary
0	0	0000
1	1	0001
2	2	0010
3	3	0011
4	4	0100
<u>4</u> 5	5	0101
6	6	0110
7	7	0111
8	8	1000
9	9	1001
Α	10	1010
В	11	1011
С	12	1100
D	13	1101
Ε	14	1110
F	15	1111

CS33 Intro to Computer Systems

VII–8

Boolean Algebra • Developed by George Boole in 19th Century - algebraic representation of logic » encode "true" as 1 and "false" as 0 And Or • A&B = 1 when both A=1 and B=1 - A | B = 1 when either A=1 or B=1 - A | B = 1 when either A=1 or B=1 - A | D | D | D | D | 1 | D | D | D | Not Exclusive-Or (Xor) • ~A = 1 when A=0 • A^B = 1 when either A=1 or B=1, but not both - A | D | D | 1 | D | D | 1 | D | D | CS33 Intro to Computer Systems

General Boolean Algebras

- Operate on bit vectors
 - operations applied bitwise

```
01101001 01101001 01101001

& 01010101 | 01010101 ^ 01010101 ~ 01010101

01000001 01111101 00111100 10101010
```

· All of the properties of boolean algebra apply

CS33 Intro to Computer Systems

VII-10

Example: Representing & Manipulating Sets

```
    Representation

          – width-w bit vector represents subsets of {0, ..., w–1}
          -a_i = 1 \text{ iff } j \in A
               01101001
                                 { 0, 3, 5, 6 }
               76543210
               01010101
                                 { 0, 2, 4, 6 }
                76543210

    Operations

                                          01000001
                                                            {0,6}
          & intersection
               union
                                          01111101
                                                            { 0, 2, 3, 4, 5, 6 }
              symmetric difference
                                          00111100
                                                            { 2, 3, 4, 5 }
               complement
                                          10101010
                                                            { 1, 3, 5, 7 }
CS33 Intro to Computer Systems
                                      VII-11
```

Bit-Level Operations in C

```
• Operations &, I, ~, ^ available in C
  - apply to any "integral" data type
     » long, int, short, char
  - view arguments as bit vectors
  - arguments applied bit-wise

    Examples (char datatype)
```

```
\sim 0x41 \rightarrow 0xBE
    \sim 01000001_2 \rightarrow 10111110_2
\sim 0 \times 000 \rightarrow 0 \times FF
    \sim 0000000002 \rightarrow 1111111112
0x69 \& 0x55 \rightarrow 0x41
    01101001_2 \& 01010101_2 \rightarrow 01000001_2
0x69 \mid 0x55 \rightarrow 0x7D
    01101001_2 \mid 01010101_2 \rightarrow 01111101_2
```

CS33 Intro to Computer Systems

VII-12

Contrast: Logic Operations in C

```
    Contrast to Logical Operators
```


```
- & &, ||, !
  » view 0 as "false"
  » anything nonzero as "true"
  » always return 0 or 1
  » early termination/short-circuited execution
```

Examples (char datatype)

```
!0x41 \rightarrow 0x00
!0x00 \rightarrow 0x01
!!0x41 \rightarrow 0x01
0x69 \&\& 0x55 \rightarrow 0x01
0x69 \mid \mid 0x55 \rightarrow 0x01
p && *p
                 (avoids null pointer access)
```

CS33 Intro to Computer Systems

VII-13



Shift Operations • Left Shift: x << y - shift bit-vector x left y positions • throw away extra bits on left

- » fill with 0's on right• Right Shift: X >> y
 - shift bit-vector x right y positions
 - » throw away extra bits on right
 - logical shift
 - » fill with 0's on left
 - arithmetic shift
 - » replicate most significant bit on left
- Undefined Behavior
 - shift amount < 0 or ≥ word size

Argument x	01100010
<< 3	00010000
Log. >> 2	00011000
Arith. >> 2	00011000

Argument x	10100010
<< 3	00010000
Log. >> 2	00101000
Arith. >> 2	11101000

CS33 Intro to	Computer	Systems
---------------	----------	---------

VII-15

The distinction between logical and arithmetic shifts should be clear by the end of this lecture.

Signed Integers

· Sign-magnitude




value =
$$(-1)^{b_{W-1}} \cdot \sum_{i=0}^{w-2} b_i \cdot 2^i$$

· two representations of zero!

CS33 Intro to Computer Systems

VII-16



Note that the most-significant bit serves as the sign bit.

Signed Integers

Two's complement

 $b_{w-1} = 0 \Rightarrow$ non-negative number

$$value = \sum_{i=0}^{w-2} b_i \cdot 2^i$$

 $b_{w-1} = 1 \Rightarrow negative number$

value =
$$(-1) \cdot 2^{w-1} + \sum_{i=0}^{w-2} b_i \cdot 2^i$$

CS33 Intro to Computer Systems

VII-18

Copyright © 2015 Thomas W. Doeppner. All rights reserved.

Note there's only one zero!

Two's complement is used on pretty much all of today's computers to represent signed integers.

Signed Integers


• Negating two's complement

$$value = -b_{w-1}2^{w-1} + \sum_{i=0}^{w-2} b_i 2^i$$

– how to compute –value? (~value)+1

CS33 Intro to Computer Systems

VII-19



If we add to the two's complement representation of a w-bit number the result of adding one to its bitwise complement, we get a w+1-bit number whose low-order w bits are zeroes and whose high-order bit is one. However, since we're constrained to only w bits, the result is a w-bit value of all zeroes, plus an overflow. If we ignore the overflow, the result is zero.

Quiz 2

- We have a computer with 4-bit words that uses two's complement to represent negative numbers. What is the result of subtracting 0010 (2) from 0001 (1)?
 - a) 0111
 - b) 1001
 - c) 1110
 - d) 1111

CS33 Intro to Computer Systems

VII-21



Unsigned Values

$$-UMin = 0$$

 $000...0$
 $-UMax = 2^{w} - 1$
 $111...1$

• Two's Complement Values

$$- TMin = -2^{w-1}
100...0
- TMax = 2^{w-1} - 1
011...1$$

Other Values

Values for W = 16

	Decimal	Hex	Binary
UMax	65535	FF FF	11111111 11111111
TMax	32767	7F FF	01111111 11111111
TMin	-32768	80 00	10000000 00000000
-1	-1	FF FF	11111111 11111111
0	0	00 00	00000000 00000000

CS33 Intro to Computer Systems

VII-22

Values for Different Word Sizes

		W		
	8	16	32	64
UMax	255	65,535	4,294,967,295	18,446,744,073,709,551,615
TMax	127	32,767	2,147,483,647	9,223,372,036,854,775,807
TMin	-128	-32,768	-2,147,483,648	-9,223,372,036,854,775,808

Observations

C Programming

- #include imits.h>
- declares constants, e.g.,
 - ULONG_MAX
 - LONG_MAX
 - LONG_MIN
- values platform-specific

CS33 Intro to Computer Systems


VII-23

Quiz 3

- What is –TMin (assuming two's complement signed integers)?
 - a) TMin
 - b) TMax
 - c) 0
 - d) 1

CS33 Intro to Computer Systems

VII-24



Unsigned computer arithmetic is performed modulo 2 to the power of the computer's word size. The outer ring of the figure demonstrates arithmetic modulo 2^4 . To see the result, for example, of adding 3 to 2, start at 2 and go around the ring three units in the clockwise direction. If we add 5 to 14, we start at 14 and move 5 units clockwise, to 3. Similarly, to subtract 3 from 1, we start at one and move three units counterclockwise to 14.

What about two's-complement computer arithmetic? We know that the values encoded in a 4-bit computer word range from -8 to 7. How do we arrange them in the ring? As shown in the second ring, it makes sense for the non-negative numbers to be in the same positions as the corresponding unsigned values. It clearly makes sense for the integer coming just before 0 to be -1, the integer just before -1 to be -2, etc. Thus, since we have a ring, the integer following 7 is -8. Now we can see how arithmetic works for two's-complement numbers. Adding 3 to 2 works just as it does for unsigned numbers. Subtracting 3 from 1 results in -2. But adding 3 to 6 results in -7; and adding 5 to -2 results in 3.

The innermost ring shows the bit encodings for the unsigned and two's-complement values. The point of all this is that, with only one implementation of arithmetic, we can handle both unsigned and two's-complement values. Thus adding unsigned 5 and 9 is equivalent to adding two's-complement 5 and -7. The result will 1110, which, if interpreted as an unsigned value is 14, but if interpreted as a two's-complement value is -2.

Signed vs. Unsigned in C

- Constants
 - by default are considered to be signed integers
 - unsigned if have "U" as suffix

```
OU, 4294967259U
```

- Casting
 - explicit casting between signed & unsigned

```
int tx, ty;
unsigned int ux, uy; // "unsigned" means "unsigned int"
tx = (int) ux;
uy = (unsigned int) ty;
```

- implicit casting also occurs via assignments and procedure calls

```
tx = ux;
uy = ty;
```

CS33 Intro to Computer Systems


VII-26

Casting Surprises Expression evaluation - if there is a mix of unsigned and signed in single expression, signed values implicitly cast to unsigned - including comparison operations <, >, ==, <=, >= - examples for W = 32: TMIN = -2,147,483,648, TMAX = 2,147,483,647 Constant₁ Constant₂ Relation **Evaluation** unsigned == 0 0U < signed -1 0 unsigned > -1 0U signed > 2147483647 -2147483647-1 < unsigned 2147483647U -2147483647-1 > signed -1 -2 > unsigned -2 (unsigned)-1 unsigned < 2147483647 2147483648U signed 2147483647 (int) 2147483648U

VII-27

Supplied by CMU.

CS33 Intro to Computer Systems



Sign Extension Example

```
short int x = 15213;
int         ix = (int) x;
short int y = -15213;
int         iy = (int) y;
```

	Decimal	Hex	Binary
x	15213	3B 6D	00111011 01101101
ix	15213	00 00 3B 6D	00000000 00000000 00111011 01101101
У	-15213	C4 93	11000100 10010011
iy	-15213	FF FF C4 93	1111111 11111111 11000100 10010011

- · Converting from smaller to larger integer data type
 - C automatically performs sign extension

CS33 Intro to Computer Systems

VII-29

Does it Work?

$$\begin{aligned} val_w &= -2^{w-1} + \sum_{i=0}^{w-2} b_i \cdot 2^i \\ val_{w+1} &= -2^w + 2^{w-1} + \sum_{i=0}^{w-2} b_i \cdot 2^i \\ &= -2^{w-1} + \sum_{i=0}^{w-2} b_i \cdot 2^i \\ val_{w+2} &= -2^{w+1} + 2^w + 2^{w-1} + \sum_{i=0}^{w-2} b_i \cdot 2^i \\ &= -2^w + 2^{w-1} + \sum_{i=0}^{w-2} b_i \cdot 2^i \\ &= -2^{w-1} + \sum_{i=0}^{w-2} b_i \cdot 2^i \end{aligned}$$


CS33 Intro to Computer Systems


VII-30


Copyright © 2015 Thomas W. Doeppner. All rights reserved.


Sign extension clearly works for positive and zero values (where the sign bit is zero). But does it work for negative values? The first line of the slide shows the computation of the value of a w-bit item with a sign bit of one (i.e., it's negative). The next two lines show what happens if we extend this to a w+1-bit item, extending the sign bit. What had been the sign bit becomes one of the value bits, and its contribution to the value is now positive rather than negative. But this is compensated by the new sign bit, whose contribution is a negative value, twice as large as the original sign bit. Thus the net effect is for there to be no change in the value.


We do this again, extending to a w+2-bit item, and again, the resulting value is the same as what we started with.











Why Should I Use Unsigned?

- · Don't use just because number nonnegative
 - easy to make mistakes

```
unsigned i;
for (i = cnt-2; i >= 0; i--)
  a[i] += a[i+1];
```

- can be very subtle

```
#define DELTA sizeof(int)
int i;
for (i = CNT; i-DELTA >= 0; i-= DELTA)
```

- · Do use when performing modular arithmetic
 - multiprecision arithmetic
- · Do use when using bits to represent sets
 - logical right shift, no sign extension


CS33 Intro to Computer Systems

VII-36

Supplied by CMU.

Note that "sizeof" returns an unsigned value. (Recall that, when mixing signed and unsigned items in an expression, the result will be unsigned.)

Byte-Oriented Memory Organization



- · Programs refer to data by address
 - conceptually, envision it as a very large array of bytes
 - » in reality, it's not, but can think of it that way
 - an address is like an index into that array
 - » and, a pointer variable stores an address
- Note: system provides private address spaces to each "process"
 - think of a process as a program being executed
 - so, a program can clobber its own data, but not that of others

CS33 Intro to Computer Systems


VII-37

Machine Words

- Any given computer has a "word size"
 - nominal size of integer-valued data
 - » and of addresses
 - until recently, most machines used 32 bits (4 bytes) as word size
 - » limits addresses to 4GB (232 bytes)
 - » become too small for memory-intensive applications
 - leading to emergence of computers with 64-bit word size
 - machines still support multiple data formats
 - » fractions or multiples of word size
 - » always integral number of bytes

CS33 Intro to Computer Systems


VII-38





- Four-byte integer
 - 0x7654321
- Stored at location 0x100
 - which byte is at 0x100?
 - which byte is at 0x103?

?



Little-endian




Big-endian



0x100 0x101 0x102 0x103

CS33 Intro to Computer Systems

VII-40



Here we have a four-byte integer one. In the big-endian representation, the address of the integer is the address of the byte containing its most-significant bits (the big end), while in the little-endian representation, the address of the integer is the address of the byte containing its least-significant bits (the little end). Suppose we pass a pointer to this integer to some procedure. However, in a type-mismatch, the procedure assumes that what is passed it is a two-byte integer. On a big-endian system, it would think it was passed a zero, but on a little-endian system, it would think it was passed a one.

This is not an argument in favor of either approach, but simply an observation that behaviors could be different.

Quiz 4

```
int main() {
  long x=1;
  proc(x);
  return 0;
}

void proc(int arg) {
  printf("%d\n", arg);
}
```

What value is printed on a big-endian 64-bit computer?

- a) 0
- b) 1
- c) 2^{32}
- d) 2³²-1

CS33 Intro to Computer Systems

VII-42